

# VMCI Sockets Programming Guide

VMware Workstation 6.5 and VMware Server 2.0

VMCI Sockets Programming Guide

Item: EN-000054-00

You can find the most up-to-date technical documentation on our Web site at:

<http://www.vmware.com/support/>

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

[docfeedback@vmware.com](mailto:docfeedback@vmware.com)

© 2008 VMware, Inc. All rights reserved. Protected by one or more U.S. Patent Nos. 6,397,242, 6,496,847, 6,704,925, 6,711,672, 6,725,289, 6,735,601, 6,785,886, 6,789,156, 6,795,966, 6,880,022, 6,944,699, 6,961,806, 6,961,941, 7,069,413, 7,082,598, 7,089,377, 7,111,086, 7,111,145, 7,117,481, 7,149,843, 7,155,558, 7,222,221, 7,260,815, 7,260,820, 7,269,683, 7,275,136, 7,277,998, 7,277,999, 7,278,030, 7,281,102, 7,290,253, 7,356,679, 7,409,487, 7,412,492, 7,412,702, 7,424,710, and 7,428, 636; patents pending.

VMware, the VMware “boxes” logo and design, Virtual SMP and VMotion are registered trademarks or trademarks of VMware, Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

**VMware, Inc.**

3401 Hillview Ave.  
Palo Alto, CA 94304  
[www.vmware.com](http://www.vmware.com)

# Contents

About This Book	5
<b>1 About VMCI Sockets</b>	<b>7</b>
Introducing VMCI Sockets	7
How VMCI Sockets Work	7
Possible Use Cases	8
Performance	8
Persistence of Sockets	8
Socket Programming	8
Features in Specific Releases	8
Location of Include File	9
Web Access with Stream VMCI Sockets	9
Network Storage with Datagram VMCI Sockets	10
<b>2 Porting to VMCI Sockets</b>	<b>11</b>
Porting Existing Socket Applications	11
Include a New Header File	11
Change AF_INET to VMCI Sockets	11
Obtain the CID	11
The VMCISock_GetLocalCID() Function	11
Connection-Oriented Stream Socket	12
Connectionless Datagram Socket	12
Initializing the Address Structure	12
Communicating Between Guests	12
VMCI Sockets and Networking	12
Setting up a Networkless Guest	12
Communicating Between Guest and Host	12
<b>3 Creating Stream VMCI Sockets</b>	<b>13</b>
Stream VMCI Sockets	13
Preparing the Server for a Connection	14
Socket() Function	14
Set and Get Socket Options	14
Bind() Function	15
Listen() Function	15
Accept() Function	15
Select() Function	15
Recv() Function	16
Send() Function	16
Close() Function	16
Poll() Information	16
Read() and Write()	16
Getsockname() Function	16
Having the Client Request a Connection	17
Socket() Function	17
Connect() Function	17
Send() Function	17
Recv() Function	18

Close() Function	18	
Poll() Information	18	
Read() and Write()	18	
<b>4</b>	<b>Creating Datagram VMCI Sockets</b>	<b>19</b>
Datagram VMCI Sockets	19	
Preparing the Server for a Connection	20	
Socket() Function	20	
Socket Options	20	
Bind() Function	20	
Getsockname() Function	21	
Recvfrom() Function	21	
Sendto() Function	21	
Close() Function	21	
Having the Client Request a Connection	21	
Socket() Function	21	
Sendto() Function	22	
Connect() and Send()	22	
Recvfrom() Function	22	
Close() Function	22	
<b>A</b>	<b>Learning More About Sockets</b>	<b>23</b>
About Berkeley Sockets and Winsock	23	
Resources on the Web	23	
Wikipedia	23	
Sockaddr	23	
MSDN	23	
Linux Manual Pages	24	
Hardcopy Books	24	
	<b>Glossary</b>	<b>25</b>
	<b>Index</b>	<b>27</b>

# About This Book

---

The VMware® *VMCI Sockets Programming Guide* describes how to program virtual machine communications interface (VMCI) sockets, an API that facilitates fast and efficient communication between virtual machines.

## Revision History

VMware revises this guide with each release of the product or when necessary. A revised version can contain minor or major changes. [Table 1](#) summarizes the significant changes in each version of this guide.

**Table 1.** Revision History

Revision	Description
20080327	First draft of this manual for possible inclusion in early beta releases.
20080620	Second draft for VMware Workstation 6.5 Beta 2 and VMware Server 2.0 RC1 releases.
20080815	Third draft, with socket options, for VMware Workstation 6.5 RC release.

## Intended Audience

This guide is intended for programmers who are developing applications with VMCI sockets to create C or C++ networking applications that target guest operating systems on VMware hosts, or virtual machine communications. VMCI sockets are based on TCP sockets. Chapters in this guide assumes that you are familiar with either Berkeley sockets or Winsock, the Windows implementation. If you are not familiar with sockets, [Appendix A](#) provides pointers to learning resources.

## Documentation Resources

To access the current versions of VMware API and SDK documentation, go to:

[http://www.vmware.com/support/pubs/sdk\\_pubs.html](http://www.vmware.com/support/pubs/sdk_pubs.html)

To access the current versions of other VMware manuals, go to:

<http://www.vmware.com/support/pubs>

## Documentation Feedback

VMware welcomes your suggestions for improving our documentation. Send your feedback to:

[docfeedback@vmware.com](mailto:docfeedback@vmware.com)

## Technical Support and Education Resources

The following sections describe the technical support and educational resources available to you.

### Online Support

You can submit questions or post comments to the Developer Community SDKs and APIs forum, which is monitored by VMware technical support and product teams. To access the forum, go to:

<http://communities.vmware.com/community/developer>

### Support Offerings

To find out how VMware support offerings can help meet your business needs, go to:

<http://www.vmware.com/support/services>

### VMware Professional Services

VMware Education Services courses offer extensive hands-on labs, case study examples, and course materials designed to be used as on-the-job reference tools. Courses are available onsite, in the classroom, and live online. For onsite pilot programs and implementation best practices, VMware Consulting Services provides offerings to help you assess, plan, build, and manage your virtual environment. To access information about education classes, certification programs, and consulting services, go to:

<http://www.vmware.com/services/>

# About VMCI Sockets

---

This chapter introduces VMCI sockets, discusses release-specific features, and illustrates several use cases. Topics include:

- [“Introducing VMCI Sockets”](#) on page 7
- [“Features in Specific Releases”](#) on page 8
- [“Web Access with Stream VMCI Sockets”](#) on page 9
- [“Network Storage with Datagram VMCI Sockets”](#) on page 10

This guide assumes that you know about either Berkeley sockets or Winsock, the Windows implementation. If you are new to sockets, see [Appendix A, “Learning More About Sockets,”](#) on page 23.

## Introducing VMCI Sockets

The VMware VMCI sockets library offers an API that is similar to the Berkeley UNIX socket interface and the Windows socket interface, two industry standards. VMCI sockets support fast and efficient communication between a virtual machine and its host, or between guest virtual machines on the same host.

---

**NOTE** The original VMCI library was released as an experimental C language interface with Workstation 6.0. It included a datagram API and a shared memory API. Both these interfaces have been deprecated.

---

In this release, the new library has more flexible algorithms, wrapped in a stream sockets interface for external presentation. VMCI sockets is a fully supported interface, not experimental.

## How VMCI Sockets Work

VMCI sockets are similar to other socket types. Like UNIX (local) sockets, VMCI sockets work on an individual physical machine, and like UNIX sockets, they can perform interprocess communication on the local system. By contrast with Internet sockets, communicating processes usually reside on different systems across the network. Like Internet sockets, VMCI sockets allow different virtual machines to communicate with each other, provided they reside on the same VMware host.

The VMCI sockets library supports both connection-oriented stream sockets like TCP, and connectionless datagram sockets like UDP.

VMCI sockets support data transfer among processes on the same system (interprocess communication). They also allow communication among processes on different systems, even ones running different versions and types of operating systems. In one protocol family, VMCI sockets combine the best aspects of interprocess communication with the advantages of networking in a hosted virtual environment.

In VMCI sockets, a virtual socket can have only two endpoints and the server cannot initiate a connection to the client, unlike TCP sockets.

Sockets require active processes, so communicating guest virtual machines must be running, not powered off.

## Possible Use Cases

VMCI sockets offer the following:

- Improved intra-host performance for socket-modified applications
- Choice of stream or datagram communication for off-the-network virtual machines
- Improved privacy of communications for hosted virtual machines
- Alternate data path for administrative control of guest virtual machines
- Improved efficiency for database-backed applications going guest-to-guest for data
- Ability to implement a host-guest file system

## Performance

Early performance testing indicates that VMCI sockets have low latency and high throughput. Socket endpoints communicate with each other at, or close to, the speed of memory.

Because communication is on a single physical system, VMCI sockets can attain performance comparable to UNIX sockets, even though they enable communication across virtual machines like Internet sockets do.

VMware tailored its VMCI sockets implementation for high performance, especially with large data sets. VMware recommends message sizes larger than 512 bytes to fully realize the performance benefits. VMCI sockets have higher performance on an individual physical machine than over-the-wire network sockets.

## Persistence of Sockets

VMCI sockets connections are dropped after suspend and resume of a virtual machine.

Connections cannot survive live migration with VMotion from source to destination host.

## Socket Programming

If you have existing socket-based applications, you need to make only a few code changes for VMCI sockets. If you do not have socket-based applications, you can easily find public-domain code on the Web. For example, Apache and Firefox, as shown in [Figure 1-1, “VMware Hosts with Stream VMCI Sockets in Guests,”](#) on page 9, use stream sockets and are open-source.

Repurposing any networking program to use VMCI sockets requires minimal effort, because VMCI sockets behave like traditional Internet sockets on a given platform. However, some socket options do not make sense for communication across the VMCI device; such options are silently ignored to ease program portability.

Modification is straightforward, as described in section [“Porting Existing Socket Applications”](#) on page 11. You include a new header file. Before the `socket()` call, you call the `VMCISock_GetAFValue()` function to return the VMCI sockets address family to replace `AF_INET`. You allocate a replacement socket addressing structure, `sockaddr_vm` instead of `sockaddr_in`. Otherwise VMCI sockets use the same API as Berkeley sockets or Windows sockets.

## Features in Specific Releases

VMCI sockets communicate from guest to guest, or guest to host, on one VMware host. They can also be used for interprocess communications on a single guest. However, you cannot use VMCI sockets between virtual machines running on two separate physical machines, or from one host to another host across a network.

In the VMware Server 2.0 and VMware Workstation 6.5 releases, stream sockets are not supported between host and guest, so you must use datagram sockets instead. Stream sockets work from guest to guest only. Datagram sockets work from guest to guest, host to guest, and guest to host.

As of the VMware Server 2.0 RC2 and VMware Workstation 6.5 RC releases, you can set the minimum, maximum, and default size of communicating stream buffers. See [“Set and Get Socket Options”](#) on page 14.

### Location of Include File

You can find the `vmci_sockets.h` include file in the following places:


- Windows guest – `C:\Program Files\VMware\VMware Tools\Vsock SDK\include`
- Linux guest – `/usr/lib/vmware-tools/include/vmci/`
- Windows host – `C:\Program Files\VMware\VMware Workstation`
- Linux host – Not installed on the system.

### Web Access with Stream VMCI Sockets

Figure 1-1 shows an example of two VMware Workstation hosts, one Windows based and the other Linux based. On each host, modified Firefox browsers on Windows and Linux virtual machines are communicating with a modified Apache server on a separate virtual machine through VMCI sockets. Meanwhile, a Web browser on each host is communicating with a Web server on the other host using standard networking through TCP/IP sockets.

VMware does not provide modified versions of any third-party applications shown here. However, open-source versions of Firefox and Apache are available, so VMCI sockets modification is feasible.

Figure 1-1. VMware Hosts with Stream VMCI Sockets in Guests



When the Firefox browsers on Linux and Windows request a connection to the Apache Web server, the VMCI sockets layer creates a socket endpoint and establishes a connection through the VMCI driver and virtual device. The VMCI sockets layer on the system with Apache receives the connection and provides an accepted socket through the socket on which Apache was listening.


Meanwhile, unmodified Web browsers on the physical machines (Windows host and Linux host) are sending requests to each other's Web servers over a standard TCP/IP network connection. If guest operating systems needed to access the Web outside the physical machine, they would have to use different (unmodified) Web browsers, or have a fallback capability outside of VMCI sockets.

## Network Storage with Datagram VMCI Sockets

Figure 1-2 shows an example of a VMware host acting as the NFS server for the home directories of its three clients: a Windows guest and two Linux guests. NFS uses datagram sockets for file I/O. The NFS code on the VMware host must be slightly modified to use VMCI sockets instead of UDP datagrams.

VMware does not provide modified versions of any third-party applications shown here. However, an open-source version of NFS is available, so VMCI sockets modification is feasible.

**Figure 1-2.** VMware Host with Datagram VMCI Sockets for NFS in Guests



Programmers use stream sockets for their high reliability, and datagram sockets for speed and low overhead.

## Porting to VMCI Sockets

---

This chapter summarizes how to port existing socket applications to VMCI sockets. Topics include:

- [“Porting Existing Socket Applications”](#) on page 11
- [“Communicating Between Guests”](#) on page 12
- [“Communicating Between Guest and Host”](#) on page 12

### Porting Existing Socket Applications

Modifying existing socket implementations is straightforward. This chapter describes the lines of code you need to change.

#### Include a New Header File

To obtain the definitions for VMCI sockets, include the `vmci_sockets.h` header file.

```
#include "vmci_sockets.h"
```

#### Change AF\_INET to VMCI Sockets

Call `VMCISock_GetAFValue()` to obtain the VMCI address family. Declare structure `sockaddr_vm` instead of `sockaddr_in`. In the `socket()` call, replace the `AF_INET` address family with the VMCI address family.

When the client creates a connection, instead of providing an IP address to choose its server, the client must provide the context ID (CID) of a virtual machine.

#### Obtain the CID

In virtual hardware version 6 (Workstation 6.0.x releases), the VMCI virtual device is not present by default. After you upgrade a virtual machine’s virtual hardware to version 7, the following line appears in the `.vmx` configuration file, and when the virtual machine powers on, a new `vmci0.id` line also appears there.

```
vmci0.present = "TRUE"
```

In virtual hardware version 7 (Workstation 6.5 releases), the VMCI virtual device is present by default. When you create a new virtual machine, the `.vmx` configuration file contains lines specifying PCI slot number and the ID of the VMCI device. On the `vmci0.id` line, CID is the number in double quotes.

```
vmci0.pciSlotNumber = "36"  
vmci0.id = "1066538581"
```

#### The `VMCISock_GetLocalCID()` Function

For convenience, you can call the `VMCISock_GetLocalCID()` function to obtain the local system’s CID. This function works on both host server and guest virtual machines.

The VMware host usually has CID = 2.

## Connection-Oriented Stream Socket

To establish a stream socket, include these declarations and calls, and replace `AF_INET` with `afVMCI`, as set by `VMCISock_GetAFValue()`.

```
int sockfd_stream;
int afVMCI = VMCISock_GetAFValue();
if ((sockfd_stream = socket(afVMCI, SOCK_STREAM, 0)) == -1) {
    perror("Socket stream");
}
```

## Connectionless Datagram Socket

To establish a datagram socket, include these declarations and calls:

```
int sockfd_dgram;
int afVMCI = VMCISock_GetAFValue();
if ((sockfd_dgram = socket(afVMCI, SOCK_DGRAM, 0)) == -1) {
    perror("Socket datagram");
}
```

## Initializing the Address Structure

To initialize the address structure passed to `bind()`, insert these source code statements, where `sockaddr_vm` for VMCI sockets replaces `sockaddr_in` for network sockets.

```
struct sockaddr_vm my_addr = {0};
my_addr.svm_family = afVMCI;
my_addr.svm_cid = VMADDR_CID_ANY;
my_addr.svm_port = VMADDR_PORT_ANY;
```

The first line declares `my_addr` as a `sockaddr_vm` structure and initializes it with zeroes. `AF_INET` replaces `afVMCI`. Both `VMADDR_CID_ANY` and `VMADDR_PORT_ANY` are predefined so that at runtime, the server can fill in the appropriate CID and port values during a bind operation. The initiating side of the connection, the client, must provide the CID and port, instead of `VMADDR_CID_ANY` and `VMADDR_PORT_ANY`.

## Communicating Between Guests

To communicate between two guest virtual machines on the same host, you can establish a VMCI sockets connection using either the `SOCK_STREAM` or the `SOCK_DGRAM` socket type.

### VMCI Sockets and Networking

If limited network access is sufficient for a virtual machine, you could replace TCP networking with VMCI sockets, thereby saving memory and processor bandwidth by disabling the network stack. If networking is enabled, as it typically is, VMCI sockets can still make some operations run faster.

### Setting up a Networkless Guest

You can install a virtual machine without any networking packages, so it cannot connect to the network. The system image of a network-free operating system is likely to be small, and isolation is a security advantage, at the expense of convenience. Install network-free systems as a networkless guest. After you upgrade VMware Tools, you can use VMCI sockets to communicate with the networkless guest.

You create a networkless guest with the option "Do not use a network connection" in Workstation wizard. Alternatively, you can transform a network-capable guest into a networkless guest by removing all its virtual networking devices in the Workstation UI.

## Communicating Between Guest and Host

To communicate between a guest virtual machine and the host, you can establish a VMCI sockets connection using the `SOCK_DGRAM` socket type.

## Creating Stream VMCI Sockets


This chapter describes the details of creating VMCI sockets to replace TCP stream sockets, in two sections:

- “Preparing the Server for a Connection” on page 14
- “Having the Client Request a Connection” on page 17

### Stream VMCI Sockets

The flowchart in [Figure 3-1](#) shows how to establish connection-oriented sockets on the server and client.

**Figure 3-1.** Connection-Oriented Stream Sockets



With VMCI sockets and TCP sockets, the server waits for the client to establish a connection. After connecting, the server and client communicate through the attached socket. In VMCI sockets, a virtual socket can have only two endpoints, and the server cannot initiate a connection to the client. In TCP sockets, more than two endpoints are possible, though rare, and the server can initiate connections. Otherwise, the protocols are identical.

## Preparing the Server for a Connection

At the top of your application, include `vmci_sockets.h` and declare a constant for the socket buffer size. In the example below, `BUFSIZE` defines the socket buffer size. The number 4096 is a good choice for efficiency on multiple platforms. It is not based on the size of a TCP packet, which is usually smaller.

```
#include "vmci_sockets.h"
#define BUFSIZE 4096
```

To compile on Windows, you must also call the Winsock `WSAStartup()` function.

```
err = WSAStartup(versionRequested, &wsaData);
if (err != 0) {
    printf(stderr, "Could not register with Winsock DLL.\n");
    goto cleanup;
}
```

This is not necessary on non-Windows systems.

## Socket() Function

In a VMCI sockets application, obtain the new address family (domain) to replace `AF_INET`.

```
int afVMCI = VMCI_Sock_GetAFValue();
if ((sockfd = socket(afVMCI, SOCK_STREAM, 0)) == -1) {
    perror("socket");
    goto cleanup;
}
```

`VMCI_Sock_GetAFValue()` returns a descriptor for the VMCI sockets address family if available.

## Set and Get Socket Options

VMCI sockets allows you to set the minimum, maximum, and default size of communicating stream buffers. Names for the three options are:

- `SO_VMCI_BUFFER_SIZE` – Default size of communicating buffers; 65536 bytes if not set.
- `SO_VMCI_BUFFER_MIN_SIZE` – Minimum size of communicating buffers; defaults to 128 bytes.
- `SO_VMCI_BUFFER_MAX_SIZE` – Maximum size of communicating buffers; defaults to 262144 bytes.

To set a new value for a socket option, call the `setsockopt()` function. To get a value, call `getsockopt()`.

For example, to halve the size of the communications buffers from 65536 to 32768, and verify that the setting took effect, insert the following code:

```
uint64 setBuf = 32768, getBuf;
/* reduce buffer to above size and check */
if (setsockopt(sockfd, afVMCI, SO_VMCI_BUFFER_SIZE, (void *)&setBuf, sizeof setBuf) == -1) {
    perror("setsockopt");
    goto close;
}
if (getsockopt(sockfd, afVMCI, SO_VMCI_BUFFER_SIZE, (void *)&getBuf, sizeof getBuf) == -1) {
    perror("getsockopt");
    goto close;
}
if (getBuf != setBuf) {
    printf(stderr, "SO_VMCI_BUFFER_SIZE not set to size requested.\n");
    goto close;
}
```

Parameters `setBuf` and `getBuf` must be declared 64 bit, even on 32-bit systems.

To have an effect, socket options must be set before establishing a connection. The buffer size is negotiated before the connection is established and stays consistent until the connection is closed. For a server socket, set options before any client establishes a connection. To be sure that this applies to all sockets, set options before calling `listen()`. For a client socket, set options before calling `connect()`.

## Bind() Function

This `bind()` call associates the stream socket with the network settings in the `sockaddr_vm` structure, instead of the `sockaddr_in` structure.

```
struct sockaddr_vm my_addr = {0};
my_addr.svm_family = afVMCI;
my_addr.svm_cid = VMADDR_CID_ANY;
my_addr.svm_port = VMADDR_PORT_ANY;
if (bind(sockfd, (struct sockaddr *) &my_addr, sizeof my_addr) == -1) {
    perror("bind");
    goto close;
}
```

The `sockaddr_vm` structure contains an element for the context ID (CID), which specifies the virtual machine. For the server (listener), this could be any connecting virtual machine. Both `VMADDR_CID_ANY` and `VMADDR_PORT_ANY` are predefined so that at bind or connection time, the appropriate CID and port number are filled in from the client. `VMADDR_CID_ANY` is replaced with the CID of the virtual machine and `VMADDR_PORT_ANY` provides an ephemeral port from the non-reserved range ( $\geq 1024$ ).

The client (connector) can obtain its local CID by calling `VMCISock_GetLocalCID()`.

The `bind()` function is the same as for a regular TCP sockets application.

## Listen() Function

The `listen()` call prepares to accept incoming client connections. The `BACKLOG` macro predefines the number of incoming connection requests that the system accepts before rejecting new ones. This function is the same as `listen()` in a regular TCP sockets application.

```
if (listen(sockfd, BACKLOG) == -1) {
    perror("listen");
    goto close;
}
```

## Accept() Function

The `accept()` call waits indefinitely for an incoming connection to arrive, creating a new socket (and stream descriptor `newfd`) when it does. The structure `their_addr` gets filled with connection information.

```
struct sockaddr_vm their_addr;
if ((newfd = accept(sockfd, (struct sockaddr *) &their_addr, sizeof their_addr) == -1) {
    perror("accept");
    goto close;
}
```

## Select() Function

The `select()` call enables a process to wait for events on multiple file descriptors simultaneously. This function hibernates, waking up the process when an event occurs. You can specify a timeout in seconds or microseconds. After timeout, the function returns zero. You can specify the read, write, and exception file descriptors as `NULL` if the program can safely ignore them.

```
if ((select(nfds, &readfd, &writefds, &exceptfds, &timeout) == -1) {
    perror("select");
    goto close;
}
```

## Recv() Function

The `recv()` call reads data from the client application. The server and client can communicate the length of data transmitted, or the server can terminate its `recv()` loop when the client closes its connection.

```
char recv_buf[BUFSIZE];
if ((numbytes = recv(sockfd, recv_buf, sizeof recv_buf, 0)) == -1) {
    perror("recv");
    goto close;
}
```

## Send() Function

The `send()` call writes data to the client application. Server and client must communicate the length of data transmitted, or agree beforehand on a size. Often the server sends only flow control information to the client.

```
char send_buf[BUFSIZE];
if ((numbytes = send(sockfd, send_buf, sizeof send_buf, 0)) == -1) {
    perror("send");
    goto close;
}
```

## Close() Function

Given the original socket descriptor obtained from the `socket()` call, the `close()` call closes the socket and terminates the connection if it is still open. Some server applications close immediately after receiving client data, while others wait for additional connections. To compile on Windows, you must call the Winsock `closesocket()` instead of `close()`.

```
#ifdef _WIN32
    return closesocket(sockfd);
#else
    return close(sockfd);
#endif
```

The `shutdown()` function is like `close()`, but shuts down the connection.

## Poll() Information

Not all socket-based networking programs use `poll()`, but if they do, no changes are required. The `poll()` function is like `select()`. See [“Select\(\) Function”](#) on page 15 for related information.

## Read() and Write()

The `read()` and `write()` socket calls are provided for convenience. They provide the same functionality as `recv()` and `send()`.

## Getsockname() Function

The `getsockname()` function retrieves the local address associated with a socket.

```
my_addr_size = sizeof my_addr;
if (getsockname(sockfd, (struct sockaddr *) &my_addr, &my_addr_size) == -1) {
    perror("getsockname");
    goto close;
}
```

## Having the Client Request a Connection

At the top of your application, include `vmci_sockets.h` and declare a constant for the socket buffer size. In the example below, `BUFSIZE` defines the socket buffer size. It is not based on the size of a TCP packet.

```
#include "vmci_sockets.h"
#define BUFSIZE 4096
```

To compile on Windows, you must call the Winsock `WSAStartup()` function. See [“Preparing the Server for a Connection”](#) on page 14 for sample code.

### Socket() Function

In a VMCI sockets application, obtain the new address family (domain) to replace `AF_INET`.

```
int afVMCI = VMCISock_GetAFValue();
if ((sockfd = socket(afVMCI, SOCK_STREAM, 0)) == -1) {
    perror("socket");
    goto exit;
}
```

`VMCISock_GetAFValue()` returns a descriptor for the VMCI sockets address family if available.

### Connect() Function

The `connect()` call requests a socket connection to the server specified by CID in the `sockaddr_vm` structure, instead of by the IP address in the `sockaddr_in` structure.

```
struct sockaddr_vm their_addr = {0};
their_addr.svm_family = afVMCI;
their_addr.svm_cid = VMCISock_GetLocalCID();
their_addr.svm_port = SERVER_PORT;
if ((connect(sockfd, (struct sockaddr *) &their_addr, sizeof their_addr)) == -1) {
    perror("connect");
    goto close;
}
```

The `sockaddr_vm` structure contains an element for the CID to specify the virtual machine. For the client making a connection, the `VMCISock_GetLocalCID()` function returns the CID of the virtual machine.

The port number is arbitrary, although server (listener) and client (connector) must use the same number, which must designate a port not already in use. Only privileged processes can use ports < 1024.

The `connect()` call allows you to use `send()` and `recv()` functions instead of `sendto()` and `recvfrom()`. The `connect()` call is not necessary for datagram sockets.

### Send() Function

The `send()` call writes data to the server application. The client and server can communicate the length of data transmitted, or the server can terminate its `recv()` loop when the client closes its connection.

```
char send_buf[BUFSIZE];
/* Initialize send_buf with your data. */
if ((numbytes = send(sockfd, send_buf, sizeof send_buf, 0)) == -1) {
    perror("send");
    goto close;
}
```

## Recv() Function

The `recv()` call reads data from the server application. Sometimes the server sends flow control information, so the client must be prepared to receive it. Use the same socket descriptor as for `send()`.

```
char recv_buf[BUFSIZE];
if ((numbytes = recv(sockfd, recv_buf, sizeof recv_buf, 0)) == -1) {
    perror("recv");
    goto close;
}
```

## Close() Function

The `close()` call shuts down a connection, given the original socket descriptor obtained from the `socket()` function. To compile on Windows, you must call the Winsock `closesocket()` instead of `close()`.

```
#ifdef _WIN32
    return closesocket(sockfd);
#else
    return close(sockfd);
#endif
```

## Poll() Information

Not all socket-based networking programs use `poll()`, but if they do, no changes are required.

## Read() and Write()

The `read()` and `write()` socket calls are provided for convenience. They provide the same functionality as `recv()` and `send()`.

## Creating Datagram VMCI Sockets


This chapter describes the details of creating VMCI sockets to replace UDP sockets, in two sections:

- “Preparing the Server for a Connection” on page 20
- “Having the Client Request a Connection” on page 21

### Datagram VMCI Sockets

The flowchart in [Figure 4-1](#) shows how to establish connectionless sockets on the server and client.

**Figure 4-1.** Connectionless Datagram Sockets



In UDP sockets, the server waits for the client to transmit, and accepts datagrams. In VMCI sockets, the server and client communicate similarly with datagrams.

## Preparing the Server for a Connection

At the top of your application, include `vmci_sockets.h` and declare a constant for the socket buffer size. In the example below, `BUFSIZE` defines the socket buffer size. The number 4096 is a good choice for efficiency on multiple platforms. It is not based on the size of a UDP datagram.

```
#include "vmci_sockets.h"
#define BUFSIZE 4096
```

To compile on Windows, you must call the Winsock `WSAStartup()` function.

```
err = WSAStartup(versionRequested, &wsaData);
if (err != 0) {
    printf(stderr, "Could not register with Winsock DLL.\n");
    goto exit;
}
```

This is not necessary on non-Windows systems.

## Socket() Function

To alter a UDP socket program for VMCI sockets, obtain the new address family to replace `AF_INET`.

```
int afVMCI = VMCI_Sock_GetAFValue();
if ((sockfd_dgram = socket(afVMCI, SOCK_DGRAM, 0)) == -1) {
    perror("socket");
    goto exit;
}
```

`VMCI_Sock_GetAFValue()` returns a descriptor for the VMCI sockets address family if available.

This call is similar to the one for stream sockets, but has `SOCK_DGRAM` instead of `SOCK_STREAM`.

## Socket Options

Currently VMCI sockets offers no options for datagram connections.

## Bind() Function

The `bind()` call associates the datagram socket with the network settings in the `sockaddr_vm` structure, instead of the `sockaddr_in` structure.

```
struct sockaddr_vm my_addr = {0};
my_addr.svm_family = afVMCI;
my_addr.svm_cid = VMADDR_CID_ANY;
my_addr.svm_port = VMADDR_PORT_ANY;
if (bind(sockfd, (struct sockaddr *) &my_addr, sizeof my_addr) == -1) {
    perror("bind");
    goto close;
}
```

The `sockaddr_vm` structure contains an element for the context ID (CID) to specify the virtual machine. For the server (listener), this could be any connecting virtual machine. `VMADDR_CID_ANY` and `VMADDR_PORT_ANY` are predefined so that at bind or connection time, the appropriate CID and port number are filled in from the client. `VMADDR_CID_ANY` is replaced with the CID of the virtual machine and `VMADDR_PORT_ANY` provides an ephemeral port from the non-reserved range ( $\geq 1024$ ).

The client (connector) can obtain its local CID by calling `VMCI_Sock_GetLocalCID()`.

The VMCI sockets `bind()` function is the same as for a UDP datagram application.

## Getsockname() Function

```
if (getsockname(sockfd, (struct sockaddr *) &my_addr, &svm_size) == -1) {
    perror("getsockname");
    goto close;
}
```

The `getsockname()` function retrieves the local address associated with a socket.

## Recvfrom() Function

The `recvfrom()` call reads data from the client application. Server and client can communicate the length of data transmitted, or the server can terminate its `recvfrom()` loop when the client closes its connection.

```
if ((numbytes = recvfrom(sockfd, buf, sizeof buf, 0,
    (struct sockaddr *) &their_addr, &svm_size)) == -1) {
    perror("recvfrom");
    goto close;
}
```

## Sendto() Function

The `sendto()` call optionally writes data back to the client application. See [“Sendto\(\) Function”](#) on page 22.

## Close() Function

The `close()` call shuts down transmission, given the original socket descriptor obtained from the `socket()` call. Some server applications close immediately after receiving client data, while others wait for additional connections. To compile on Windows, you must call the Winsock `closesocket()` instead of `close()`.

```
#ifdef _WIN32
    return closesocket(sockfd);
#else
    return close(sockfd);
#endif
```

## Having the Client Request a Connection

At the top of your application, include `vmci_sockets.h` and declare a constant for buffer size. This does not have to be based on the size of a UDP datagram.

```
#include "vmci_sockets.h"
#define BUFSIZE 4096
```

To compile on Windows, you must call the Winsock `WSAStartup()` function. See [“Preparing the Server for a Connection”](#) on page 20 for sample code.

## Socket() Function

To alter a UDP socket program for VMCI sockets, obtain the new address family to replace `AF_INET`.

```
int afVMCI = VMCISock_GetAFValue();
if ((sockfd = socket(afVMCI, SOCK_DGRAM, 0)) == -1) {
    perror("socket");
    goto exit;
}
```

## Sendto() Function

Because this is a connectionless protocol, you pass the socket address structure `their_addr` as a parameter to the `sendto()` call.

```
struct sockaddr_vm their_addr = {0};
their_addr.svm_family = AFVMCI;
their_addr.svm_cid = SERVER_CID;
their_addr.svm_port = SERVER_PORT;
if ((numbytes = sendto(sockfd, buf, BUFSIZE, 0,
    (struct sockaddr *) &their_addr, sizeof their_addr)) == -1) {
    perror("sendto");
    goto close;
}
```

The `sockaddr_vm` structure contains an element for the CID to specify the virtual machine. For the client making a connection, the `VMCISock_GetLocalCID()` function returns the CID of the virtual machine.

The port number is arbitrary, although the server (listener) and client (connector) must use the same number, which must designate a port not already in use. Only privileged processes can use ports < 1024.

## Connect() and Send()

Even with this connectionless protocol, applications can call the `connect()` function once to set the address, and call the `send()` function repeatedly without having to specify the `sendto()` address each time.

```
if ((connect(sockfd, (struct sockaddr *) &their_addr, sizeof their_addr)) == -1) {
    perror("connect");
    goto close;
}
if ((numbytes = send(sockfd, send_buf, BUFSIZE, 0)) == -1) {
    perror("send");
    goto close;
}
```

## Recvfrom() Function

The `recvfrom()` call optionally reads data from the server application. See [“Recvfrom\(\) Function”](#) on page 21.

## Close() Function

The `close()` call shuts down a connection, given the original socket descriptor obtained from the `socket()` function. To compile on Windows, call the Winsock `closesocket()`, as shown in [“Close\(\) Function”](#) on page 21.



# Learning More About Sockets

---

This appendix introduces Internet sockets and provides pointers to further information.

## About Berkeley Sockets and Winsock

A socket is a communications endpoint with a name and address in a network. Sockets were made famous by their implementation in Berkeley UNIX, and made universal by their incorporation into Windows.

Most socket-based applications employ a client-server approach to communications. Rather than trying to start two network applications simultaneously, one application tries to make itself always available (the server or the provider) while another requests services as needed (the client or the consumer).

VMCI sockets are designed to use the client-server approach but, unlike TCP sockets, they do not support multiple endpoints simultaneously initiating connections with one another.

Data going over a socket can be in any format, and travel in either direction.

Many people are confused by AF\_INET as opposed to PF\_INET. Linux defines them as identical. This manual uses AF only. AF means address family, while PF means protocol family. As designed, a single protocol family could support multiple address families. However as implemented, no protocol family ever supported more than one address family. For Internet Protocol version 6 (IPv6), AF\_INET6 is synonymous with PF\_INET6.

WinSock includes virtually all of the Berkeley sockets API, as well as additional WSA functions to cope with cooperative multitasking and the event-driven programming model of Windows.

## Resources on the Web

Here is a succinct and comprehensible API explanation:

<http://www.cas.mcmaster.ca/~qiao/courses/cs3mh3/tutorials/socket.html>

### Wikipedia

Here is an overview of the history and design of sockets:

[http://en.wikipedia.org/wiki/Berkeley\\_sockets](http://en.wikipedia.org/wiki/Berkeley_sockets)

### Sockaddr

Here is an overview of Winsock design and usage:

<http://www.sockaddr.com/TheSocketsParadigm.html>

### MSDN

Here is reference information about Winsock:

[http://msdn2.microsoft.com/en-us/library/ms740673\(VS.85\).aspx](http://msdn2.microsoft.com/en-us/library/ms740673(VS.85).aspx)

## Linux Manual Pages

socket(7) – Type `man socket` on a Linux system.

[http://www.yo-linux.com/cgi-bin/man2html?cgi\\_command=socket\(2\)](http://www.yo-linux.com/cgi-bin/man2html?cgi_command=socket(2))

[http://www.yo-linux.com/cgi-bin/man2html?cgi\\_command=socket\(7\)](http://www.yo-linux.com/cgi-bin/man2html?cgi_command=socket(7))

## Hardcopy Books

*Internetworking with TCP/IP, Volume 3: Client-Server Programming and Applications, Linux/Posix Sockets Version*, by Douglas E. Comer and David L. Stevens, 601 pages, Prentice-Hall, 2000.

*UNIX Network Programming, Volume 1: The Sockets Networking API*, Third Edition, by W. Richard Stevens (RIP), Bill Fenner, and Andrew M. Rudoff, 1024 pages, Addison-Wesley, 2003.

# Glossary

---

## **D**      **datagram**

A self-contained unit of data containing enough information to be routed from its source to its destination without reliance on earlier exchanges between source and destination hosts and the transporting network.

## **I**      **IP**

Internet Protocol, the network layer upon which TCP and UDP are based. Defined by the IETF in RFC 791. IP is a best-effort packet routing protocol. In 2008, IPv4 (version 4) is nearly universal but IPv6 (version 6) deployments are beginning.

## **S**      **socket**

A communications connection endpoint with a name and address in a network. The two endpoints of a socket can reside on the same system or on different systems across the network. Sockets are most often used for network applications, but they are also useful for interprocess communications on a single server.

### **stream socket**

A network connection that provides a two-way, sequenced, reliable, unduplicated flow of data without record boundaries, with well-defined mechanisms for establishing connections and detecting errors.

## **T**      **TCP**

Transmission Control Protocol, the Internet standard for connection-oriented stream sockets.

## **U**      **UDP**

User Datagram Protocol, the Internet standard for connectionless datagram sockets.

## **V**      **VMCI**

Virtual machine communication interface, a shared memory API and datagram interface now replaced by VMCI sockets, a stream and datagram sockets interface.



# Index

## A

about VMCI sockets 7  
accept() 15  
address structure for sockets 12  
AF\_INET and PF\_INET 23  
AF\_INET and VMCI sockets 11  
afVMCI from VMCISock\_GetAFValue() 12, 14, 15, 17

## B

bind() 12, 15, 20  
books about sockets 24

## C

close() 16, 18, 21  
connect() 17  
connectionless socket 12  
connection-oriented socket 12  
context ID (CID) summary 11

## D

datagram VMCI sockets 19

## G

getsockname() 16, 21  
getsockopt() 14  
guest to guest 8, 12  
guest to host 8, 12

## H

hidden information about sockets 23  
host to guest 8, 12

## I

illustration of datagram VMCI sockets 10  
illustration of stream VMCI sockets 9

## L

listen() 15

## P

PF\_INET and AF\_INET 23  
poll() 16, 18  
porting sockets applications 11

## R

read() 16, 18  
recv() 16, 18

recvfrom() 21  
release contents 8

## S

select() 15  
send() 16, 17  
sendto() 21, 22  
setsockopt() 14  
SO\_VMCI\_BUFFER\_SIZE 14  
SOCK\_DGRAM 12  
SOCK\_STREAM 12  
socket() 8, 12, 14, 17, 20, 21  
stream VMCI sockets 13

## T

technical support resources 6

## U

use cases for VMCI sockets 8

## V

VMCI library deprecated 7  
VMCISock\_GetAFValue() 8, 14, 17, 20  
VMCISock\_GetLocalCID() 11, 15, 17, 20

## W

Web resources about sockets 23  
write() 16, 18  
WSAStartup() 14, 17, 20

