

Workstation User's Manual

VMware Workstation 7.0

This document supports the version of each product listed and supports all subsequent versions until the document is replaced by a new edition. To check for more recent editions of this document, see <http://www.vmware.com/support/pubs>.

EN-000168-00

vmware[®]

You can find the most up-to-date technical documentation on the VMware Web site at:

<http://www.vmware.com/support/>

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

docfeedback@vmware.com

Copyright © 1998–2009 VMware, Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. VMware products are covered by one or more patents listed at <http://www.vmware.com/go/patents>.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

VMware, Inc.

3401 Hillview Ave.
Palo Alto, CA 94304
www.vmware.com

Contents

About This Book 19

1 Introduction and System Requirements 21

Product Benefits 21

Overview of This Manual 22

Host System Requirements 23

PC Hardware 23

Memory 23

Display 24

Disk Drives 24

Local Area Networking 25

Host Operating System 25

Virtual Machine Specifications 29

Processor 29

Chip Set 29

BIOS 30

Memory 30

Graphics 30

IDE Drives 30

SCSI Devices 30

Floppy Drives 31

Serial (COM) Ports 31

Parallel (LPT) Ports 31

USB Ports 31

Keyboard 31

Mouse and Drawing Tablets 31

Ethernet Card 32

Sound 32

Virtual Networking 32

Supported Guest Operating Systems 32

Support for 64-Bit Guest Operating Systems 37

2	Installing and Upgrading VMware Workstation	39
	Installation Prerequisites	39
	Sharing a Workstation Host with Other VMware Products	40
	Install Workstation on a Windows Host	41
	Install Workstation Silently	42
	Uninstall Workstation from a Windows Host	44
	Install Workstation on a Linux Host	44
	Using Command-Line Installation Options	46
	Uninstall Workstation from a Linux Host	47
	Preparing for an Upgrade	47
	Upgrade Workstation on a Windows Host	48
	Upgrading to a Windows Vista and Windows 7 Host	49
	Upgrade Workstation on a Linux Host	51
3	Learning Workstation Basics	53
	Start Workstation on a Windows Host	53
	Start Workstation on a Linux Host	54
	Overview of the Workstation Window	54
	Home Page and Views	56
	Toolbar Buttons	59
	View the Sidebar	62
	Favorites List in the Sidebar	63
	Check for Product Updates	65
	Quickly Create a Virtual Machine and Install an Operating System	66
	Introduction to Workstation Preferences	67
	Introduction to Virtual Machine Settings	69
	Hardware Tab	69
	Options Tab	70
	Closing Virtual Machines and Exiting Workstation	71
	Set a Virtual Machine to Run in the Background	72
	Keyboard Shortcuts	72
	Change the Hot-Key Combination	74
	Gathering Information for VMware Technical Support	75
	Register and Create a Support Request	75
	Gather Debugging Information for a Virtual Machine	75
	Running the Support Script	76

4	Creating and Upgrading a Virtual Machine	79
	Methods of Creating Virtual Machines	79
	Configuration Options for the New Virtual Machine Wizard	80
	Easy Install Feature for Some Guest Operating Systems	80
	Typical Compared to Custom Configurations	82
	Guest Operating System Selection	83
	Virtual Machine Location	83
	Virtual Hardware Compatibility Levels	84
	Number of Processors	84
	Memory Allocation	85
	Network Connection Type	85
	I/O Adapter Types	86
	Disk Types	86
	Normal and Independent Disk Modes	87
	Virtual Disks and Physical Disks	87
	Disk Capacity	88
	Pocket ACE Disk Size Calculator on Windows Only	88
	Use the New Virtual Machine Wizard	89
	Installing a Guest Operating System	89
	Installation Requirements for the ESX Guest Operating System	90
	Respond to Easy Install Prompts	90
	Install a Guest Operating System Manually	91
	Use a Paravirtualized Kernel in Linux Guests	93
	Upgrade a Guest Operating System	94
	Change the Version of a Virtual Machine	94
	Using an Older-Version Virtual Machine Without Upgrading	96
	Files That Make Up a Virtual Machine	97
5	Installing and Using VMware Tools	101
	Components of VMware Tools	101
	VMware Tools Service	102
	VMware Device Drivers	102
	VMware User Process	103
	VMware Tools Control Panel	104
	Installing VMware Tools	104
	Install VMware Tools in a Windows Guest	104
	Configure the Video Driver on Older Versions of Windows	105
	Automate the Installation of VMware Tools in a Windows Guest	106

Install VMware Tools in a Linux Guest	109
Install VMware Tools in a Solaris Guest	111
Install VMware Tools in a FreeBSD Guest	112
Install VMware Tools in a NetWare Guest	113
Start the VMware User Process Manually If You Do Not Use a Session Manager	114
VMware Tools Update Process	115
How Automatic Updates Occur	115
How You Are Notified to Do a Manual Update	116
Use Global Settings to Update VMware Tools Automatically	116
Set VMware Tools Update Options for Each Virtual Machine	117
Update VMware Tools in Older Windows Virtual Machines	117
Uninstall VMware Tools	118
Repair or Change Installed Modules in a Windows Guest	118
Open the VMware Tools Control Panel	119
Use the Windows Control Panel to Display the Taskbar Icon	120
Options Tab Settings	120
Devices Tab Settings	122
Scripts Tab Settings	122
Shrink Tab Settings	123
About Tab	123
Configure VMware Tools in a NetWare Guest	123
Customizations to VMware Tools	125
How VMware Tools Scripts Affect Power States	125
Execute Commands After You Power Off or Reset a Virtual Machine	128
Passing a String from the Host to the Guest at Startup	129
Passing Information Between the Guest and Another Program	131
Use the VMware Tools Service Command-Line Interface	132

6 Creating a Virtual Machine from a System Image or Another Virtual Machine 133

Conversion Process for Importing from Other Formats	133
VMware Converter Compared to the Conversion Wizard	135
Supported Source Machines	135
Importing from Various Sources	136
Supported Destinations	140
Designating a Destination for a Virtual Machine	140
Conversion Impact on Settings	142
Migration Issues Caused by Hardware Changes	143

Open a Third-Party Virtual Machine or System Image	143
Import a Virtual Machine, Virtual Appliance, or System Image	144
Import a Windows XP Mode Virtual Machine	145
7 Getting Started with Virtual Machines	147
Starting a Virtual Machine	148
Start a Virtual Machine from the Workstation User Interface	148
Start a Virtual Machine That Is Running in the Background	149
Start a Virtual Machine by Using VM Streaming	149
Virtual Machine Location	150
Shut Down a Virtual Machine	151
Configure Power Off and Reset Options for a Virtual Machine	152
Download Components	153
Pausing a Virtual Machine	154
Pause Feature Limitations	154
Pause and Unpause a Virtual Machine	155
Encrypting a Virtual Machine	155
Restrictions on Encryption	156
Encrypt a Virtual Machine	156
Remove Encryption from a Virtual Machine	157
Change the Password for an Encrypted Virtual Machine	157
Delete a Virtual Machine	158
Controlling the Virtual Machine Display	158
Using Unity Mode	158
Use Full Screen Mode	162
Use Quick Switch Mode	165
Use Exclusive Mode	165
Use Multiple Monitors for One Virtual Machine	166
Use Multiple Monitors for Multiple Virtual Machines	169
Fitting the Workstation Console to the Virtual Machine Display	169
Working with Nonstandard Resolutions	171
Configuring Video and Sound	172
Setting Screen Color Depth	172
Support for Direct3D Graphics	173
Configuring Sound	175
Install New Software in a Virtual Machine	179
Disable Acceleration If a Program Does Not Run	179
Report Battery Information in the Guest	180

	Use Host Printers in a Virtual Machine	180
	Use Removable Devices in a Virtual Machine	181
	Configure the Appliance View for a Virtual Machine	182
	Create a Screenshot of a Virtual Machine	183
	Create and Play Back a Movie of a Virtual Machine	184
	Advanced Options for Application Developers	185
8	Transferring Files and Text Between the Host and Guest	187
	Using the Drag-and-Drop Feature	187
	Enable or Disable the Drag-and-Drop Feature	188
	Using the Copy and Paste Feature	189
	Enable or Disable the Copy and Paste Feature	190
	Using Shared Folders	190
	Set Up Shared Folders	191
	Enabling and Disabling Shared Folders	193
	Viewing a Shared Folder	195
	Permissions and Folder Mounting for Shared Folders on Linux Guests	196
	Using a Mapped Drive	198
	Map or Mount a Virtual Disk to a Drive on the Host	199
	Disconnect the Host from the Virtual Disk	200
9	Preserving the State of a Virtual Machine	201
	Using the Suspend and Resume Features	201
	Use Hard Suspend or Soft Suspend	201
	Suspend or Resume a Virtual Machine	202
	Using Snapshots	203
	Scenarios for Using Multiple Snapshots	203
	Information Captured by Snapshots	205
	Snapshot Conflicts	206
	Enable or Disable Background Snapshots	206
	Exclude a Virtual Disk from Snapshots	207
	Snapshot Manager Overview	208
	Take a Snapshot	209
	Rename a Snapshot or Recording	210
	Restore an Earlier State from a Snapshot	211
	Delete a Snapshot or a Recording	212
	Take or Revert to a Snapshot at Power Off	213
	Using AutoProtect Snapshots	214
	Snapshots and Workstation 4 Virtual Machines	215

10 Cloning, Moving, and Sharing Virtual Machines 217

- The Virtual Machine's Universal Unique Identifier 217
 - UUID Options When You Move a Virtual Machine 218
 - Specify a UUID for a Virtual Machine 218
- Cloning a Virtual Machine 219
 - Types of Clones 220
 - Creating Clones 221
- Moving a Virtual Machine 223
 - Hosts with Different Hardware 223
 - Move a Virtual Machine to a New Location or a New Host 225
- Moving an Older Virtual Machine 226
- Moving Linked Clones 227
- Sharing Virtual Machines with Other Users 227
- Using VNC for Remote Connections to a Virtual Machine 228
 - Configure a Virtual Machine as a VNC Server 228
 - Use a VNC Client to Connect to a Virtual Machine 229
- Make Virtual Machines Available for Streaming from a Web Server 230
- Sharing Virtual Machines with VMware Player 231
 - Start and Exit VMware Player 232
 - Setting Up Virtual Machines for Use with VMware Player 233

11 Using Disks and Disk Drives 235

- Virtual Machine Disk Storage 235
 - Benefits of Using Virtual Disks 236
 - Physical Disks 238
- Virtual Disk Maintenance Tasks 238
 - Defragment Virtual Disks 239
 - Compact a Virtual Disk 240
 - Expand a Virtual Disk 240
- Adding Virtual and Physical Disks to a Virtual Machine 241
 - Add a New Virtual Disk to a Virtual Machine 242
 - Add an Existing Virtual Disk to a Virtual Machine 243
 - Remove a Virtual Disk from a Virtual Machine 243
 - Using Physical Disks in a Virtual Machine 244
- Adding DVD/CD-ROM and Floppy Drives to a Virtual Machine 250
 - Add DVD or CD Drives to a Virtual Machine 250
 - Add a Floppy Drive to a Virtual Machine 252
 - Connect a CD-ROM, DVD, or Floppy Drive to an Image File 253

- Using VMware Virtual Disk Manager 254
- Using Dual-Boot Computers with Virtual Machines 254
- Legacy Virtual Disks 254

12 Recording and Replaying Virtual Machine Activity 257

- Uses of the Record/Replay Feature 257
- Physical and Virtual Hardware Requirements 258
- Configure Record/Replay for a Virtual Machine 259
 - Record Control Dialog Box Features 261
 - Replay Control Dialog Box Features 262
- Create a Recording 264
- Replay a Recording 265
 - Browse a Recording 266
- Using an Execution Trace File of a Recording 266
 - Enable Execution Tracing for a Recording 267
 - Create an Execution Trace File of a Recording 268
- Maintenance Tasks for Using Recordings 268
 - Delete a Recording 268
 - Disable Periodic Screenshots 269

13 Configuring Teams 271

- Benefits of Using Teams 271
- Managing Teams 272
 - Create a Team 272
 - Open a Team and Add It to the Favorites List 273
 - Rename a Team 274
 - Power Off or Close a Team 274
 - Delete a Team 275
- Summary and Console Views for Teams and Their Virtual Machines 276
- Managing the Members of a Team 276
 - Add a Virtual Machine to a Team 276
 - Remove a Virtual Machine from a Team 277
 - Specify the Startup Sequence for a Team 278
- Power Operations for Teams and Their Members 279
 - Power On a Team 279
 - Suspend or Resume a Team 279
 - Perform Power Operations on One Team Member 280

Working with Team Networks	280
LAN Segment Requirements Regarding IP Addresses	280
Create a Team LAN Segment	281
Configure LAN Segments	281
Add or Remove Network Adapters	282
Delete a LAN Segment	283
Cloning and Taking Snapshots of Team Virtual Machines	283
14 Configuring a Virtual Network	285
Components of the Virtual Network	285
Virtual Switch	285
DHCP Server	286
Network Adapter	286
Common Networking Configurations	286
Bridged Networking	287
Network Address Translation (NAT)	289
Host-Only Networking	290
Example of a Custom Networking Configuration	291
Set Up a Custom Networking Configuration	292
Changing a Networking Configuration	295
Find the Network Type of a Virtual Machine	295
Add Virtual Network Adapters	295
Modify Existing Virtual Network Adapters	296
Configuring Bridged Networking	297
Configure VMnet0 Automatic Bridged Networking on a Windows Host	297
Configure vmnet0 Automatic Bridged Networking on a Linux Host	298
Setting Up a Second Automatic Bridged Network Interface	299
Changing the Subnet or DHCP Settings for a Virtual Network	299
Change Subnet or DHCP Settings on a Windows Host	300
Change Subnet or DHCP Settings on a Linux Host	300
Configuring Host Virtual Network Adapters	301
Connect or Disconnect a Host Virtual Network Adapter	301
Setting Up Two Separate Host-Only Networks	302

15	Advanced Virtual Networking	303
	Selecting IP Addresses on a Host-Only Network or NAT Configuration	304
	How the Subnet Number Is Assigned	304
	Determining Whether to Use DHCP or Statically Assign Addresses	305
	DHCP Conventions for Assigning IP Addresses	305
	Configure the DHCP Server on a Windows Host	306
	Configure the DHCP Server on a Linux Host	306
	Avoiding IP Packet Leakage in a Host-Only Network	306
	Disable Packet Forwarding on Windows Hosts	307
	Disable Packet Forwarding on Linux Hosts	308
	Maintaining and Changing the MAC Address of a Virtual Machine	308
	Avoiding MAC Address Changes	308
	Assign the Same MAC Address to Any Virtual Machine Manually	309
	Controlling Routing Information for a Host-Only Network on Linux	310
	Potential Issues with Host-Only Networking on Linux	311
	DHCPD on the Linux Host Does Not Work After Installing Workstation	311
	DHCP and DDNS	311
	Configuring Host-Only Virtual Machines	312
	Set Up Using Configuration 1 or 2	312
	Set Up Using Configuration 3	313
	Complete Configuring the Virtual Network Adapters	313
	Set Up Routing Between Two Host-Only Networks	314
	Using Virtual Network Adapters in Promiscuous Mode on a Linux Host	316
	Using NAT	316
	How the NAT Device Uses the VMnet8 Virtual Switch	317
	DHCP on the NAT Network	317
	DNS on the NAT Network	318
	External Access from the NAT Network	318
	Advanced NAT Configuration	319
	Configure NAT on a Windows Host	319
	Custom NAT and DHCP Configuration on a Windows Host	319
	Specifying Connections from Ports Below 1024	320
	Configuring NAT on a Linux Host	321
	Considerations for Using NAT	324
	Using NAT with NetLogon	324
	Sample Linux nat.conf File	327

Using Samba with Workstation	328
Add Users to the Samba Password File	329
Using a Samba Server for Bridged and Host-Only Networks	329
Use Samba Without Network Access	330
16 Connecting Devices	331
Using Parallel Ports	331
Add a Virtual Parallel Port to a Virtual Machine	332
Troubleshoot ECR Errors for Parallel Ports	332
Configuring a Parallel Port on a Linux Host	333
Using Serial Ports	335
Add a Virtual Serial Port to a Virtual Machine	335
Change the Input Speed of the Serial Connection	337
Debugging over a Virtual Serial Port	338
Configuring Keyboard Features	339
Use the Enhanced Virtual Keyboard for Windows Hosts	339
Hot Keys for Virtual Machines	340
Specify a Language Keyboard Map for VNC Clients	341
Keyboard Mapping on a Linux Host	342
Using USB Devices in a Virtual Machine	351
Enable the USB 2.0 Controller for a Virtual Machine	352
Add a USB Controller to a Virtual Machine	352
Connecting USB Devices	353
USB Driver Installation on a Windows Host	355
Access and Use a USB Device on a Linux Host	356
How Device Control Is Shared Between Host and Guest	356
Disconnecting USB Devices from a Virtual Machine	357
Use Smart Cards with Virtual Machines	358
Switch to Using the Virtual Smart Card Reader on Linux Hosts	360
Disable Smart Card Sharing	360
Support for Generic SCSI Devices	361
Installing Required Adapters or Drivers for Some Windows Guests	362
Avoiding Concurrent Access on Linux Hosts	363
Add a Generic SCSI Device to a Virtual Machine	363
Troubleshoot Problems Detecting Generic SCSI Devices	364
Use Four-Way Virtual Symmetric Multiprocessing	366
Use a Virtual Machine That Originally Had More Than Four Virtual Processors	367

17	Special-Purpose Configuration Options for Windows Hosts	369
	Restricting the User Interface	369
	Enable the Restricted User Interface	370
	Restrict the User Interface and Return to a Snapshot	370
	Disable the Restricted User Interface	371
	Making a Virtual Machine Always Use Full Screen Switch Mode	372
	Specify Global Configuration Settings for Full Screen Switch Mode	372
	Virtual Key Codes	373
	Hot Key for Cycling Through Virtual Machines and the Host Computer	375
	Hot Keys for Switching Directly to Virtual Machines and the Host Computer	375
	Other Entries in the Global Configuration File	376
	Using vmware-fullscreen to Run a Virtual Machine	377
	Guest ACPI S1 Sleep	380
18	Learning the Basics of VMware ACE	381
	Benefits of Using VMware ACE	381
	Key Features of VMware ACE	382
	VMware ACE Terminology	383
	Network and Disk Space Requirements for the Administrative Workstation	384
	Overview of Creating and Deploying ACE Packages	385
	Overview of the ACE User Interface	386
	Troubleshooting Users' Problems	387
19	Setting and Using Policies and Customizing VMware Player	389
	Benefits of Using Policies	390
	Set Policies for ACE Instances	390
	Setting Access Control Policies	391
	Create or Edit an Access Control Policy	392
	Activation Settings	392
	Authentication Settings	393
	Using an Authentication Script	394
	Include a Power-On and Power-Off Script in the Package	394
	Set a Recovery Key for Encrypted ACE Instances	396
	Set Activation Limit	396
	Active Directory Password Change Proxying	397

Setting Host to Guest Data Script Policies	397
Specify a Script and a Command to Run It	398
Setting Expiration Policies	399
Setting Copy Protection Policies	400
Setting Resource Signing Policies	401
Setting Network Access Policies	402
Before You Begin Setting Host Policies	402
Use the Network Access Wizard to Configure Network Access	403
Guidelines for Specifying Zone Conditions	404
Using the Ruleset Editor to Configure Host and Guest Access	407
Change NAT Settings	409
Configure Which Physical Network Adapter to Use	410
Understanding the Interaction of Host and Guest Access Filters with Tunneling Protocols	411
Updating a Network Access Policy	411
Setting Removable Devices Policies	411
Setting USB Device Policies	412
Access Levels for USB Devices	412
Set an Access Policy for USB Devices	412
Setting Virtual Printer Policies	414
Setting Runtime Preferences Policies	415
Runtime Preferences Settings	415
Enhanced Virtual Keyboard Settings	416
Exit Behavior Settings	416
Pocket ACE Cache Settings	417
Setting Snapshot Policies	418
Setting Administrator Mode Policies	419
Use Administrator Mode on an ACE Instance	419
Setting Kiosk Mode Policies	420
Change the Key Combination for Exiting Kiosk Mode	420
Setting Hot-Fix Policies for Standalone ACE Instances	421
Setting the Policy Update Frequency for Managed ACE Instances	421
Control Which ACE Instances Run on a Host	422
Writing Plug-In Policy Scripts	424
Examples of Policy Scripts	425
Customizing the VMware Player Interface on Windows Hosts Only	428
Create and Specify a Skin File	428
Customizing the VMware Player Icons	429
Customizing the Title Bar Text	430

- Customizing the Removable Device Display 430
- Shortcut Key Values 432
- Sample Skin File 433

20 Deploying ACE Packages 435

- Edit Deployment Settings 435
 - Encryption Settings 436
 - Package Lifetime Settings 436
 - Instance Customization on Windows Guests Only 437
 - Custom EULA Settings 445
 - Deployment Platform Settings 446
- ACE Resources Directory 446
- Review the Configuration of an ACE-Enabled Virtual Machine 447
- Use Preview Mode to Test Policy and Deployment Settings 448
- Creating a Package 449
 - Overview of Package Creation and Validation 450
 - Turn Off the VMware Tools Check for Test Deployments 451
 - Prerequisites for Using the Packaging Wizards 452
 - Use the New Package Wizard 453
 - View Package Properties and Add Notes 454
- Perform an End-to-End Deployment Test 455
- Deploy Packages 456

21 Pocket ACE 457

- Use Cases for Pocket ACE 458
- Portable Device Requirements 459
- Policies and Deployment Settings for Pocket ACE 460
- Create a Pocket ACE Package 460
- Deploying the ACE Package on a Portable Device 461
 - Use the Graphical Utility to Deploy Pocket ACE Packages 461
 - Use the Command-Line Utility to Deploy Pocket ACE Packages 462
- Run the Pocket ACE Instance 463

22 Installing ACE Packages 465

- Installing an ACE Package on a Windows Host 465
 - Install an ACE Instance on a Single Windows Host 466
 - Installing an ACE Package Silently on Multiple Windows Hosts 466
 - Uninstall VMware Player or an ACE instance from a Windows Host 468

Installing an ACE Package on a Linux Host	469
Manually Install VMware Player on a Linux Host	469
Install the ACE Instance on a Single Linux Host	470
Install an ACE Package Silently on Multiple Linux Hosts	471
Prepare a Linux Host for Running in Kiosk Mode	472
Uninstall VMware Player or an ACE Instance from a Linux Host	473
Upgrading ACE Instances to ACE 2.6	473
Start and Use an ACE Instance	474
Change Default Kiosk Mode Startup Behavior	475
Use Multiple Virtual Machines in Kiosk Mode	476
Install an ACE Client License	478
Change the ACE Client License	478
Quit VMware Player	479
Troubleshooting Tools	479
Using the vmware-acetool Command-Line Tool	479
Respond to Hot Fix Requests	481
Troubleshooting Setup Issues	482
 Appendix: Workstation Command-Line Reference	 485
Startup Options for Workstation and Virtual Machines	485
Using Startup Options in a Windows Shortcut	487
 Glossary	 489
 Index	 495

About This Book

This manual, the *Workstation User's Manual*, provides information about installing and using VMware® Workstation 7.0. With Workstation, you can convert an existing physical PC into a VMware virtual machine or create a new virtual machine. Each virtual machine represents a complete PC, including the processor, memory, network connections and peripheral ports. Use Workstation to do the following:

- Host legacy applications and overcome platform migration issues.
- Configure and test new software or patches in an isolated environment.
- Automate tasks for software development and testing.
- Demonstrate multi-tier configurations on a single PC.

Intended Audience

This book is intended for anyone who needs to install, upgrade, or use VMware Workstation. Workstation users typically include people who do software development and testing or work with multiple operating systems or computing environments: software developers, QA engineers, trainers, salespeople who run demos, and anyone who wants to create virtual machines.

Document Feedback

VMware welcomes your suggestions for improving our documentation. If you have comments, send your feedback to docfeedback@vmware.com.

Technical Support and Education Resources

The following sections describe the technical support resources available to you. To access the current version of this book and other books, go to <http://www.vmware.com/support/pubs>.

Online and Telephone Support

To use online support to submit technical support requests, view your product and contract information, and register your products, go to <http://www.vmware.com/support>.

Customers with appropriate support contracts should use telephone support for the fastest response on priority 1 issues. Go to http://www.vmware.com/support/phone_support.html.

Support Offerings

To find out how VMware support offerings can help meet your business needs, go to <http://www.vmware.com/support/services>.

VMware Professional Services

VMware Education Services courses offer extensive hands-on labs, case study examples, and course materials designed to be used as on-the-job reference tools. Courses are available onsite, in the classroom, and live online. For onsite pilot programs and implementation best practices, VMware Consulting Services provides offerings to help you assess, plan, build, and manage your virtual environment. To access information about education classes, certification programs, and consulting services, go to <http://www.vmware.com/services>.

Introduction and System Requirements

1

VMware Workstation is a desktop software that allows you to run multiple x86-compatible desktop and server operating systems simultaneously on a single PC, in fully networked, portable virtual machines—with no rebooting or hard drive partitioning required. This chapter includes the following topics:

- [“Product Benefits”](#) on page 21
- [“Overview of This Manual”](#) on page 22
- [“Host System Requirements”](#) on page 23
- [“Virtual Machine Specifications”](#) on page 29
- [“Supported Guest Operating Systems”](#) on page 32

Product Benefits

Workstation is used in the software development, quality assurance, training, sales, and IT fields.

Workstation streamlines software development and testing:

- Develop and test multiple operating systems and applications on a single PC.
- Connect virtual machines to simulate and test multitier configurations.
- Use multiple snapshots and debugging support to facilitate testing.
- Archive test environments on file servers where they can be easily restored or shared.

Workstation enhances productivity of IT professionals:

- Configure and test desktops and servers as virtual machines before deploying them to production.
- Test new multitier applications, application updates, and operating system patches on a single PC.
- Host legacy applications within virtual machines, facilitating operating system migrations and eliminating the need to port legacy applications.
- Create a virtual library of end-user configurations on a shared drive.

Workstation facilitates computer-based training and software demos:

- Package and deploy classroom material in virtual machines.
- Allow students to experiment with multiple operating systems, applications, and tools in secure, isolated virtual machines.
- Configure virtual machines to undo all changes at shutdown.
- Demo complex or multitier configurations on a single laptop.

Overview of This Manual

If you are a veteran Workstation user, see the Workstation Release Notes for a list of new features. For upgrade instructions, see [“Preparing for an Upgrade”](#) on page 47.

If you are new to Workstation, the first chapters of this manual—through [Chapter 7, “Getting Started with Virtual Machines,”](#) on page 147—guide you through the key steps for installing the software and provide an introduction to using Workstation.

Later chapters provide in-depth information about the sophisticated features of Workstation. These chapters are intended for expert users.

[Chapter 18, “Learning the Basics of VMware ACE,”](#) on page 381 through [Chapter 22, “Installing ACE Packages,”](#) on page 465 describe how to use the ACE features included with the version of Workstation that runs on Windows hosts. VMware ACE authoring features enable you to package and deploy Pocket ACE and desktop virtual machines with encryption, restricted network access, and device control.

Host System Requirements

Like physical computers, the virtual machines running under Workstation perform better if they have faster processors and more memory.

The terms *host* and *guest* describe physical and virtual machines:

- **Host** — The physical computer on which you install the Workstation software is called the host computer, and its operating system is the host operating system.
- **Guest** — The operating system running inside a virtual machine is called a guest operating system.

For definitions of these and other special terms, see [“Glossary”](#) on page 489.

PC Hardware

- Standard x86-compatible or x86-64-compatible personal computer
- 1.3GHz or faster CPU minimum
- Multiprocessor systems are supported.
- Support for 64-bit guest operating systems is available with Intel VT or AMD-V CPUs.

For hardware requirements to support Windows 7 Aero graphics, see [“Recommendations for Windows 7 Aero Graphics Support”](#) on page 24.

Memory

You need enough memory to run the host operating system, plus the memory required for each guest operating system and for applications on the host and guest. The minimum memory requirement is 1GB, VMware recommends to have 2GB and above. For more information on memory requirements, see your guest operating system and application documentation.

As of version 7.0 of Workstation, the total amount of memory you can assign to all virtual machines running on a single host is limited only by the amount of RAM on the host. The maximum amount of memory for each virtual machine is 32GB.

For memory requirements to support Windows 7 Aero graphics, see [“Recommendations for Windows 7 Aero Graphics Support”](#) on page 24.

Display

16-bit or 32-bit display adapter is recommended. For display requirements to support Windows 7 Aero graphics, see [“Recommendations for Windows 7 Aero Graphics Support”](#) on page 24.

NOTE Use the latest graphics driver recommended for your host.

Recommendations for Windows 7 Aero Graphics Support

To support Windows 7 Aero graphics, VMware recommends the following configuration:

- CPU
 - Intel Dual Core, 2.2GHz and above
 - AMD Athlon 4200+ and above
- Host GPCPU
 - nVidia GeForce 8800GT and above
 - ATI Radeon HD 2600 and above
- Memory—at least 3GB of host system memory, 1GB of memory allocated to the guest operating system, and 256MB graphics memory.

Disk Drives

Guest operating systems can reside on physical disk partitions or in virtual disk files.

Hard Disks

- IDE and SCSI hard drives are supported.
- VMware recommends at least 1GB free disk space for each guest operating system and the application software used with it. If you use a default setup, the actual disk space needs are approximately the same as those for installing and running the guest operating system and applications on a physical computer.
- 200MB (Linux) or 1.5GB (Windows) free disk space is required for basic installation. Delete the installer afterwards to reclaim disk space.

Optical CD-ROM/DVD-ROM Drives

- IDE and SCSI optical drives are supported.
- CD-ROM and DVD-ROM drives are supported.
- ISO disk image files are supported.

Floppy Drives

Virtual machines can connect to the host's disk drives. Floppy disk image files are also supported.

Local Area Networking

- You can use any Ethernet controller that the host operating system supports.
- Non-Ethernet networks are supported by using built-in network address translation (NAT) or using a combination of host-only networking plus routing software on the host operating system.

Host Operating System

VMware Workstation is available for Windows and Linux host operating systems. VMware ACE features are included only in the version of Workstation that runs on Windows hosts.

A Web browser is required for the Workstation Help system.

Windows Host Operating Systems

Workstation supports the following Windows 32-bit and 64-bit host operating systems.

Table 1-1. Supported Windows Host Operating Systems

Operating System Type	Operating System Edition
32-bit	Windows 7 Ultimate Edition
	Windows 7 Enterprise Edition
	Windows 7 Professional
	Windows 7 Home Basic and Premium
	Windows Vista Enterprise Edition, SP1, SP2
	Windows Vista Business Edition, SP1, SP2
	Windows Vista Home Basic and Premium Editions, SP1, SP2
	Windows Vista Ultimate Edition, SP1, SP2
	Listed versions are also supported with no service pack.
	Windows Server 2008 Enterprise, SP1, R2
	Windows Server 2008 Standard, SP1, R2
	Windows Server 2003 Standard Edition with SP1, R2, SP2
	Windows Server 2003 Small Business Edition with SP1, R2, SP2
	Windows Server 2003 Enterprise Edition with SP1, R2,SP2
	Windows XP Home Edition with SP2 or later service pack
	Windows XP Professional with SP2 or later service pack
64-bit	Windows 7 Ultimate Edition
	Windows 7 Enterprise Edition
	Windows 7 Professional
	Windows 7 Home Basic and Premium
	Windows Vista Enterprise Edition, SP1, SP2
	Windows Vista Business Edition, SP1, SP2
	Windows Vista Home Basic and Premium Editions, SP1, SP2
	Windows Vista Ultimate Edition, SP1, SP2
	Listed versions are also supported with no service pack.
	Windows Server 2008 Enterprise, SP1, R2
	Windows Server 2008 Standard, SP1, R2
	Windows Server 2003 Standard Edition with SP1, R2, SP2
	Windows Server 2003 Small Business Edition with SP1, R2, SP2
	Windows Server 2003 Enterprise Edition with SP1, R2,SP2
	Windows XP Professional x64 Edition with SP1 or later service pack

Linux Host Operating Systems

Workstation supports the following Linux 32-bit and 64-bit distributions and kernels for the host operating systems. Workstation might not run on systems that do not meet these requirements.

As newer Linux kernels and distributions are released, VMware modifies and tests its products for stability and reliability on those host platforms. VMware makes every effort to add support for new kernels and distributions in a timely manner, but until a kernel or distribution is added to the following list, its use with VMware products is not supported. Look for newer prebuilt modules in the Downloads area of the VMware Web site.

In Workstation 7.0, only Linux kernels version 2.6.9 and later are supported.

Table 1-2. Supported Linux Host Operating Systems

Operating System Type	Operating System Edition
32-bit	Asianux Server 3
	CentOS 5.2
	CentOS 5.1
	CentOS 5.0
	Mandriva 2009
	Mandriva 2008, 2008-1
	Oracle Enterprise Linux 5.2
	Oracle Enterprise Linux 5.1
	Oracle Enterprise Linux 5.0
	Red Hat Enterprise Linux 5.3 WS, AS, ES
	Red Hat Enterprise Linux 5.2 WS, AS, ES
	Red Hat Enterprise Linux 5.1 WS, AS, ES
	Red Hat Enterprise Linux 5.0 WS, AS, ES
	Red Hat Enterprise Linux 4.8 WS, AS, ES
	Red Hat Enterprise Linux 4.7 WS, AS, ES
	Red Hat Enterprise Linux 4.6 WS, AS, ES
	Red Hat Enterprise Linux WS 4.5 (formerly 4.0 Update 5) WS, AS, ES
	SUSE Linux Enterprise Server 11
	SUSE Linux Enterprise Server 10 SP1, SP2
	SUSE Linux Enterprise Desktop 11
	SUSE Linux Enterprise Desktop 10, SP1, SP2
	Listed versions are also supported with no service pack.

Table 1-2. Supported Linux Host Operating Systems (Continued)

Operating System Type	Operating System Edition
32-bit	openSUSE 11.2
	openSUSE 11.1
	openSUSE 11
	openSUSE 10.3
	openSUSE 10.2 (formerly known as SUSE Linux 10.2)
	Ubuntu Linux 9.04
	Ubuntu Linux 8.10
	Ubuntu Linux 8.04, 8.04.1, 8.04.2, 8.04.3
	Ubuntu Linux 6.06
64-bit	Asianux Server 3
	CentOS 5.2
	CentOS 5.1
	CentOS 5.0
	Mandriva 2009
	Mandriva 2008, 2008-1
	Note: On 64-bit Mandriva hosts, some 32-bit compatibility libraries are required. Specifically, 32-bit <code>glibc</code> , <code>X11</code> , and <code>libXtst.so</code> are required.
	Oracle Enterprise Linux 5.2
	Oracle Enterprise Linux 5.1
	Oracle Enterprise Linux 5.0
	Red Hat Enterprise Linux 5.3 WS, AS, ES
	Red Hat Enterprise Linux 5.2 WS, AS, ES
	Red Hat Enterprise Linux 5.1 WS, AS, ES
	Red Hat Enterprise Linux 5.0 WS, AS, ES
	Red Hat Enterprise Linux 4.8 WS, AS, ES
	Red Hat Enterprise Linux 4.7 WS, AS, ES
	Red Hat Enterprise Linux 4.6 WS, AS, ES
	Red Hat Enterprise Linux WS 4.5 (formerly 4.0 Update 5) WS, AS, ES
	SUSE Linux Enterprise Server 11
	SUSE Linux Enterprise Server 10 SP1, SP2
	SUSE Linux Enterprise Desktop 11
	SUSE Linux Enterprise Desktop 10, SP1, SP2
	Listed versions are also supported with no service pack.

Table 1-2. Supported Linux Host Operating Systems (Continued)

Operating System Type	Operating System Edition
64-bit	openSUSE 11.2
	openSUSE 11.1
	openSUSE 11
	openSUSE 10.3
	openSUSE 10.2 (formerly known as SUSE Linux 10.2)
	Ubuntu Linux 9.04
	Ubuntu Linux 8.10
	Ubuntu Linux 8.04, 8.04.1, 8.04.2, 8.04.3
	Ubuntu Linux 6.06
	Note: On 64-bit Ubuntu 6.x hosts, some 32-bit compatibility libraries are required. Specifically, 32-bit <code>glibc</code> and <code>X11</code> are required.

Virtual Machine Specifications

The following sections describe the devices that Workstation virtual machines support.

Processor

- Same processor as that on host computer.
- One virtual processor on a host with one or more logical processors.
- Up to four virtual processors (four-way virtual symmetric multiprocessing, or Virtual SMP) on a host with at least two logical processors.

The following are considered to have two logical processors:

- A multiprocessor host with two or more physical CPUs.
- A single-processor host with a multicore CPU.
- A single-processor host with hyperthreading enabled.

See [“Use Four-Way Virtual Symmetric Multiprocessing”](#) on page 366.

Chip Set

- Intel 440BX-based motherboard
- NS338 SIO
- 82093AA IOAPIC

BIOS

Phoenix BIOS 4.0 Release 6 with VESA BIOS

Memory

You can allocate up to 32GB of memory for a virtual machine, depending on host memory.

No maximum limit for the total available for all virtual machines.

Graphics

VGA and SVGA are supported.

IDE Drives

- Up to four devices—disks, CD-ROM or DVD-ROM (DVD drives can be used to read data DVD-ROM discs; DVD video is not supported).
- Hard disks can be virtual disks or physical disks.
- IDE virtual disks up to 950GB.
- CD-ROM can be a physical device or an ISO image file.

SCSI Devices

- Up to 60 devices.
- SCSI virtual disks up to 950GB.
- Hard disks can be virtual disks or physical disks.
- Generic SCSI support allows devices to be used without need for drivers in the host operating system. Works with scanners, CD-ROM, DVD-ROM, tape drives and other SCSI devices.
- LSI Logic LSI53C10xx Ultra320 SCSI I/O controller.
- Mylex (BusLogic) BT-958 compatible host bus adapter (requires add-on driver from VMware for Windows XP and Windows Server 2003).

Floppy Drives

- Up to two 1.44MB floppy devices.
- Physical drives or floppy image files.

Serial (COM) Ports

- Up to four serial (COM) ports.
- Output to serial ports, Windows or Linux files, or named pipes.

Parallel (LPT) Ports

- Up to three bidirectional parallel (LPT) ports.
- Output to parallel ports or host operating system files.

USB Ports

- USB 1.1 UHCI controller.
- USB 2.0 EHCI controller. (Use the virtual machine settings editor to enable USB 2.0 support. See [“Enable the USB 2.0 Controller for a Virtual Machine”](#) on page 352.)
- Supports most devices, including USB printers, scanners, PDAs, hard disk drives, memory card readers, and digital cameras, as well as streaming devices such as webcams, speakers, and microphones.

Keyboard

104-key Windows 95/98 enhanced.

Mouse and Drawing Tablets

- PS/2 and USB mouse.
- Serial tablets supported.
- USB tablets supported.

Ethernet Card

- Up to 10 virtual Ethernet cards.
- AMD PCnet-PCI II compatible.
- For 64-bit guests: Intel Pro/1000 MT Server Adapter compatible.

Sound

- Sound output and input.
- Emulates Creative Labs Sound Blaster AudioPCI. (Does not support MIDI input or game port controller/joysticks.)

Virtual Networking

- Support for 10 virtual Ethernet switches on Microsoft Windows host operating systems. Support for 255 virtual Ethernet switches on Linux hosts. Three switches are configured by default for bridged, host-only, and NAT networking.
- Support for most Ethernet-based protocols, including TCP/IP, NetBEUI, Microsoft Networking, Samba, Novell NetWare, and Network File System.
- Built-in NAT supports client software using TCP/IP, FTP, DNS, HTTP, and Telnet, including VPN support for PPTP over NAT.

Supported Guest Operating Systems

[Table 1-3](#) provides a simplified list of guest operating systems supported for virtual machines running in Workstation. For the most recent list, including details about specific operating system versions, service packs, and updates supported, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link. The guide also provides notes on installing the most common guest operating systems.

Table 1-3. Guest Operating Systems

Operating System Type	Operating System Edition
Windows 32-bit	Windows 7 Ultimate Edition
	Windows 7 Enterprise Edition
	Windows 7 Professional
	Windows 7 Home Basic and Premium
	Windows Vista Home Basic and Premium
	Windows Vista Business
	Windows Vista Enterprise
	Windows Vista Ultimate
	Windows Server 2008 Standard Edition without Hyper-V
	Windows Server 2008 Datacenter Edition without Hyper-V
	Windows Server 2008 Enterprise Edition without Hyper-V
	Windows Server 2003 Standard Edition
	Windows Server 2003 Small Business Edition
	Windows Server 2003 Web Edition
	Windows Server 2003 Enterprise
	Windows XP Professional
	Windows XP Home Edition
	Windows PE
	Windows RE
	Windows 2000 Professional
	Windows 2000 Server
	Windows 2000 Advanced Server
	Windows NT 4.0 Workstation with SP6
	Windows NT 4.0 Server with SP6
	Windows NT 4.0 Terminal Server Edition with SP6
	Windows Me
	Windows 98
	Windows 95
	Windows 3.1 (with Windows for Workgroups)
Microsoft MS-DOS	MS-DOS

Table 1-3. Guest Operating Systems (Continued)

Operating System Type	Operating System Edition
Windows 64-bit	Windows 7 Ultimate Edition
	Windows 7 Enterprise Edition
	Windows 7 Professional
	Windows 7 Home Basic and Premium
	Windows Vista Home Basic and Premium
	Windows Vista Business
	Windows Vista Enterprise
	Windows Vista Ultimate
	Windows Server 2008 x64 Standard Edition without Hyper-V
	Windows Server 2008 Datacenter x64 Edition without Hyper-V
	Windows Server 2008 Enterprise x64 Edition without Hyper-V
	Windows Server 2003 Standard Edition
	Windows Server 2003 Small Business Edition
	Windows Server 2003 Web Edition
	Windows Server 2003 Enterprise
	Windows Server x64
	Windows XP Professional
	Windows PE
	Windows RE

Table 1-3. Guest Operating Systems (Continued)

Operating System Type	Operating System Edition
Linux 32-bit	Asianux Server
	CentOS
	Mandrake Linux
	Mandriva Linux
	Mandriva Corporate Desktop
	Mandriva Corporate Server
	Novell Linux Desktop
	Oracle Enterprise Linux
	Red Hat Linux
	Red Hat Enterprise Linux Server
	Red Hat Enterprise Linux Advanced Server (AS)
	Red Hat Enterprise Linux Enterprise Server (ES)
	Red Hat Enterprise Linux Workstation
	Red Hat Enterprise Linux Desktop with or without the Workstation Option
	Red Hat Enterprise Linux Advanced Platform
	SUSE Linux
	openSUSE Linux
	SUSE Linux Enterprise Server
	SUSE Linux Enterprise Desktop
	Turbolinux Server
	Turbolinux Enterprise Server
	Turbolinux Workstation
	Turbolinux Desktop
	Ubuntu Linux

Table 1-3. Guest Operating Systems (Continued)

Operating System Type	Operating System Edition
Linux 64-bit	Asianux Server
	CentOS
	Mandriva Linux
	Mandriva Corporate Desktop
	Mandriva Corporate Server
	Oracle Enterprise Linux
	Red Hat Enterprise Linux Server
	Red Hat Enterprise Linux Advanced Server (AS)
	Red Hat Enterprise Linux Enterprise Server (ES)
	Red Hat Enterprise Linux Workstation
	Red Hat Enterprise Linux Desktop with or without the Workstation Option
	Red Hat Enterprise Linux Advanced Platform
	SUSE Linux
	openSUSE Linux
	SUSE Linux Enterprise Server
	SUSE Linux Enterprise Desktop
	Turbolinux Server
	Ubuntu Linux
Novell NetWare 32-Bit	NetWare
Novell Open Enterprise Server 32-bit	Open Enterprise Server 32-bit
FreeBSD 32-bit	FreeBSD 32-bit Note: If you use SCSI virtual disks larger than 2GB with FreeBSD 4.0–4.3, the guest operating system does not boot. To work around this issue, see the <i>VMware Guest Operating System Installation Guide</i> .
FreeBSD 64-bit	FreeBSD 64-bit
Sun 32-bit	Solaris x86 32-bit
	Sun Java Desktop System (JDS)
Sun 64-bit	Solaris x86 64-bit

Support for 64-Bit Guest Operating Systems

Workstation supports virtual machines with 64-bit guest operating systems only on host machines that have one of the supported 64-bit processors. When you power on a virtual machine with a 64-bit guest operating system, Workstation performs an internal check. If the host CPU is not a supported 64-bit processor, you cannot power on the virtual machine.

Workstation supports virtual machines with 64-bit guest operating systems, running on host machines with the following processors:

- Revision D or later of AMD Athlon 64, Opteron, Turion 64, and Sempron
- Intel Pentium 4 and Core 2, and Core i7 processors with EM64T and Intel Virtualization Technology

Workstation supports virtual machines with 64-bit guest operating systems only on host machines that have one of the supported 64-bit processors. When you power on a virtual machine with a 64-bit guest operating system, Workstation performs an internal check. If the host CPU is not a supported 64-bit processor, you cannot power on the virtual machine.

VMware also provides a standalone utility that you can use without Workstation to perform the same check and determine whether your CPU is supported for Workstation virtual machines with 64-bit guest operating systems. Download the 64-bit processor check utility from the downloads area of the VMware Web site.

Workstation supports virtual machines with 64-bit guest operating systems only in versions 6.0 and later. If your version of Workstation is 5.0 or earlier, upgrade to version 6.0 or later for 64-bit guest operating system support. A virtual machine created in Workstation version 6.0 with a 64-bit operating system cannot be powered on or resumed in Workstation versions 5.0 and earlier.

Installing and Upgrading VMware Workstation

2

This chapter discusses how to install Workstation on your Linux or Windows host. This chapter contains the following topics:

- [“Installation Prerequisites”](#) on page 39
- [“Sharing a Workstation Host with Other VMware Products”](#) on page 40
- [“Install Workstation on a Windows Host”](#) on page 41
- [“Install Workstation on a Linux Host”](#) on page 44
- [“Preparing for an Upgrade”](#) on page 47
- [“Upgrade Workstation on a Windows Host”](#) on page 48
- [“Upgrade Workstation on a Linux Host”](#) on page 51

Installation Prerequisites

Installing VMware Workstation is usually a simple process of running a standard installation wizard.

Before you run the installation program, be sure you have the following:

- **A compatible host** – Verify that the computer and host operating system meet the system requirements for running Workstation. See [“Host System Requirements”](#) on page 23.
- **Workstation installation software** – If you have the packaged distribution of Workstation, the installation software is on the installation media in your package. If you have the electronic distribution, the installation software is in the file you downloaded.

Workstation is available for Windows and Linux host computers. The installation files for both host platforms are included in the packaged distribution.

- **Workstation or VMware ACE serial number** – Your serial number is on the registration card in your package. If you purchased Workstation or VMware ACE online, the serial number is sent by email.

Your serial number allows you to use Workstation only on the host operating system for which you licensed the software. For example, if you have a serial number for a Windows host, you cannot run the software on a Linux host.

You need one license for each user.

To use Workstation on a different host operating system, purchase a license on the VMware Web site. You can also obtain an evaluation license at no charge for a 30-day evaluation of the software. For more information, go to the VMware Web site.

If you do not enter the Workstation serial number at installation time (an option available on a Windows host), you are prompted to enter it the first time you attempt to power on a virtual machine.

- **A guest operating system** – After Workstation is installed, you need the operating system installation CDs, DVDs, or ISO image files to set up a guest in a virtual machine.
- **(Optional) Eclipse or Microsoft Visual Studio** – To install the Integrated Virtual Debugger for Eclipse or Visual Studio plug-ins included with Workstation, Eclipse or Visual Studio must be installed on the host before you run the Workstation installer. If you install one or both of these programs after you install Workstation, run the Workstation installer again and select the **Modify** option to install the plug-ins at that time.

For more information about supported versions of Visual Studio and Eclipse, see the following guides on the VMware Web site:

- *Integrated Virtual Debugger for Eclipse Developer's Guide*
- *Integrated Virtual Debugger for Visual Studio Developer's Guide*

Sharing a Workstation Host with Other VMware Products

You cannot have VMware Workstation installed on the same host machine with another VMware product, such as VMware Player, VMware Server, or the VMware Virtual Machine Console. The only VMware products that can share a host machine with Workstation are the VMware VirtualCenter client software and VMware Converter. If you plan to install VMware Workstation on a host machine that already contains another VMware product, you must uninstall that product first.

After you complete the prerequisites and determine which computer you want to use for hosting Workstation, see the appropriate platform-specific installation topic.

Install Workstation on a Windows Host

Before you begin, make sure you have the items listed in [“Installation Prerequisites”](#) on page 39. Although you can enter the serial number after installation, VMware recommends entering it at installation time.

This topic describes how to use an installation wizard to install Workstation. To instead use the command-line interface to perform a silent installation on many computers, see [“Install Workstation Silently”](#) on page 42.

To install Workstation on a Windows host

- 1 Log in to your Microsoft Windows host as the Administrator user or as a user who is a member of the Windows Administrators group.

Log in as local administrator (that is, do not log in to the domain, unless your domain account is also a local administrator).

Although an administrator must install Workstation, a user without administrative privileges can run the program after it is installed.

- 2 From the **Start** menu, choose **Run** and specify the path to either the CD/DVD drive or the downloaded installer file:

- If you are installing from the installation media, enter **D:\setup.exe**, where D: is the drive letter for your CD/DVD drive.
- If you are installing from a downloaded file, browse to the directory where you saved the downloaded installer file, and run the installer.

The filename is similar to `VMware-workstation-<xxxx-xxxx>.exe`, where `<xxxx-xxxx>` is a series of numbers representing the version and build numbers.

On Windows Vista and Windows 7, when the User Account Control dialog box prompts you for permission to run the installer, click **Continue**.

If you have an earlier version of Workstation installed on your system, the installer removes that version before installing the new version. After the uninstallation is complete, you might be prompted to restart your computer before the installer can install the new version.

- 3 When the wizard opens and finishes computing space requirements, click **Next**.

- 4 On the Setup Type page, select **Typical** unless you do not want to install the applicable Workstation IDE plug-ins, or if you have Eclipse or Visual Studio installed in a non-standard location.

If you have Visual Studio or Eclipse installed, the installer installs an integrated virtual debugger. If you do not want a plug-in installed, select the **Custom** setup, and select not to install that component.

If you select **Custom**, you can use the **Space** button to find out how much disk space is required for each component of the installation. Click **Help** for a description of what each type of icon in the list means.

- 5 (Optional) On the Destination Folder page (for typical setups) or the Custom Setup page (for custom setups), if you do not want Workstation installed in the directory that is shown, click **Change** and specify a different directory.

If you specify a directory that does not exist, the installer creates it for you. You cannot install Workstation on a network drive.

- 6 Follow the rest of the wizard prompts.

Some installations might require that you reboot your computer. When you restart, you do not need to log in as a user with Administrator privileges.

Install Workstation Silently

If you are installing Workstation on several Windows host computers and do not want to respond to wizard prompts, you can use the silent installation feature of the Microsoft Windows Installer (MSI). This feature is convenient, for example, in a large enterprise.

Before you begin, ensure that the host computer has version 2.0 or higher of the MSI runtime engine. This version of the installer is available in versions of Windows beginning with Windows XP and is available separately from Microsoft. For additional details on using the Microsoft Windows Installer, see the Microsoft Web site.

To install Workstation silently

- 1 Open a command prompt and enter the following command to silently extract the administrative installation image from the VMware Workstation installer:

```
setup.exe /s /e <install_temp_path>
```

setup.exe is the name of the installer on the installation media. If you are using a downloaded installer, the filename is similar to **VMwareWorkstation-
<xxxx>.exe**, where **<xxxx>** is a series of numbers representing the version and build numbers.

<install_temp_path> is the full path to the folder where you want to store the administrative installation image.

- 2 Enter the following command on one line to run a silent installation using **msiexec** and the administrative installation image you extracted in the previous step:

```
msiexec -i "<install_temp_path>\VMware Workstation.msi"  
[INSTALLDIR="<path_to_program_directory>"] ADDLOCAL=ALL  
[REMOVE=<feature_name,feature_name>] /qn
```

To install Workstation in a location other than the default, change the path that follows **INSTALLDIR=** to specify the location.

Use the optional **REMOVE=<property>** to skip installation of certain features. The **REMOVE=<property>** setting can take one or more of the values listed in [Table 2-1](#).

Table 2-1. Values for the REMOVE Property

Value	Description
Authd	VMware authorization service, which is used to perform tasks when you are not running Workstation as an Administrator user.
Network	Networking components, including the virtual bridge and the host adapters for host-only networking and NAT networking. Do not remove this component if you want to use NAT or DHCP.
DHCP	Virtual DHCP server.
NAT	Virtual NAT device.

If you specify more than one value, use a comma to separate the values. For example, **REMOVE=Authd,NAT**.

If you specify **REMOVE=Network**, the installer skips installation of certain networking components, including NAT and DHCP. You do not need to specify DHCP or NAT separately.

You can customize the installation further by using the format `<property>=<value>` to add any of the installation properties listed in [Table 2-2](#) to the command. A value of 1 means true. A value of 0 means false. If you use the serial number property, enter the serial number with hyphens (xxxxx-xxxxx-xxxxx-xxxxx).

Table 2-2. Property Values

Property	Effect of the Property	Default Value
DESKTOP_SHORTCUT	Installs a shortcut on the desktop.	1
DISABLE_AUTORUN	Disables CD Autorun on the host.	1
REMOVE_LICENSE	(Uninstall only) Removes all stored licenses at uninstall.	0
SERIALNUMBER	Enters the serial number.	

Uninstall Workstation from a Windows Host

Use the Windows Control Panel to uninstall Workstation. Workstation licenses, preference settings, and virtual machines are not removed, but virtual network settings are removed.

To uninstall Workstation from a Windows host

Do one of the following:

- On Windows Vista and Windows 7 hosts, go to **Start > Control Panel > Programs > Programs and Features > Uninstall a program** and uninstall **VMware Workstation**.
- On other Windows hosts, use the Add/Remove Programs item in the control panel and remove **VMware Workstation**.

Install Workstation on a Linux Host

Before you begin, read the following notes and make adjustments to your host system:

- Make sure you have the items listed in [“Installation Prerequisites”](#) on page 39.
- The real-time clock function must be compiled into your Linux kernel.

- Workstation for Linux requires that the parallel port PC-style hardware option (CONFIG_PARPORT_PC) be built and loaded as a kernel module (that is, it must be set to `m` when the kernel is compiled).
- To use the Workstation Help system, you must have a Web browser installed on the host computer.

The installation topic describes an installation from the installation media included in the Workstation media kit. If you downloaded the software, the steps are the same except that you start from the directory where you saved the downloaded installer file, not from the `Linux` directory on the installation media.

The bundle installer lets you install the product in one step. If the GUI-based installer fails, run the installer file with the `--console` option in your terminal.

NOTE On Red Hat Enterprise Linux 5.1 hosts and possibly some other Linux distributions, the bundle-based installer launches a command-line wizard rather than a GUI wizard.

`VMware-Workstation-<xxxx-xxxx>.<architecture>.bundle` is the name of the installer file. In the name, `<xxxx-xxxx>` is a series of numbers that represent the version and build numbers, and `<architecture>` is `i386` or `x86_64`.

To install Workstation on a Linux host

- 1 Log in to your Linux host with the user name you plan to use when running Workstation.

- 2 In a terminal window, become root to perform the initial installation steps:

su or sudo

The command you use depends on your Linux distribution and configuration.

- 3 If you are installing from the installation media instead of a downloaded file, mount the Workstation installation media.
- 4 Change directories to the directory where the installer file is located and run the following command:

sh `VMware-Workstation-<xxxx-xxxx>.<architecture>.bundle`

If you are using the Workstation installation media, this file is in the `Linux` directory.

- 5 Accept the VIX EULA to continue.
- 6 (Optional) If you are using the `--console` option or running a host that does not support the GUI installation do one of the following:
 - To scroll through the VIX EULA, press spacebar and at the end of EULA the **Do you agree? [yes/no]** prompt appears.
 - To exit the VIX EULA press **q** and the **Do you agree? [yes/no]** prompt appears.
- 7 (Optional) Enter the directory path to the Integrated Virtual Debugger for Eclipse if Eclipse is installed.
- 8 Select either **Yes** or **No** to confirm whether you want to install the Eclipse C/C++ debugging plug-in.
- 9 On some Linux distributions, if the installer detects insufficient file descriptors you can update the hard limit for open files on the installer page.

If the hard limit for open files is 1024 or less, the virtual machine may fail if a large number of snapshots are used.
- 10 Click **Install**.

See [“Start Workstation on a Linux Host”](#) on page 54.

Using Command-Line Installation Options

You can also use command-line installation options to install Workstation on a Linux host. To use the options, you must be logged in as root. After finishing the installation process, exit from the root account.

The common command-line installation options are the following:

- `--gtk` – Opens the GUI-based VMware installer, which is the default option.
- `--console` – Allows you to use the terminal for installation.
- `--custom` – Shows all the installation questions. You can customize the installation directories, set or reset the Eclipse directories and hard limit for the number of open file descriptors.
- `--regular` – Shows installation questions that have not been answered before or are required. This is the default option.
- `--required` – Shows only the EULA, then proceeds to install Workstation.
- `--ignore-errors` or `-I` – Allows the installation to continue even if there is an error in one of the installer scripts. However, the section that has an error does not complete, so the component may not be properly configured.

Uninstall Workstation from a Linux Host

When you uninstall Workstation 7.0, product licenses, preference settings, and virtual machines are not removed. A confirmation dialog box appears to check whether to remove or preserve your configurations.

To uninstall Workstation from a Linux host

- If you used the bundle installer, enter the following command:

```
vmware-installer -u vmware-workstation
```

Select either **Yes** or **No** to confirm whether you want to preserve or remove your configuration files.

- If you used the RPM installer to install Workstation 4, 5.x, and 6.x, enter the following commands:

```
rpm -qa | grep VM
```

The VMware Workstation product installer name appears.

```
rpm -e <VMware_Workstation_ product_ installer_name>
```

Preparing for an Upgrade

When you install a new version of Workstation, the previous version is uninstalled but the preferences you set, license files, and virtual machines are not removed. Virtual machines created with an earlier version of Workstation are not deleted, however VMware recommends that you make backup copies in preparation for the upgrade.

VMware recommends that you complete the following tasks before upgrading:

- Make sure all virtual machines are Workstation 4, 5.x, or 6.x virtual machines. Direct upgrades from a Workstation 2 or 3 virtual machine are not supported in Workstation 6.x and 7.0.
- If a virtual machine was created with a version of Workstation earlier than Workstation 5.5 and it has a snapshot, delete the snapshot before upgrading. See [“Delete a Snapshot or a Recording”](#) on page 212.
- For upgrades from Workstation 4, 5.x, or 6.x, if you bridged (mapped) virtual networks to specific physical or virtual adapters, write down the settings you used.

Although Workstation 7.0 generally preserves network settings during the upgrade, it cannot preserve bridge settings created with Workstation 4, 5.x, or 6.x.

- If any virtual machines are suspended, resume them, shut down the guest operating systems, and power them off.
- If any virtual machines are running in the background, start them in Workstation and power them off. See [“Start a Virtual Machine That Is Running in the Background”](#) on page 149.
- Back up the virtual machines by making backup copies of all the files in the virtual machine directories.

This includes .vmdk or .dsk files, .vmx or .cfg files, and .nvram files. Depending on your upgrade path, you might not be able to run your virtual machines under both Workstation 7.0 and your previous version of Workstation.

- Power off all running virtual machines.

You can now use one of the following platform-specific tasks to install Workstation:

- [“Upgrade Workstation on a Windows Host”](#) on page 48
- [“Upgrade Workstation on a Linux Host”](#) on page 51

Upgrade Workstation on a Windows Host

You can upgrade from Workstation version 4, 5.x, or 6.x to Workstation 7.0 by running the VMware Workstation 7.0 installation program.

Before you begin, make sure that you have a Workstation 7.0 serial number. Also perform the tasks described in [“Preparing for an Upgrade”](#) on page 47.

To upgrade Workstation and upgrade the host operating system to Windows Vista and Windows 7, see [“Upgrading to a Windows Vista and Windows 7 Host”](#) on page 49.

To upgrade Workstation on a Windows host

- 1 Log in to your Microsoft Windows host as the Administrator user or as a user who is a member of the Windows Administrators group.
- 2 Launch the Workstation 7.0 installer from your download directory or CD/DVD drive.

Workstation automatically uninstalls the previous version but saves all the network settings except for bridged settings used to map individual virtual networks to specific physical or virtual adapters.

- 3 Reboot your computer if you are prompted to do so, and log in again as the Administrator user or as a user who is a member of the Windows Administrators group.

- 4 Follow the installation wizard prompts to complete the installation.

- 5 Reboot your computer if you are prompted to do so.

You can now log in as you normally do. You do not need to log in as an Administrator now that Workstation is installed.

- 6 If you used bridged settings to map virtual networks to specific physical or virtual adapters, re-create the mappings.

Although Workstation 7.0 generally preserves network settings during the upgrade, it cannot preserve mappings created with Workstation 4, 5.x, or 6.x.

To use Workstation 7.0 to upgrade virtual machines, see [“Change the Version of a Virtual Machine”](#) on page 94.

Upgrading to a Windows Vista and Windows 7 Host

This topic provides instructions for various upgrade scenarios that involve Windows Vista and Windows 7.

During the upgrade from Windows XP to Windows Vista or Windows 7, the location of virtual machines might change. The Windows Vista and Windows 7 upgrade use the registry to map the virtual machines to a new location by using the following paths:

- On Windows XP, the default virtual machine location before the upgrade is: `C:\Documents and Settings\<username>\My Documents\My Virtual Machines`.
- On Windows Vista and Windows 7, the default virtual machine location after the upgrade is: `C:\Users\<username>\Documents\Virtual Machines\<guestOSname>`.

After the upgrade is complete, if the **Favorites** list in Workstation does not work correctly, you can remove the virtual machines from it and add them again.

Upgrade Workstation 5.x on Windows XP to Workstation 7.0 on Windows Vista or Windows 7

As part of the upgrade, you must uninstall the Workstation 5.x application, however the Workstation 5.x virtual machines are not deleted.

To upgrade Workstation 5.x on Windows XP to Workstation 7.0 on Windows Vista or Windows 7

- 1 On the Windows XP host, use the Control Panel's **Add/Remove Programs** item to uninstall Workstation 5.x.
- 2 Upgrade the operating system to Windows Vista or Windows 7, as described in the Microsoft documentation.
- 3 Install Workstation 7.0.
- 4 (Optional) To upgrade the virtual machines, use the Change Version wizard in Workstation 7.0.

See [“Change the Version of a Virtual Machine”](#) on page 94.

Upgrade Workstation 5.x on Windows Vista to Workstation 7.0 on Windows Vista

Because Workstation 5.x was only experimentally supported on Windows Vista, VMware recommends manually uninstalling Workstation 5.x before installing Workstation 7.0.

As part of the upgrade, you must uninstall the Workstation 5.x application, however the Workstation 5.x virtual machines are not deleted.

To upgrade Workstation 5.x on Windows Vista to Workstation 7.0 on Windows Vista

- 1 Go to **Start > Control Panel > Programs > Programs and Features > Uninstall a program**.
- 2 Select **VMware Workstation** and click **Uninstall**.
- 3 Install Workstation 7.0.

See [“Install Workstation on a Windows Host”](#) on page 41.

- 4 (Optional) To upgrade the virtual machines, use the Change Version wizard in Workstation 7.0.

See [“Change the Version of a Virtual Machine”](#) on page 94.

Upgrade Workstation 6.x on Windows XP to Workstation 7.0 on Windows Vista or Windows 7

Before you begin, make sure that you have Windows XP with Service Pack 2.

To upgrade Workstation 6.x from Windows XP to Windows Vista or Windows 7

- 1 Log in as the Administrator user or as a user who is a member of the Windows Administrators group.
- 2 Make sure that Workstation is not running and that no virtual machines are running in the background.
- 3 Upgrade the host operating system to Windows Vista and Windows 7, as described in the Microsoft documentation.
- 4 Run the Workstation 7.0 installer.
- 5 (Optional) To upgrade the virtual machines, use the Change Version wizard in Workstation 7.0.

See [“Change the Version of a Virtual Machine”](#) on page 94.

Upgrade Workstation on a Linux Host

You can upgrade from Workstation version 4, 5.x, or 6.x to version 7.0 by running the VMware Workstation 7.0 installation program.

Before you begin, complete the following:

- Make sure that you have a Workstation 7.0 serial number. You are prompted to enter the serial number after installation is complete, the first time you start Workstation after the upgrade. Also perform the tasks described in [“Preparing for an Upgrade”](#) on page 47.
- If your previous installation was from an RPM installer and you want to install Workstation 7.0, manually uninstall the previous version of Workstation. To manually uninstall Workstation, see [“Uninstall Workstation from a Linux Host”](#) on page 47.

If you currently have Workstation 4, 5.x, or 6.x installed on your system, the older version will be uninstalled automatically before the latest version of Workstation is installed. Workstation 7.0 saves network settings except for bridged settings used to map individual virtual networks to specific physical or virtual adapters.

NOTE Starting with Workstation 5.x, Samba is no longer automatically configured during installation.

To upgrade Workstation on a Linux host

- 1 Run the Workstation bundle installer as you would for a new installation.
- 2 If you used bridged settings to map virtual networks to specific physical or virtual adapters, re-create the mappings.

Although Workstation 7.0 generally preserves network settings during the upgrade, it cannot preserve mappings created with Workstation 4, 5.x, or 6.x.

- 3 (Optional) To upgrade the virtual machines, use the Change Version wizard in Workstation 7.0.

See [“Change the Version of a Virtual Machine”](#) on page 94.

Learning Workstation Basics

3

This chapter discusses launching the Workstation program and introduces the VMware Workstation window. This chapter includes the following topics:

- [“Start Workstation on a Windows Host”](#) on page 53
- [“Start Workstation on a Linux Host”](#) on page 54
- [“Overview of the Workstation Window”](#) on page 54
- [“Check for Product Updates”](#) on page 65
- [“Quickly Create a Virtual Machine and Install an Operating System”](#) on page 66
- [“Introduction to Workstation Preferences”](#) on page 67
- [“Introduction to Virtual Machine Settings”](#) on page 69
- [“Closing Virtual Machines and Exiting Workstation”](#) on page 71
- [“Keyboard Shortcuts”](#) on page 72
- [“Gathering Information for VMware Technical Support”](#) on page 75

Start Workstation on a Windows Host

Depending on the options you selected during installation, you might have a desktop shortcut, a **Start** menu item, a quick launch shortcut, or some combination of these for launching Workstation.

To start Workstation on a Windows host

- 1 From the **Start** menu, choose **Start > Programs > VMware > VMware Workstation**.
- 2 If this is the first time you are launching Workstation, read and accept the end user license agreement (EULA).

Start Workstation on a Linux Host

Whether you can start Workstation from a Linux user interface depends on the Linux distribution. For example, on Red Hat Enterprise Linux 5.1, the **VMware Workstation** menu item is in the **Applications > System Tools** menu.


You can always start Workstation from the command line. Although you must become root to install Workstation, you do not have to be root to start and run Workstation.

To start Workstation on a Linux host

- 1 Open a terminal window.
- 2 Do one of the following:
 - If `/usr/bin` is in your default path, enter the following command:
`vmware &`
 - If `/usr/bin` is not in your default path, enter the following command:
`/usr/bin/vmware &`
- 3 Read and accept the end user license agreement (EULA).

Overview of the Workstation Window

A Workstation virtual machine is like a separate computer that runs in a window on your physical computer. However, Workstation displays more than the screen of another computer. From the Workstation window, you can access and run virtual machines and teams of virtual machines. You can also switch easily from one virtual machine to another.

Figure 3-1. VMware Workstation Window

The VMware Workstation window contains the following sections:

- **Home page, summary, console, or appliance view** – Main part of the window that shows the virtual machines.
- **Tabs** – Each open virtual machine has a tab. Click a tab to make that virtual machine active. Click the **Close** button to close the tab. Depending on how you configure Workstation, the virtual machine is then either powered off or continues to run in the background.
- **Sidebar** – Bookmark your favorite virtual machines and teams of virtual machines for quick access. You can also see which virtual machines are powered on. Right-click context menus enable you to perform many operations on a selected virtual machine. An additional section of the sidebar displays ACE Management Servers.
- **Status bar** – Displays Workstation messages and an icon for each removable device. You can click or right-click an icon to disconnect it or edit its configuration.
- **Message log**— A note icon indicates whether any unread messages are present in the message log for the selected virtual machine. If the icon is dimmed, all messages were read. To open the message log, right-click the icon and choose **Open Message Log**. Alternatively, from the menu bar, choose **VM > Message Log**.

Messages include warning information about the virtual machine, such as **Could not connect to the floppy drive.** or **No bootable device was detected.** Select an item in the message log to see a detailed description of the message.

Home Page and Views

Workstation displays one of four views in the main part of the window: the home page, the summary view, the console view, or the appliance view.

Home Page

Click the **Home** tab to display the Workstation home page. Use the icons on the home page to start creating a new virtual machine or open an existing virtual machine.

To close the home page, click the X to the right of the tabs on a Windows host or the X on the tab on a Linux host. To display the home page again, choose **View > Go to Home Tab**.

Summary View


When you select a tab for a powered-off virtual machine or team of machines, Workstation displays only a summary of the configuration information about that item. Workstation also displays a summary for a suspended virtual machine or team. Click the **Summary** button in the toolbar at any time to examine settings in the summary view.

Summary views appear only for virtual machines that are currently open. See [“Starting a Virtual Machine”](#) on page 148. The summary or console view remains visible as long as the virtual machine remains open.

[Figure 3-2](#) shows an example of the summary view.

Figure 3-2. Summary View for a Virtual Machine on a Windows Host

Summary View button




The **Commands** section gives you access to the most-often used commands from the **VM** menu. On Windows hosts, for ACE-enabled virtual machines, this includes commands for creating security policies and virtual machine packages to deploy to end users, as well as a command for previewing the ACE-enabled virtual machine in VMware Player.

The section that includes the **Devices**, **Options**, and (sometimes) **ACE** and **Packages** tabs enables you to review configuration settings quickly. Double-click an item on the tab to display the item's configuration panel and change a setting.

Console View

The console view for an active virtual machine is like the monitor display of a physical computer.

Figure 3-3. Console View on a Windows Host



When a virtual machine is active, the name of the virtual machine or team of virtual machines appears in a tab at the top of the console. To switch from the active virtual machine or team, click the tab of another virtual machine or team. You can use the console tabs in the window mode and also in the quick switch mode.

Appliance View

If you set up the virtual machine to act as an appliance, such as a Web server with a browser-based console, you can specify that the default view is an appliance view. The appliance view gives a brief description of the type of server or appliance. It also provides a link that opens the browser on the host system and connects to the appliance's management console.

The appliance view is available only for virtual machines that you designate as appliances. See [“Configure the Appliance View for a Virtual Machine”](#) on page 182.

Displaying Multiple Virtual Machines at the Same Time

To simultaneously view more than one virtual machine when they are not all on the same team, open multiple Workstation windows and launch one or more virtual machines in each Workstation window.

Use a team of virtual machines to coordinate and use multiple virtual machines within a single console window. See [“Summary and Console Views for Teams and Their Virtual Machines”](#) on page 276.

Toolbar Buttons

The toolbar area at the top of the VMware Workstation window contains buttons to power virtual machines on and off, change the Workstation display, manage snapshots, and record virtual machine activity.

Figure 3-4. Workstation Toolbars





Figure 3-5. ACE Toolbar (Windows Hosts Only)



If you point to a toolbar button, a tooltip appears and displays the name of the button. To change which buttons appear, see [“Customize the Toolbar on a Windows Host”](#) on page 62 and [“Customize the Toolbar on a Linux Host”](#) on page 61.

The **Power** toolbar contains the following buttons:

- **Power Off** – Turns off the active virtual machine or team like the power button on a physical PC. You can configure Workstation for a soft power off (called shut down) or a hard power off (called power off). See [“Shut Down a Virtual Machine”](#) on page 151 or [“Power Off or Close a Team”](#) on page 274.
- **Suspend** – Stops a virtual machine or team in a manner that allows you to resume your work later. See [“Using the Suspend and Resume Features”](#) on page 201.

- **Power On or Resume** – Powers on a selected virtual machine or team that is powered off, or resumes a virtual machine or team that is suspended. See [“Starting a Virtual Machine”](#) on page 148, [“Power On a Team”](#) on page 279, and [“Using the Suspend and Resume Features”](#) on page 201.
- **Reset** – Resets a virtual machine or team like the reset button on a physical PC. See [“Configure Power Off and Reset Options for a Virtual Machine”](#) on page 152.

The **Snapshot** toolbar contains the following buttons:

- **Take Snapshot** – Enables you to save the state of a virtual machine in the same manner you might save a word-processing document. You can return to that state if you make a mistake by using the **Revert** button. See [“Using Snapshots”](#) on page 203.
- **Revert** – Allows you to return a virtual machine to the parent state, a state previously preserved by taking a snapshot. See [“Using Snapshots”](#) on page 203.
- **Manage Snapshots** – Opens the snapshot manager, where you can view the virtual machine's existing snapshots, revert to a snapshot, take a new snapshot, and make a clone from a snapshot. See [“Snapshot Manager Overview”](#) on page 208.

The **View** toolbar contains the following buttons:

- **Show or Hide Sidebar** – Toggles between showing and hiding the sidebar. See [“View the Sidebar”](#) on page 62.
- **Quick Switch** – Enlarges the Workstation console to cover the entire host monitor. Console tabs enable you to switch between virtual machines and teams with a single click. See [“Use Quick Switch Mode”](#) on page 165.
- **Full Screen** – Enlarges the virtual machine display to cover the entire host monitor. The virtual machine no longer appears in a window. See [“Use Full Screen Mode”](#) on page 162.
- **Unity** – Integrates your favorite guest applications with your host's desktop so that guest application windows look just like host application windows, but with color-coded borders. See [“Using Unity Mode”](#) on page 158.
- **Summary View** – Displays the summary view. See [“Summary View”](#) on page 56.
- **Appliance View** – Displays the appliance view. See [“Appliance View”](#) on page 58.
- **Console View** – Displays the console view. See [“Console View”](#) on page 58.

The **Replay** toolbar contains the following buttons:

- **Replay Last Recording** – Plays the last recording made for this virtual machine.
- **Record** – Begins recording the activity of this virtual machine.

For information about the record/replay feature, see [Chapter 12, “Recording and Replaying Virtual Machine Activity,”](#) on page 257.

The **ACE** toolbar, which is available on Windows hosts only, contains the following buttons:

- **Edit Policies** – Opens the policy editor.
- **Edit Deployment Settings** – Opens the deployment settings editor.
- **Create New Package** – Opens the New Package wizard.
- **Create Pocket ACE Package** – Opens the Pocket ACE Package wizard.
- **Preview in Player** – Allows you to run an ACE instance as it will run on the user’s machine. Using preview mode also allows you to view the effects of changed policies as they will appear on the user’s machine.

See [Chapter 18, “Learning the Basics of VMware ACE,”](#) on page 381.

Customize the Toolbar on a Linux Host

You can customize the Workstation toolbar by adding, removing, and rearranging toolbar buttons. On a Linux host, all the buttons are contained in a single toolbar.

To customize the toolbar on a Linux host

- 1 Right-click the far-right side of the toolbar to display a **Toolbar** menu.
- 2 Click **Power**, **Snapshot**, **View**, or **Replay** to add or remove that toolbar.

When a toolbar name is checked, the corresponding buttons appear in the interface.
- 3 In the Desktop Style part of the menu, choose the display style for toolbar buttons.

Customize the Toolbar on a Windows Host

You can customize the Workstation toolbar by adding, removing, and rearranging toolbar buttons.

To customize the toolbar on a Windows host

- 1 Right-click any part of the toolbar to display a **Toolbar** menu.
- 2 Click **Power**, **Snapshot**, **ACE**, **View**, or **Replay** to add or remove that toolbar.

When a toolbar is checked, it appears in the interface.

To change which buttons appear in a toolbar or the order in which they appear, display that toolbar and continue with the following steps.

- 3 Right-click the **Power**, **Snapshot**, **ACE**, **View**, or **Replay** toolbar to open the Customize Toolbar dialog box.

Buttons listed under **Current Toolbar Buttons** appear in the toolbar, in the order shown in the Customize Toolbars dialog box.

- 4 Do any of the following:
 - To add or remove a button from the toolbar, select the button and click **Add** or **Remove**. Add a separator to display a vertical line between the buttons.
 - To change the order of the buttons, select any button under **Current Toolbar Buttons** and click **Move Up** or **Move Down**.
 - To change the order of the currently displayed buttons without opening the Customize Toolbar window, hold down the Shift key while you drag a button to a different location in the toolbar.
 - To restore the default setup, with all buttons displayed, click **Reset**.
- 5 Click **Close**.

View the Sidebar

The sidebar contains a list of favorites and shows which virtual machines or teams of virtual machines are currently powered on. On Windows hosts, an additional section of the sidebar displays ACE Management Servers. For more information, see the *VMware ACE Management Server Administrator's Manual*.

To view the Sidebar

Choose **View > Sidebar**.

If the sidebar was hidden, it becomes visible. If it was visible, it is hidden.








Favorites List in the Sidebar

The **Favorites** list lets you organize and access frequently used items.

The **Favorites** list provides the following benefits:

- **Fast access** – Quickly access frequently used items. With your virtual machines and teams on the **Favorites** list, you can open them without browsing the host file system. Also like browser bookmarks, **Favorites** list icons can be organized in folders, added, rearranged, or deleted.
- **Status** – Different icons indicate the status of virtual machines and teams. A **Favorites** list icon indicates whether the team or virtual machine is powered off, powered on, or suspended. A brown (rather than blue) virtual machine icon indicates that the virtual machine is a Workstation 4 virtual machine.

Table 3-1. Icon Status in the Favorites List

	Powered off Workstation 5.x, 6.x, or 7.x virtual machine or full clone. To determine the exact version, use the summary view's Version field.
	Powered off virtual machine created as a linked clone of another virtual machine.
	Powered off team of virtual machines.
	Powered off Workstation 4 virtual machine.
	Powered on indicator can appear for virtual machines and teams.
	Suspended indicator can appear for virtual machines and teams.
	Unavailable indicator can appear if a virtual machine or team gets corrupted or moved from the location that was used to create the favorites item. The indicator also appears if the virtual machine is already open in VMware Player or is opened by another user.

- **Right-click commands** – Right-click on a **Favorites** icon to display a menu of commands you can use for that virtual machine or team. You can click elsewhere in the **Favorites** list (that is, not on a virtual machine or team) to display a context menu from which you can choose to create a new virtual machine, team, or folder. You can also open an existing virtual machine, team, Microsoft Virtual PC or Virtual Server virtual machine, StorageCraft, or Symantec Backup Exec System Recovery system image.

Use Folders for Organizing Favorites

You can organize favorites into folders and nest folders inside other folders.

To use folders for organizing favorites

- 1 Right-click **Favorites** (or any item in the **Favorites** list), and choose **New Folder**.
- 2 Complete the New Folder dialog box that appears.
- 3 (Optional) Drag and drop folders to place one inside another.
- 4 Drag and drop Favorites items in the desired folder.

Add Virtual Machines and Teams to the Favorites List

Virtual machines and teams are automatically added to the **Favorites** list when you complete the New Virtual Machine wizard. You can also add them manually.

To add virtual machines and teams to the Favorites list

- 1 Choose **File > Open** and browse to the location of the virtual machine (.vmx file) or team (.vmtm file).
- 2 Click **Open**.
- 3 Choose **File > Add to Favorites**.

Remove an Item from the Favorites List

You can remove the name of a virtual machine or team from the **Favorites** list regardless of whether the virtual machine or team is open or powered on. Removing the name does not affect the virtual machine's files or operation.

To remove an item from the Favorites list

- 1 Click a name in the **Favorites** list to select it.
- 2 Choose **File > Remove from Favorites**.

Rename an Item in the Favorites List

Renaming an item in the **Favorites** list also renames the virtual machine or team.

To rename a Favorite list entry for a virtual machine or a team

- 1 Right-click the **Favorites** item to rename.
- 2 Choose **Rename** from the context menu.
- 3 Type the new name for the item and press Enter.

Powered On List

This list in the sidebar enables you to find out which virtual machines or teams are currently powered on. Right-click items in the **Powered On** list to display a menu of commands you can use for that virtual machine or team.

Check for Product Updates

Workstation automatically checks for product updates every three days. If an update check fails on two consecutive attempts, you receive a notification.

NOTE Checking for product updates works only if the host computer is connected to the Internet.

To check for product updates

- 1 (Optional) To check for updates immediately, choose **Help > Check for Updates on the Web**.
- 2 To configure Workstation to periodically check for updates, choose **Edit > Preferences > Updates**.
- 3 In the **Software updates** section, select **Check for new version of VMware Workstation on startup** and click **OK**.

Quickly Create a Virtual Machine and Install an Operating System

The instructions in this section get you started quickly with creating a virtual machine and installing a guest operating system. After you create a virtual machine, you will find the information in the rest of this chapter easier to understand.

The instructions tell you to accept the default settings so that you can complete the New Virtual Machine wizard quickly. The purpose is to learn about Workstation. Later, when you want to create virtual machines that you actually use in your work or production environment, you can learn about all the options available. This information is provided in [Chapter 4, “Creating and Upgrading a Virtual Machine,”](#) on page 79.

For simplicity, use a Windows installation CD or ISO image file for the operating system you install in the virtual machine. Most Windows operating systems fit on one CD, whereas Linux requires multiple CDs. If you want to use a Linux guest operating system, use installation media for one of the newer versions of Red Hat, SUSE Linux, or Ubuntu. The easy install feature is supported for these operating systems.

To quickly create a virtual machine

- 1 To use an installation CD or DVD for the operating system, rather than an ISO image file, insert the CD or DVD in the host CD-ROM drive.
- 2 Start VMware Workstation.

For instructions, see [“Start Workstation on a Windows Host”](#) on page 53 or [“Start Workstation on a Linux Host”](#) on page 54.
- 3 Choose **File > New > Virtual Machine**.
- 4 On the Welcome page, select **Typical** and click **Next**.
- 5 On the Guest Operating system Installation page, select **Installer disc** or **Installer disc image file**, as appropriate, and click **Next**.
- 6 Complete the fields on the Easy Install Information page.

Specifying a password is optional. On Windows, the password you enter here is used for an account with Administrator permissions. On Windows 2000, the password is used for the Administrator account.
- 7 Accept the defaults on the rest of the wizard pages.

The virtual machine is created and its name is added to the **Favorites** list.

The console view for the virtual machine appears. Soon the boot device (such as the CD-ROM) is detected and installation of the operating system begins.

On Windows 2000 guests, if you entered a password when completing the New Virtual Machine wizard, then when the operating system starts up, it might prompt you to enter an Administrator password. Use the password that you created when completing the New Virtual Machine wizard.

After installation is finished, VMware Tools is automatically installed.

Now that you have a virtual machine with a guest operating system installed, you can refer to it as you read the rest of the topics in this chapter.

Introduction to Workstation Preferences

The Preferences dialog box appears when you choose **Edit > Preferences**. It lets you change a number of settings that apply to Workstation, no matter which virtual machine you are running.

The default settings for Workstation preferences are correct for most cases. Do not change settings unless you are an experienced user.

NOTE On a Linux host, you must be logged in as root to save global preference changes.

Following is a list of the tabs in the Preferences dialog box, along with cross-references to the sections of this manual that pertain to each tab:

- **Workspace** tab – Lets you configure the following settings:
 - **Location** section – Lets you change the directory in which newly created virtual machines are stored. See [“Virtual Machine Location”](#) on page 83 and [“Files That Make Up a Virtual Machine”](#) on page 97.
 - **Virtual Machines** section – Several of these options have to do with exiting Workstation while leaving some virtual machines powered on. See [“Closing Virtual Machines and Exiting Workstation”](#) on page 71. For information about enabling shared folders, see [“Set Up Shared Folders”](#) on page 191.
- **Input** tab – Lets you adjust the way the virtual machine captures control of keyboard and mouse. For example, by default the virtual machine grabs keyboard and mouse input when you click in the virtual machine window.

- **Hot Keys** tab – Lets you specify the key combination that is used with hot-key sequences for all your virtual machines. Use hot-key combinations to enter and leave full screen mode, ungrab mouse and keyboard input, and so on. See [“Keyboard Shortcuts”](#) on page 72.
- **Display** tab – Lets you adjust the manner in which the console and the host display accommodate a different guest operating system display resolution.
Also see [“Fitting the Workstation Console to the Virtual Machine Display”](#) on page 169 and [“Use Full Screen Mode”](#) on page 162.
- **Memory** tab – For details on adjusting memory settings in Workstation, click **Help** on this tab. On Linux, you must be running Workstation as root in order to change these settings.
- **Priority** tab – For information about the snapshot settings on this tab, see [“Enable or Disable Background Snapshots”](#) on page 206. On Linux, you must be running Workstation as root in order to change this setting.

For information about the process priority settings available on Windows hosts, click **Help** on this tab.

- **Updates** tab – Lets you specify whether to automatically update VMware Tools and download other components on Windows and Linux guest systems when a new version becomes available. On Linux hosts, you must be running Workstation as root in order to change these settings.

VMware Tools is a suite of utilities that enhances the performance of the virtual machine's guest operating system and improves management of the virtual machine. See [Chapter 5, “Installing and Using VMware Tools,”](#) on page 101.

- **Devices** tab – (Windows hosts only) By default, the Autorun feature on the host is disabled. Therefore, when you insert a CD or DVD in the CD/ DVD-ROM drive, the Autorun feature is not available. You can open the CD or DVD on the host using Windows Explorer.

In addition to the cross-references mentioned in this list, more information about the settings on each tab is available in the Workstation online help. Click **Help** in the Preferences dialog box.

The settings on the following tabs apply only to the user currently logged on to the host computer: **Workspace** tab, **Input** tab, **Hot Keys** tab, **Priority** tab, and **Tools** tab.

The settings on the following tabs apply no matter which virtual machine is running or which user is logged on to the host computer: **Display** tab, **Memory** tab, and **Devices** tab.

Introduction to Virtual Machine Settings


Workstation configures a new virtual machine based on the guest operating system you select in the New Virtual Machine wizard. After the virtual machine is created, you can use the virtual machine settings editor to change many configuration options set by the wizard. The virtual machine settings editor appears when you select a virtual machine and choose **VM > Settings**.

On guests with Windows XP and later versions, if you make changes to the virtual machine configuration after activating the guest you might have to reactivate it. To minimize the changes, set the final memory size for the virtual machine and install VMware Tools before you activate the guest.

Hardware Tab

Use the **Hardware** tab to add, remove, and configure virtual devices for the selected virtual machine.

Figure 3-6. Virtual Machine Settings Hardware Tab




When you select an item in the **Hardware** list, the options that correspond to the item appear on the right side of the dialog box. For example, in [Figure 3-6](#), memory options appear because the **Memory** item is selected.

Topics and chapters related to each of the virtual devices in the **Hardware** list are provided later in this manual. To display online help for an item you select in the **Hardware** list, click **Help**.

Options Tab

The **Options** tab lets you adjust characteristics of the selected virtual machine:

- Many options control interactions between the host and the guest operating system, such as how folders can be shared, how files are transferred, and what happens to a guest operating system when you exit Workstation.
- Some options let you override similar Preferences dialog box options, which are global preferences set for all virtual machines. For example, you can use the **Advanced** option to override the process priorities set on the **Priority** tab in the Preferences dialog box.
- Some options let you change settings you might initially make when running the New Virtual Machine wizard to create a virtual machine. For example, you can use the **General** options to change the name of the virtual machine.

Figure 3-7. Virtual Machine Settings Options Tab

The settings for the virtual machine **Options** tab are discussed later in this manual, in the task-specific topics and procedures where you would use them. To display online help for an item you select in the **Options** list, click **Help**.

Closing Virtual Machines and Exiting Workstation

When you close a virtual machine or team, and when you exit Workstation, if any virtual machines are still powered on, you are prompted to specify one of the following actions to take:

- Continue running the virtual machine in the background. If a virtual machine continues running after you exit Workstation, you can still interact with it through virtual network computing (VNC) or some other service.
- Suspend the virtual machine. The suspend operation saves the state of the virtual machine. See [“Using the Suspend and Resume Features”](#) on page 201.
- Power the virtual machine off. If you configured the power operation to do a “soft” power-off, a VMware Tools script runs in order to cleanly shut down the guest operating system before powering off. See [“Configure Power Off and Reset Options for a Virtual Machine”](#) on page 152.

To avoid receiving a prompt every time you exit Workstation or close a virtual machine or team, set a preference for virtual machines to always run in the background when you exit.

Set a Virtual Machine to Run in the Background

You can set a virtual machine that is powered on to continue running in the background when you close a virtual machine or team tab, or when you exit Workstation. You can still interact with it through VNC or another service.

By default, when virtual machines run in the background, a status icon appears in the notification area of the taskbar. Point to the icon to display a tooltip that shows the number of virtual machines and teams that are running in the background. These are the virtual machines and teams that belong to the user who is logged in.

To set a virtual machine to run in the background

Do one of the following:

- Click **Run in Background** at the prompt when you close the virtual machine or exit Workstation.
- Set a Workstation preference:
 - a From the VMware Workstation menu bar, choose **Edit > Preferences**.
 - b On the **Workspace** tab, select **Keep VMs running after Workstation closes** and click **OK**.

When you close a tab or exit Workstation, you no longer receive a prompt.

Keyboard Shortcuts

You can use keyboard shortcuts to interact with Workstation and with virtual machines. Most of the available keyboard shortcuts for Workstation are listed next to their associated commands in Workstation menus.

Hot keys, or keyboard shortcuts for interactions with virtual machines, are shown in [Table 3-2](#). Hot-key combinations can be used to do the following:

- Switch between virtual machines
- Enter and exit full screen mode
- Ungrab input
- Send Ctrl+Alt+Del to the virtual machine only (and not to the host)
- Send commands to the virtual machine only (and not to the host)

By default, most hot-key combinations include Ctrl+Alt, but you can change this combination. See [“Change the Hot-Key Combination”](#) on page 74.

If you change the Preferences setting for the hot-key combination, substitute your new setting for Ctrl+Alt as needed in the shortcuts listed in [Table 3-2](#). For example, if you change the hot-key combination to Ctrl+Shift+Alt, you must press Ctrl+Shift+Alt+spacebar to have Workstation not process a command.

Table 3-2. Hot-Key Combinations

Shortcut	Action
Ctrl+G	Grab input from keyboard and mouse.
Ctrl+Alt	Release the mouse cursor. If the virtual machine is in the type of full screen mode called exclusive mode, pressing Ctrl+Alt changes the virtual machine from exclusive mode to windowed mode.
Ctrl+Alt+Insert	Shuts down or (depending upon the guest operating system) logs out of the guest. This command is received solely by the virtual machine. Note: For this and all shortcuts that include Ctrl+Alt, changing the hot-key combination changes the sequence you need to use. For instance, if you change the hot-key combination to Ctrl+Shift+Alt, you must press Ctrl+Shift+Alt+Insert to end the guest operating system session.
Ctrl+Alt+Delete	Shuts down or (depending upon the operating system) logs out of the guest operating system. On Windows hosts, if you are not using the enhanced virtual keyboard feature, this command is received by both the host operating system and the virtual machine, even when Workstation has control of input. You can cancel the ending of the host operating system's session and return to the virtual machine to log out or shut down or perform administrative tasks.
Ctrl+Alt+spacebar	Sends any command to the virtual machine so that Workstation does not process it. Hold down Ctrl+Alt as you press and release the spacebar, and continue to hold the Ctrl+Alt keys down as you press the next key in the combination.
Ctrl+Alt+Tab	Switch among open virtual machines while mouse and keyboard input are grabbed.
Ctrl+Tab Ctrl+Shift+Tab	On Windows hosts, switch among open virtual machines while mouse and keyboard input are not grabbed. Workstation must be the active application.
Ctrl+Alt+right arrow	In full screen mode, switch to the next powered-on virtual machine.
Ctrl+Alt+left arrow	In full screen mode, switch to the previous powered-on virtual machine.
Ctrl+Shift+U	In Unity mode, gives access to the virtual machine Start or Applications menu.

Change the Hot-Key Combination

Hot-key combinations, or shortcut keys, are key combinations you press to interact with virtual machines. For a list of actions you can invoke by using hot keys, see [Table 3-2](#).

By default, most hot-key combinations include Ctrl+Alt, but you can change this combination. For example, you can change the setting so that all hot-key combinations use Ctrl+Shift+Alt. This is useful if you want to prevent certain key combinations (such as Ctrl+Alt+Del) from being intercepted by Workstation instead of being sent to the guest operating system.

The hot-key preferences you set in the preferences editor apply to virtual machines you access from within Workstation. These settings do not affect virtual machines or ACE instances distributed to other users.

To change the hot-key combination

- 1 Choose **Edit > Preferences**.
- 2 Click the **Hot Keys** tab.
- 3 Use the following information to help you choose a key combination:

Custom key combinations involve using a combination of the Ctrl, Shift, Alt, and Windows keys. The Windows key is the key between the Ctrl and Alt keys on your keyboard. The modifiers for the custom combination are:

- **Down** – The key must be pressed to use the hot-key sequence.
- **Up** – The key must not be pressed to use the hot-key sequence.
- **Either** – The key can be up or down. This modifier is useful to allow users a variety of keystrokes to leave full screen mode. For example, selecting **Either** for the Shift key means that both Ctrl+Alt+Enter and Ctrl+Shift+Alt+Enter cause Workstation to exit full screen mode.

If you select **Either** for all of the keys (Ctrl, Alt, Shift, and Win) in the custom combination, you can use the Esc key to release the cursor.

- 4 (Optional) To set a hot-key preference for the Unity application menu, enter your custom key combination in the **Unity applications menu hot key** field, or use the default combination **Ctrl + Shift + U**.
- 5 Click **OK**.

Gathering Information for VMware Technical Support

When you need help from VMware technical support, VMware recommends that you create a support request. For some problems, the representative will ask you to turn on debugging, run a script to collect log files, and send the logs to VMware.

Register and Create a Support Request

Before you can report problems to the VMware support team, you must register for a VMware account.

Before you begin, locate the serial number. It is on the registration card in your package. If you purchased Workstation online, the serial number is sent by email.

To register and create a support request

- 1 From the Workstation menu bar, choose **Help > VMware on the Web > Register Now!**
- 2 Follow the instructions on the Web site.
- 3 To report problems, from the Workstation menu bar, choose **Help > VMware on the Web > Request Support**.

Gather Debugging Information for a Virtual Machine

Workstation provides several levels of logging to help diagnose and troubleshoot various types of problems.

You can use full debugging mode to gather the greatest amount of data, which is useful when a virtual machine freezes or powers off unexpectedly. You can use statistics mode to gather performance statistics when virtual machines run slowly. You can also increase logging without going into full debugging mode. A VMware technical support representative can tell you which level to use.

After you gather debugging information, you can send the log files to VMware technical support.

To gather debugging information for a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off or suspended.
- 3 Choose **VM > Settings**.
- 4 On the **Options** tab, select **Advanced**.

- 5 Select from the **Gather debugging information** drop-down menu or the **Log virtual machine progress periodically** check box, as directed by VMware technical support.

Using full debugging mode and logging progress periodically cause a decrease in performance.

- 6 In the **File locations** section, note the directory path to the log file.

To view the complete path, click in the read-only text box and use the right arrow key to scroll through the path.

- 7 Click **OK**.

Running the Support Script

To help diagnose a problem, the VMware support team might ask you to run a support script to gather information. For example, if a virtual machine exits abnormally or fails, run the support script to collect the appropriate log files and system information.

In Workstation 7.0, you can run the support script by selecting **Help > Collect Support Data**. You can also run the script from the command line.

Run the Support Script from the Workstation User Interface

Run the support script only when requested to do so by VMware technical support.

The support collection script collects data from all of the virtual machines you select and from your host machine, and stores all of the data in a single file. On Windows hosts, after the script finishes running, it creates a .ZIP file of the collected data and displays the file in an open Windows Explorer window. The default location of the .ZIP file:

- On Windows XP is
C:\Documents and Settings\\Local Settings\Temp\vmware-support\
- On Windows Vista and Windows 7 is
C:\Users\\AppData\Local\Temp\vmware-support\

On Linux hosts, the script creates a compressed .TGZ file in the user's home directory. Because the script is not run as root, the script displays messages indicating that it cannot collect some information. This is normal. If the VMware support team needs that information, a support representative asks you to run the script from the command line as root. For instructions, see [“Run the Support Script from a Linux Terminal Window”](#) on page 78.

Before you begin, create a support request. See [“Register and Create a Support Request”](#) on page 75. Increase the level of logging, as described in [“Gather Debugging Information for a Virtual Machine”](#) on page 75. Make sure that the latest VMware Tools is installed in the virtual machines to collect support data from the guest and that the virtual machines are powered on.

To run the support script from the Workstation user interface

- 1 Select **Help > Collect Support Data**.

A dialog box displays all your open Workstation virtual machines.

- 2 Check the boxes for the virtual machines to collect support data from and select **Collect**.
 - If you select **Collect** with no virtual machines selected, the support collection script collects data only from your host machine.
 - If you select a check box for a virtual machine and select **Collect**, the support collection script collects the current data from the your guest and host machines.

The virtual machine must be powered on and have the latest VMware Tools running. VMware recommends that you use this option to collect the current data for your guest machine.

- 3 Add the .ZIP or .TGZ data file to your support request.

Run the Support Script from a Windows Command Prompt

Run this script only when requested to do so by VMware technical support.

Before you begin, create a support request. See [“Register and Create a Support Request”](#) on page 75. Increase the level of logging, as described in [“Gather Debugging Information for a Virtual Machine”](#) on page 75.

To run the support script from a Windows command prompt

- 1 Open a command prompt.
- 2 Change to the VMware Workstation program directory:

```
C:
cd \Program Files\VMware\VMware Workstation
```

If you did not install the program in the default directory, use the appropriate drive letter and path in the `cd` command above.

- 3 Run the support script:

```
cscript vm-support.vbs
```

After the script runs, it displays the name of the directory where it has stored its output.

- 4 Use a file compression utility such as WinZip or PKZIP to zip the script output directory, and include the zip file with your support request.

If you are reporting a problem you encountered while installing VMware Workstation, also include the installation log file.

On a Windows host, the file is `VMInst.log`. It is saved in the `Temp` folder. On a Windows XP or Windows Server 2003 host, the default location is `C:\Documents and Settings\<username>\Local Settings\Temp`.

You can use the command `cd %temp%` to locate the `Local Settings` folder, which is hidden by default. To see its contents, open **My Computer**, go to **Tools > Folder Options**, click the **View** tab and select **Show Hidden Files and Folders**.

Run the Support Script from a Linux Terminal Window

Run this script only when requested to do so by VMware technical support.

Before you begin, create a support request. See [“Register and Create a Support Request”](#) on page 75. Increase the level of logging, as described in [“Gather Debugging Information for a Virtual Machine”](#) on page 75.

To run the support script from a Linux terminal window

- 1 Open a terminal window.
- 2 Run the support script as the user who is running the virtual machine:

```
vm-support
```

If you are not running the script as root, the script displays messages indicating that it cannot collect some information. This is normal. If the VMware support team needs that information, a support representative will ask you to run the script again as root.

The script creates a compressed `.TGZ` file in the user's home directory.

- 3 Include that output file with your support request.

If you are reporting a problem you encountered while installing Workstation, also include the installation log file.

Creating and Upgrading a Virtual Machine

4

This chapter describes how to create a virtual machine by using the New Virtual Machine wizard. It also provides general information about installing guest operating systems.

This chapter includes the following topics:

- [“Methods of Creating Virtual Machines”](#) on page 79
- [“Configuration Options for the New Virtual Machine Wizard”](#) on page 80
- [“Use the New Virtual Machine Wizard”](#) on page 89
- [“Installing a Guest Operating System”](#) on page 89
- [“Upgrade a Guest Operating System”](#) on page 94
- [“Change the Version of a Virtual Machine”](#) on page 94
- [“Using an Older-Version Virtual Machine Without Upgrading”](#) on page 96
- [“Files That Make Up a Virtual Machine”](#) on page 97

Methods of Creating Virtual Machines

Workstation gives you several options for creating virtual machines:

- Create a virtual machine.

If you do not have any virtual machines or system images, you must use this method. Use the New Virtual Machine wizard to create a virtual machine. Next, you must install an operating system. The process is the same as installing it on a physical computer.

The rest of this chapter describes this method of creating a virtual machine.

- Clone a virtual machine from an existing VMware virtual machine or virtual machine template.

Clones are useful when you must deploy many identical virtual machines to a group. Cloning is preferable to copying a virtual machine because a clone's MAC address and UUID are different from the original virtual machine, to avoid network conflicts. Use the Clone Virtual Machine wizard to create a clone.

See [“Cloning a Virtual Machine”](#) on page 219.

- On Windows hosts, convert a physical machine, virtual machine, or system image that was created by using another VMware product or a third-party product.

This process creates a clone of the original virtual machine or system image. Use the Conversion wizard to convert a physical or virtual machine or a system image.

See [Chapter 6, “Creating a Virtual Machine from a System Image or Another Virtual Machine,”](#) on page 133.

Configuration Options for the New Virtual Machine Wizard

As you complete the New Virtual Machine wizard, you are prompted to make decisions about many aspects of the virtual machine. The topics in this section provide information about the issues involved so that you can determine which choices you want to make before running the wizard.

Easy Install Feature for Some Guest Operating Systems

The easy install features enable you to perform an unattended installation of the guest operating system after you complete the New Virtual Machine wizard. You can use this feature regardless of whether you choose a typical or a custom configuration in the wizard.

On Windows guests, the easy install feature is available for the following operating systems:

- Windows Vista, Windows 7, Windows XP, and Windows 2000
- Windows Server 2008, Windows Server 2003, and Windows 2000 Server

On Linux guests, the easy install feature is available for the following operating systems:

- Ubuntu 7.10 and later
- Red Hat Enterprise Linux 3 through 5

If you specify an installer disc (DVD or CD) or ISO image file and if the wizard detects an operating system that supports the easy install feature, you are prompted to supply the following information:

- For Windows guests:
 - (Optional) **Windows product key** – If you specify a product key, you are not prompted for it later, during installation of the operating system. Enter a product key unless the installation media already contains a volume license product key.
 - **Full name** – This name is used for registering the operating system. Do not use the name Administrator or Guest. If you use one of these names, you will receive an error message during installation of the operating system and be prompted to enter a different name.
 - (Optional) **Password** – On Windows operating systems other than Windows 2000, the password you enter here is used for an account with Administrator permissions. On Windows 2000, the password you enter here is used for the Administrator account.
- For Linux guests:
 - **Full name** – This name is used for registering the operating system, if registration is required. The first name is used as the host name for the virtual machine.
 - **User name** – You can use lowercase letters and numbers, with no spaces. Do not use the name root. Some operating systems set up sudo access for this user, and some require this user to use su to get root privileges.
 - **Password** – The password you enter here is used for both the user name you supply and the root user.

This feature also installs VMware Tools in the guest operating system. For more information about VMware Tools, see [“Components of VMware Tools”](#) on page 101.

If you plan to use a CD, DVD, or ISO image that contains a product key number and is already set up to perform an unattended installation, the only benefit you gain by using the easy install feature is the automatic installation of VMware Tools.

Typical Compared to Custom Configurations

The New Virtual Machine wizard prompts you to choose between doing a typical configuration and a custom configuration. If you select **Typical**, the wizard prompts you to specify or accept defaults for the following choices:

- Medium for installing the guest operating system (CD, image file, or neither)
- Guest operating system
- Virtual machine name and the location of the virtual machine files
- Size of the virtual disk and whether to split the disk into 2GB files
- Hardware customization, for advanced users

You are not prompted to specify the virtual machine version. The virtual machine version (Workstation 5.x, 6.x, or 7.0) is assumed to be the one specified in the preferences editor. From the Workstation menu bar, choose **Edit > Preferences**, and see the setting for **Default hardware compatibility**.

On the last page of the wizard, you can click **Customize Hardware** to change the defaults for memory allocation, number of virtual CPUs, network connection type, and so on.

Many circumstances require you to select a custom installation. Select **Custom** if you want to do any of the following:

- Make a different version of virtual machine than what is specified in the preferences editor.
- Specify the I/O adapter type for SCSI adapters: BusLogic, LSI Logic, or LSI Logic SAS.
- Specify whether you want to create an IDE or a SCSI virtual disk, regardless of the default that is usually used for the guest operating system.
- Use a physical disk rather than a virtual disk (for expert users).
- Use an existing virtual disk rather than create a virtual disk.
- Place the virtual disk file in a location other than the virtual machine directory.
- Allocate all virtual disk space rather than allowing the disk space to gradually grow to the maximum.

Guest Operating System Selection

If you specify that the source media for installing the operating system is **Installer disc** or **Installer disc image file** and if the wizard can detect the operating system, you might not see a wizard page for selecting the operating system.

After you specify an operating system or after the wizard detects it from the installation media, Workstation uses this information to do the following:

- Select appropriate default values, such as the amount of memory to allocate.
- Name files associated with the virtual machine.
- Adjust settings for optimal performance.
- Work around special behaviors and bugs within a guest operating system.

If the operating system you plan to use is not listed, select **Other** for both guest operating system and version.

For some operating systems, the operating system and VMware Tools are installed automatically after the virtual machine is created. See [“Easy Install Feature for Some Guest Operating Systems”](#) on page 80.

NOTE Workstation supports 64-bit guest operating systems only in Workstation versions 5.5 and later, and only on host machines with supported processors. For the list of processors Workstation supports for 64-bit guest operating systems, see [“PC Hardware”](#) on page 23.

Virtual Machine Location

The following examples show the default locations suggested for virtual machines:

- On Windows XP and Windows Server 2003 hosts, the default folder for a Windows XP Professional virtual machine is:

```
C:\Documents and Settings\<username>\My Documents\My Virtual  
Machines\<guestOSname>
```

- On Windows Vista and Windows 7 hosts, the default folder is:

```
C:\Users\<username>\Documents\Virtual Machines\<guestOSname>
```

- On Linux hosts, the default location for a Windows XP Professional virtual machine is:

```
<homedir>/vmware/<guestOSname>
```

The `<homedir>` value is the home directory of the user who is currently logged in.

Virtual machine performance might be slower if your virtual hard disk is on a network drive. For best performance, be sure the virtual machine's folder is on a local drive. However, if other users need to access this virtual machine, consider placing the virtual machine files in a location that is accessible to them. See [“Sharing Virtual Machines with Other Users”](#) on page 227.

NOTE If you plan to deploy the virtual machine on a USB drive, first, create the virtual machine on your local hard disk. You can then use Pocket ACE features to deploy the virtual machine.

For information about the files stored in the virtual machine folder, see [“Files That Make Up a Virtual Machine”](#) on page 97.

Virtual Hardware Compatibility Levels

This option is available for custom configurations only.

When you make a selection from the **Hardware Compatibility** list, you see a list of other VMware products and versions that are compatible with your selection. You also see a list of features that are not available for that version.

If one of the feature compatibility check boxes is available for the version you select, you can select the check box to see a list of the additional limitations.

Number of Processors

This option is available for custom configurations only. Setting the virtual machine to have multiple virtual CPUs (up to four for VMware Workstation 7) is supported only for host machines with at least two logical processors. (If you are creating a Workstation 4 virtual machine, you do not see this panel.)

The following are all considered to have two logical processors:

- A single-processor host with hyperthreading enabled
- A single-processor host with a dual-core CPU
- A multiprocessor host with two CPUs, regardless of whether they are dual-core or have hyperthreading enabled

Memory Allocation

This option is available for custom configurations or if you click **Customize Hardware** on the last page of the New Virtual Machine wizard.

A color-coded icon corresponds to each value. To use one of these amounts, move the slider to the corresponding icon. The high end of the range that appears is determined by the amount of memory allocated to all running virtual machines. If you allow virtual machine memory to be swapped, this value changes to reflect the amount of swapping that was specified. To change the amount of memory available to all virtual machines, use the Workstation preferences editor (**Edit > Preferences**).

Network Connection Type

This option is available for custom configurations or if you click **Customize Hardware** on the last page of the New Virtual Machine wizard. You have several options for connecting the virtual machine to the network:

- **Bridged networking** – If your host computer is on a network and you have a separate IP address for your virtual machine (or can get one automatically from a DHCP server), select **Bridged**. Other computers on the network can then communicate directly with the virtual machine.
- **NAT (Network Address Translation)** – If you do not have a separate IP address for your virtual machine but you want to be able to connect to the Internet, select **NAT**. The virtual machine and the host share a single network identity that is not visible outside the network.
- **Host-only** – Host-only networking provides a network connection between the virtual machine and the host computer, using a virtual network adapter that is visible to the host operating system. With host-only networking, the virtual machine can communicate only with the host and other virtual machines in the host-only network. Select **Host-only** to set up an isolated virtual network.

See [“Common Networking Configurations”](#) on page 286.

I/O Adapter Types

This option is available for custom configurations only. An IDE and a SCSI adapter are installed in the virtual machine. The IDE adapter is always ATAPI. For the SCSI adapter, you can choose BusLogic, LSI Logic, or LSI Logic SAS. BusLogic and LSI Logic adapters have parallel interfaces. LSI Logic SAS has a serial interface.

The default for your guest operating system is already selected. Older operating systems, such as Windows XP and Red Hat Enterprise Linux 2, default to BusLogic. Only Windows Server 2008 defaults to LSI Logic SAS.

NOTE The LSI Logic adapter has improved performance and works better with generic SCSI devices. The LSI Logic adapter is also supported by ESX Server 2.0 and higher.

Your choice of SCSI adapter does not affect your decision to make your virtual disk an IDE or SCSI disk. However, some guest operating systems, such as 32-bit Windows XP, do not include a driver for the LSI Logic or LSI Logic SAS adapter. You must download the driver from the LSI Logic Web site.

NOTE Drivers for a Mylex (BusLogic) compatible host bus adapter are not obvious on the LSI Logic Web site. Search the support area for the numeric string in the model number. For example, search for “958” for BT/KT-958 drivers.

The *VMware Guest Operating System Installation Guide* includes driver support information where appropriate. For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link.

Disk Types

This option is available for custom configurations only. The recommended disk for your guest operating system is already selected by default.

On Linux hosts, and in the Add Hardware wizard, you can select a disk mode on the Select a Disk Type page. See [“Normal and Independent Disk Modes”](#) on page 87.

Normal and Independent Disk Modes

The option to select normal or independent mode is available on Linux hosts for custom configurations only. Normal mode means you want to include disks in any snapshots you take. If you do not want data on the disk to be recorded when you take a snapshot of the virtual machine, you can configure the disk to be independent.

If you configure the disk to be independent, you can further specify whether changes you make to the disk are to persist or be discarded when you power off the virtual machine or restore it to a snapshot.

Although for Windows hosts, this configuration setting is not available in the New Virtual Machine wizard, you can exclude virtual disks from snapshots by using the virtual machine settings editor. See [“Exclude a Virtual Disk from Snapshots”](#) on page 207.

Virtual Disks and Physical Disks

This option is available for custom configurations only. If you use a typical configuration, a new virtual disk is created and used for the virtual machine. Virtual disks are the best choice for most virtual machines. They are easy to set up and can be moved to new locations on the same host computer or to different host computers.

Even for custom configurations, you usually choose the option **Create a New Virtual Disk**. In some cases you might want to choose **Use an Existing Virtual Disk**, to use a virtual disk you created previously. The wizard displays a page for you to enter the path or browse to the existing virtual disk (.vmdk) file.

It is possible to use a physical hard disk (a “raw” disk) or IDE disk partition in a virtual machine. Do not use a physical disk configuration unless you are an expert user. See [“Using Physical Disks in a Virtual Machine”](#) on page 244.

Disk Capacity

The wizard prompts you to set a size between 0.1GB and 950GB for a virtual disk. On Windows hosts, the **Pocket ACE size calculator** control can help determine the disk size for an ACE instance that fits on a portable device.

Select the option **Split virtual disk into 2 GB files** if your virtual disk is stored on a file system that does not support files larger than 2GB.

For custom configurations, you are also given the option **Allocate all disk space now**. VMware recommends that you allow the disk to grow. Allocating all disk space now gives somewhat better performance, but it is a time-consuming operation. Also it requires as much physical disk space as you specify for the virtual disk. If you allocate all the disk space now, you cannot use the shrink disk feature later.

Pocket ACE Disk Size Calculator on Windows Only

The Pocket ACE feature allows you to store ACE instances on portable devices such as USB keys (flash memory drives), Apple iPod mobile digital devices, and portable hard drives. ACE users attach these portable devices to x86 host computers and run their ACE instances with VMware Player.

On the Specify Disk Capacity page of the New Virtual Machine wizard, you can use the **Pocket ACE size calculator** button to determine what number to use in the **Disk size** text box. Disk size refers only to the size of the virtual hard disk. If you plan to create Pocket ACEs, you must also consider the amount of disk space required for memory, installers, and other files related to virtual machine overhead.

Select the **Fast synchronize cache** check box to reserve space for writing changes from the Pocket ACE cache on the host. Having this space available reduces the time it takes to synchronize files with the host.

To determine what number to enter in the **Virtual hard disk size** text box of the calculator, you need to know how much disk space is available on the device. Plug the USB device in to your host computer and use the My Computer item to display its properties. This number cannot be less than the amount shown for **Space required on USB device** in the calculator. If necessary reduce the number in the **Virtual hard disk size** text box until the amount of total space required is correct for the device.

Use the New Virtual Machine Wizard

The New Virtual Machine wizard guides you through the key steps for setting up a new virtual machine, helping you set various options and parameters.

Many of the settings you specify in the New Virtual Machine can be changed later, if necessary. You can use the virtual machine settings editor if you need to make changes after the initial creation. (From the menu bar, choose **VM > Settings**.)

Before you begin, determine what type of media to use for installing the operating system in the virtual machine and do one of the following:

- If you plan to use an installation CD or DVD for installing the guest operating system, insert the CD or DVD in the host's CD-ROM drive.
- If you plan to use an ISO image file, make sure the file is accessible to the host.

To use the New Virtual Machine wizard

- 1 From the Workstation menu bar, choose **File > New > Virtual Machine**.
- 2 Follow the prompts.

For more information about the fields on a wizard page, click **Help** on that page.

After the wizard creates the virtual machine, the next step is installing the guest operating system. See [“Installing a Guest Operating System”](#) on page 89.

Installing a Guest Operating System

Installation of a guest operating system can be automated or manual:

- If you specified an installer disc or image (.iso) file and if the wizard detected an operating system that supports the easy install feature, installation is automated.

An unattended installation of the operating system and VMware Tools begins when the virtual machine is powered on.

The installation process usually runs without requiring input from you. See [“Respond to Easy Install Prompts”](#) on page 90.

- If you did not use the easy install feature, see [“Install a Guest Operating System Manually”](#) on page 91.

Installation Requirements for the ESX Guest Operating System

You can use the easy install feature to install ESX 4.0 and ESXi 4.0 guests on Workstation. Before you begin, make sure you fulfill the following requirements:

- Hardware-assisted virtualization must be enabled for the ESX 4.0 and ESXi 4.0 guests. The host system must have Intel EM64T processors with VT-x or AMD64 Family 10H and later processors with AMD-V. Where applicable, VT-x or AMD-V must be enabled in the BIOS (or other firmware). Power off and restart Intel hosts after changing the BIOS settings to enable hardware virtualization.
- ESX 4.0 guests must be configured with two or more cores. VMware recommends that the host system should have at least as many cores as the guest.
- Only 32-bit guests may be installed to run as nested virtual machines inside an ESX guest. These virtual machines can only be configured to use binary translation.
- VMware Tools are not available for ESX 4.0 or ESXi 4.0 guests. Do not install the Linux version of VMware Tools in an ESX guest.
- For instructions on how to set the virtual Ethernet adapter on a Linux host to run in promiscuous mode, see the VMware knowledge base article 287 available on the VMware Web site.

For more information on how to configure ESX 4.0 and ESXi 4.0, see the VMware vSphere documentation set available on the VMware Web site.

Respond to Easy Install Prompts

Usually you are not prompted for input during operating system installation if the easy install feature runs. If, however, you did not enter all the easy install information in the New Virtual Machine wizard, you might be prompted for a product key, user name, or password.

Also, if the operating system installation disc or image spans multiple CDs, DVDs, or image files, you might be prompted when the installer requires the next disk.

To respond to easy install prompts

- 1 If you are prompted to supply a product key, user name, or password, do the following:
 - a Click in the virtual machine window to allow mouse and keyboard input to be grabbed by the virtual machine.
 - b Type in the required information.

- 2 If you are using CDs or DVDs and are prompted to insert the next CD or DVD, use the CD or DVD drive attached to the host.
- 3 If you are using image files and are prompted to insert the next disc, do the following:
 - On Windows hosts, click **Change Disk**, browse to the image file for the next CD, and click **OK**.
 - On Linux hosts, from the Workstation menu bar, choose **VM > Removable Devices > CD/DVD**, browse to the image file for the next CD, check the **Connected** option, and click **Save**.

Install a Guest Operating System Manually

You must install an operating system manually if you did not or were not able to use the easy install feature when completing the New Virtual Machine wizard.

Before you begin, use the following documents to determine additional requirements for the specific operating system and version you plan to install:

- For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link.
- For information about installing a Linux operating system that has a VMware VMI (Virtual Machine Interface) enabled kernel in the guest operating system, see [“Use a Paravirtualized Kernel in Linux Guests”](#) on page 93.

A new virtual machine is like a physical computer with a blank hard disk. Before you can use it, you need to partition and format the virtual disk and install an operating system. The operating system’s installation program might handle the partitioning and formatting steps for you.

Installing a guest operating system inside a virtual machine is essentially the same as installing it on a physical computer.

NOTE Workstation supports 64-bit guest operating systems only in Workstation 5.5 and higher, and only on host machines with supported processors. For the list of processors Workstation supports for 64-bit guest operating systems, see [“PC Hardware”](#) on page 23.

To install a guest operating system manually

- 1 Start Workstation.
- 2 Do one of the following so that the virtual machine can access the installation media for the guest operating system:
 - For a CD or DVD, if necessary, configure the virtual machine to use the host's CD-ROM/DVD drive, and insert the operating system media in the drive.

In some host configurations, the virtual machine cannot boot from the installation CD-ROM. You can work around that problem by creating an ISO image file from the installation CD-ROM. Use the virtual machine settings editor (choose **VM > Settings**) to connect the virtual machine's CD drive to the ISO image file, and power on the virtual machine.
 - For an ISO image, connect the CD-ROM drive to an ISO image file of an installation disk.

To use a PXE server to install the guest operating system over a network connection, you do not need the operating system installation media. When you power on the virtual machine, the virtual machine detects the PXE server.
- 3 Click the **Power On** button.
- 4 Follow the instructions provided by the operating system vendor.
- 5 If the operating system spans several CDs, follow these steps when you are prompted to insert the second CD:
 - a Disconnect from the current image by choosing **VM > Removable Devices > CD-ROM > Disconnect**.
 - b Edit the CD settings by choosing **VM > Removable Devices > CD-ROM > Edit**.
 - c For **Use ISO image file**, click **Browse**, and select the ISO image for the second CD.
 - d In the **Device Status** area, select the **Connected** check box and click **OK**.
 - e In the guest operating system, click **OK** or respond to the prompt so that installation can continue.
 - f Repeat this process for additional CDs.

After the guest operating system is installed, you can use the standard tools within the operating system to configure its settings. VMware recommends that you install VMware Tools before you activate the license for the operating system. See [“Installing VMware Tools”](#) on page 104.

Use a Paravirtualized Kernel in Linux Guests

Since 2005, VMware has been collaborating with the Linux community to develop a common paravirtualization interface. In 2006, VMware released its VMI specification as an open specification. It allows VMware virtual machines to support various paravirtualized operating systems from popular Linux distributions.

Before you begin, obtain installation media (CD or ISO image) for the operating system. Paravirtualized kernel support is available for 32-bit versions of Ubuntu 7.04, 7.10, or 8.04 and SUSE Linux Enterprise Server 10 SP2.

The 64-bit version of SUSE Linux Enterprise Server 10 SP2 already contains paravirtualization. You do not need to use a Workstation setting to enable it.

For more information about paravirtualization in general, see the following VMware Web site at:

<http://www.vmware.com/interfaces/paravirtualization.html>

If you have a VMware VMI (Virtual Machine Interface) enabled kernel in the guest operating system, you will see improved performance if you enable paravirtual support in the virtual machine.

To use a paravirtualized kernel in Linux guests

- 1 Use the New Virtual Machine wizard to create virtual machine for one of the supported 32-bit guest operating systems.
- 2 After you finish creating the virtual machine, enable paravirtual kernel support, as follows:
 - a Choose **VM > Settings**.
 - b On the **Hardware** tab, select **Processors**, and in the **Execution Mode** section, select the **VMware kernel paravirtualization** check box.

Upgrade a Guest Operating System

When you use the New Virtual Machine wizard to create a virtual machine, one of the settings you specify is the guest operating system type and version. Workstation chooses configuration defaults based on the guest type and version you choose.

If you upgrade a guest operating system to a newer version, also update the guest operating system version for the virtual machine.

To upgrade a guest operating system

- 1 Start Workstation and select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 Click the **Options** tab.
- 5 On the **General** settings panel, in the **Version** field, select the version to which you plan to upgrade and click **OK**.

The setting you specify here is written to the virtual machine's configuration file. This setting does not actually change the guest operating system itself.

- 6 Power on the virtual machine.
- 7 To upgrade the guest operating system, follow the upgrade instructions provided by the operating system vendor.

Change the Version of a Virtual Machine

If you created virtual machines with an earlier version of Workstation, you must upgrade to the latest version to use the newest features. For information about new features, see the release notes.

If you created Workstation 6.5 or 7.0 virtual machines and you want to deploy those virtual machines to run on a different VMware product, you might need to downgrade to a version that is compatible with that product.

Using Workstation 7.0, you can downgrade to versions 4, 5.x, 6, or 6.5.

You can also determine which virtual hardware version to use.

Consider the following when changing the virtual hardware version of a virtual machine:

- For Workstation 4, 5.x, 6, 6.5 and 7.0 virtual machines, you can change the version of the original virtual machine or create a full clone, so that the original remains unaltered. For Workstation 4 virtual machines, Workstation changes the original virtual machine.
- If you upgrade a Workstation 4 or 5.x virtual machine that is compatible with ESX Server to Workstation 6, 6.5, or 7.0 you cannot use the Change Version wizard to later downgrade it again to an ESX-compatible virtual machine.

On Windows hosts, however, you can use the Conversion wizard (choose **File > Import**) to perform such a downgrade.

- When you upgrade a Windows XP, Windows Server 2003, Windows Vista, or Windows 7 virtual machine, the Microsoft product activation feature might require you to reactivate the guest operating system.

To change the version of a virtual machine

- 1 Make backup copies of the virtual disks (.vmdk files).
- 2 If you are upgrading from a Workstation 4 or 5.x virtual machine, or downgrading to a Workstation 4 or 5.x virtual machine, make a note of the NIC settings in the guest.

Specifically, if you specified a static IP address for this virtual machine, after the upgrade, that setting might be changed to automatic assignment by DHCP.

To check the NIC settings, use the method appropriate for your operating system. For example, on Windows XP, you can use the Control Panel's Network Connections item to find information about the TCP/IP address for the virtual machine.

- 3 Shut down the guest operating system and power off the virtual machine.
- 4 Select the virtual machine and choose **VM > Upgrade or Change Version**.
- 5 Follow the prompts.

When you select a hardware compatibility version, you see a list of the VMware products that are compatible with that version. If you select Workstation 4, 5, or 6 you also see a list of Workstation 6.5 and 7.0 features that are not supported for that version.

6 Power on the virtual machine.

If you upgrade a virtual machine that contains a Windows 98 operating system to a Workstation 6.5 or 7.0 virtual machine, you are prompted to install a PCI-PCI bridge driver when you power on the virtual machine. Because Workstation 6.5 and 7.0 has 32 more PCI-PCI bridges than Workstation 6, you might need to respond to the prompt 32 or 33 times.

7 If applicable, in the guest operating system, check the NIC settings and adjust them if they changed, as described in [Step 2](#).

8 If the virtual machine does not have the latest version of VMware Tools installed, update VMware Tools.

Even if, for example, you upgraded a Workstation 5.x virtual machine to Workstation 6.x rather than 7.0, be sure to update VMware Tools to the version included with Workstation 7.0. See [“VMware Tools Update Process”](#) on page 115. Do not remove the older version of VMware Tools before installing the new version.

If you are upgrading a virtual machine that runs from a physical (raw) disk, you can safely ignore the message, `Unable to upgrade <drive_name>`. One of the supplied parameters is invalid. Click **OK**.

Using an Older-Version Virtual Machine Without Upgrading

You might not want to upgrade a virtual machine because you want it to remain compatible with other VMware products you are using. Following is a brief summary of VMware product version compatibility.

Version of Workstation	Compatible VMware Products
4.x	ACE 1.x, 2.0, 2.5, and 2.6, ESX 4.0, VMware Fusion 1.1, 2.0, and 3.0, GSX Server 3.x, VMware Server 1.x and 2.0, and Workstation 4.x, 5.x, 6.x, and 7.0
5.x	ACE 2.0, 2.5, and 2.6, ESX 4.0, VMware Fusion 1.1, 2.0, and 3.0, GSX Server 3.x, VMware Server 1.x and 2.0, and Workstation 5.x, 6.x, and 7.0
6.x	ACE 2.0, 2.5, and 2.6, ESX 4.0, VMware Fusion 1.1, 2.0, and 3.0, VMware Server 2.0, and Workstation 6.0, 6.5, and 7.0
7.0	ACE 2.5 and 2.6, ESX 4.0, VMware Fusion 2.0 and 3.0, VMware Server 1.x and 2.0, and Workstation 6.5 and 7.0

You can run older versions of virtual machines in Workstation 7.0, but you will not have the benefits of the new features of Workstation 7.0.

For more information about compatibility between VMware products, see the *VMware Virtual Machine Mobility Planning Guide*.

If you decide not to upgrade a virtual machine, you still need to upgrade VMware Tools to the new version. Follow the instructions for your guest operating system in [“VMware Tools Update Process”](#) on page 115. Do not remove the older version of VMware Tools before installing the new version.

Files That Make Up a Virtual Machine

You might never need to know the filenames or locations for your virtual machine files. Virtual machine file management is performed by Workstation.

A virtual machine typically is stored on the host computer in a set of files, usually in a directory created by Workstation for that specific virtual machine. See [“Virtual Machine Location”](#) on page 83.

The key files are listed in [Table 4-1](#) by extension. In these examples, <vmname> is the name of your virtual machine.

Table 4-1. Virtual Machine Files

Extension	File Name	Description
.log	<vmname>.log or vmware.log	The log file of key Workstation activity. This file is useful for troubleshooting. This file is stored in the directory that holds the configuration (.vmx) file of the virtual machine.
.nvram	<vmname>.nvram or nvram	The NVRAM file, which stores the state of the virtual machine's BIOS.

Table 4-1. Virtual Machine Files (Continued)

Extension	File Name	Description
.vmdk	<vmname>.vmdk	<p>VMDK files, which store the contents of the virtual machine's hard disk drive.</p> <p>A virtual disk is made up of one or more virtual disk (.vmdk) files. The virtual machine settings editor shows the name of the first file in the set. This file contains pointers to the other files in the set.</p> <p>(If you specify that all space should be allocated when you create the disk, these files start at the maximum size and do not grow.) Almost all of a .vmdk file's content is the virtual machine's data, with a small portion allotted to virtual machine overhead.</p> <p>If the virtual machine is connected directly to a physical disk, the .vmdk file stores information about the partitions the virtual machine is allowed to access.</p> <p>Earlier VMware products used the extension .disk for virtual disk files.</p>
	<vmname>-s<###>.vmdk	<p>If you specified that the files can grow, the filenames include an s in the file number (for example, Windows XP Professional-s001.vmdk).</p> <p>If you specified that the virtual disk is split into 2GB chunks, the number of .vmdk files depends on the size of the virtual disk. As data is added to a virtual disk, the .vmdk files grow, to a maximum of 2GB each.</p>
	<vmname>-f<###>.vmdk	<p>If the disk space was allocated when the disk was created, the names include an f instead of an s (for example, Windows XP Professional-f001.vmdk).</p>
	<vmname>-<disk>-<###>.vmdk	<p>If the virtual machine has one or more snapshots, some files are redo-log files. They store changes made to a virtual disk while the virtual machine is running. The ### indicates a unique suffix added by Workstation to avoid duplicate file names.</p>
.vmem	<uuid>.vmem	<p>The virtual machine's paging file, which backs up the guest main memory on the host file system. This file exists only when the virtual machine is running or if the virtual machine fails.</p>
	<snapshot_name_number>.vmem	<p>Each snapshot of a virtual machine that is powered on has an associated .vmem file, which contains the guest's main memory, saved as part of the snapshot.</p>

Table 4-1. Virtual Machine Files (Continued)

Extension	File Name	Description
.vmsd	<vmname>.vmsd	A centralized file for storing information and metadata about snapshots.
.vmsn	<vmname>-Snapshot.vmsn	The snapshot state file, which stores the running state of a virtual machine at the time you take that snapshot.
	<vmname>-Snapshot<###>.vmsn	The file that stores the state of a snapshot.
.vmss	<vmname>.vmss	The suspended state file, which stores the state of a suspended virtual machine. Some earlier VMware products used the extension .std for suspended state files.
.vmtm	<vmname>.vmtm	The configuration file containing team data.
.vmx	<vmname>.vmx	The primary configuration file, which stores settings chosen in the New Virtual Machine wizard or virtual machine settings editor. If you created the virtual machine with an earlier version of Workstation on a Linux host, this file might have a .cfg extension.
.vmxf	<vmname>.vmxf	A supplemental configuration file for virtual machines that are in a team. This .vmxf file remains if a virtual machine is removed from the team.

Other files might be present in the directory. Some are present only while a virtual machine is running. See [“Lock Files”](#) on page 236.

Installing and Using VMware Tools

5

This chapter discusses how to install, update, and run VMware Tools. This chapter includes the following topics:

- [“Components of VMware Tools”](#) on page 101
- [“Installing VMware Tools”](#) on page 104
- [“VMware Tools Update Process”](#) on page 115
- [“Uninstall VMware Tools”](#) on page 118
- [“Repair or Change Installed Modules in a Windows Guest”](#) on page 118
- [“Open the VMware Tools Control Panel”](#) on page 119
- [“Configure VMware Tools in a NetWare Guest”](#) on page 123
- [“Customizations to VMware Tools”](#) on page 125
- [“Use the VMware Tools Service Command-Line Interface”](#) on page 132

Components of VMware Tools

VMware Tools is a suite of utilities that enhances the performance of the virtual machine’s guest operating system and improves management of the virtual machine. Although the guest operating system can run without VMware Tools, you lose important functionality and convenience.

VMware Tools includes the following components:

- VMware Tools service
- VMware device drivers
- VMware user process
- VMware Tools control panel

VMware Tools Service

The program file is called `vmtoolsd.exe` on Windows guest operating systems and `vmtoolsd` on Linux, FreeBSD, and Solaris guests.

This service starts when the guest operating system boots and performs various duties within the guest operating system:

- Passes messages from the host operating system to the guest operating system.
- Executes commands in the operating system to cleanly shut down or restart a Linux, FreeBSD, or Solaris system when you select power operations in Workstation.
- On Windows guests, allows the mouse cursor to move freely between the guest and host operating systems.
- On Windows guests, matches the guest's screen resolution to the host's screen resolution and the reverse.
- Synchronizes the time in the guest operating system with the time in the host operating system.
- Runs scripts that help automate guest operating system operations. The scripts run when the virtual machine's power state changes.

The VMware Tools service is not installed on NetWare operating systems. Instead, the `vmwtool` program is installed. It synchronizes time and allows you to turn the CPU idler on or off.

VMware Device Drivers

These device drivers include:

- SVGA display driver that provides high display resolution and significantly faster overall graphics performance.
- An audio driver that is required for all 64-bit Windows guests and 32-bit Windows Server 2003, Windows Server 2008, Windows Vista, and Windows 7 guests.
- VMXNet networking drivers for some guest operating systems.
- BusLogic SCSI driver for some guest operating systems.
- VMware mouse driver.
- A kernel module for handling shared folders, called `hgfs.sys` on Windows and `.vmhgfs` on Linux and Solaris.

- The Virtual Machine Communication Interface (VMCI) driver for creating client-server applications that are optimized for fast and efficient communication between virtual machines.
- A paravirtual SCSI driver for PVSCSI adapters, which enhance the performance of some virtualized applications.

VMware User Process

The program file is called `VMwareUser.exe` on Windows guests and `vmware-user` on Linux, Solaris, and FreeBSD guests. On NetWare guests, the `vmwtool` program is installed instead of `vmware-user`.

The VMware user process performs the following tasks within the guest operating system:

- Lets you copy and paste text and files between host operating systems and Windows, Linux, Solaris, and FreeBSD guest operating systems.
- Lets you drag and drop files between host operating systems and Windows, Linux, Solaris, and FreeBSD guest operating systems.
- Lets you use the Unity feature with Windows and Linux guests.
- On Linux, Solaris, and FreeBSD guests, grabs and releases the mouse cursor when the SVGA driver is not installed.
- On Linux, Solaris, and FreeBSD guests, matches the guest's screen resolution to the host's.

This process starts when you begin an X11 session. To use a different mechanism to start the process, see [“Start the VMware User Process Manually If You Do Not Use a Session Manager”](#) on page 114.

On NetWare operating systems, the `vmwtool` program controls the grabbing and releasing of the mouse cursor. It also lets you copy and paste text. You cannot drag and drop or copy and paste files between hosts and NetWare guest operating systems.

VMware Tools Control Panel

The VMware Tools control panel lets you modify settings, shrink virtual disks, and connect and disconnect virtual devices. See [“Open the VMware Tools Control Panel”](#) on page 119.

Installing VMware Tools

The installers for VMware Tools are stored with Workstation as ISO image files. Workstation downloads the most recent version of these files from a VMware Web site.

When you select **VM > Install VMware Tools**, Workstation determines whether it has downloaded the most recent version of the ISO file for the specific operating system. If Workstation does not have the most recent version, or if Workstation has never downloaded an image file for that operating system, you are prompted to download the file.

When Workstation has the most recent version of the ISO image file, Workstation temporarily connects the virtual machine's first virtual CD-ROM drive to the correct ISO image file.

The installation procedure varies depending on the operating system:

- [“Install VMware Tools in a Windows Guest”](#) on page 104
- [“Install VMware Tools in a Linux Guest”](#) on page 109
- [“Install VMware Tools in a Solaris Guest”](#) on page 111
- [“Install VMware Tools in a FreeBSD Guest”](#) on page 112
- [“Install VMware Tools in a NetWare Guest”](#) on page 113

Install VMware Tools in a Windows Guest

VMware Tools is supported on all Windows guest operating systems. Before you use the menu command to install VMware Tools, perform the following tasks, as necessary:

- Make sure the virtual machine is powered on.
- If you are running Workstation on a Windows host and your virtual machine has only one CD-ROM drive, make sure the CD-ROM drive is configured as an IDE or SCSI CD-ROM drive. It cannot be configured as a generic SCSI device. If necessary, add an IDE or SCSI CD-ROM drive to the virtual machine. See [“Adding DVD/CD-ROM and Floppy Drives to a Virtual Machine”](#) on page 250.

- Make sure the virtual CD-ROM drive is configured to auto-detect a physical drive. This task is necessary if you connected the virtual machine's CD drive to an ISO image file when you installed the operating system. Change the connection from the ISO image to auto-detect a physical drive. (With the virtual machine powered off, choose **VM > Settings > CD/DVD > Use Physical Drive > Auto-detect.**)
- If the guest operating system is a Windows NT, Windows 2000, Windows XP, Windows Server 2003, Windows Vista, or Windows 7 operating system, log in as an administrator. Any user can install VMware Tools in a Windows 95, Windows 98, or Windows Me guest operating system.

To install VMware Tools

- 1 On the host, from the Workstation menu bar, choose **VM > Install VMware Tools.**

If an earlier version of VMware Tools is installed, the menu item is **Update VMware Tools.**

Depending on whether Autorun is enabled, one of the following occurs inside the guest operating system:

- If Autorun is enabled in the guest operating system, a dialog box appears after a few seconds. You receive a prompt to confirm whether you want to install VMware Tools.
- If Autorun is not enabled, the dialog box does not appear automatically. Click **Start > Run** and enter **D:\setup\setup.exe** where **D:** is your first virtual CD-ROM drive.

- 2 Click **Yes** to launch the InstallShield wizard.
- 3 Follow the on-screen instructions.

On some Windows operating systems, after the SVGA driver is installed, you are prompted to reboot to use this new driver.

- 4 Reboot the virtual machine if necessary.

To change the default configuration options, see [“Open the VMware Tools Control Panel”](#) on page 119.

Configure the Video Driver on Older Versions of Windows

If you are installing VMware Tools in a virtual machine that has a Windows NT, Windows Me, Windows 98, or Windows 95 operating system, you might need to configure the video driver manually. When you click **Finish** in the VMware Tools installation wizard, a message appears indicating that VMware Tools failed to install the SVGA driver.

A Notebook window, the Display Properties/Settings dialog box, and a message box appear, prompting you to reboot the machine.

To configure the video driver on older versions of Windows

- 1 In the message box that prompts you to reboot, click **No**.

If you click **Yes**, after the virtual machine reboots, run the VMware Tools installer again (choose **VM > Reinstall VMware Tools**). Select the **Repair** option.

The **Repair** option allows the Notebook window to appear again so that the installer can access the SVGA driver.

- 2 Follow the instructions in the Notebook file.

The instructions are specific to each operating system. They provide steps for selecting the VMware SVGA driver, usually in the Display Properties/Settings dialog box, and installing it from the VMware Tools ISO image.

The English version of the instructions from the Notebook file are reprinted in Knowledge Base article 1001819 at the VMware Web site.

Automate the Installation of VMware Tools in a Windows Guest

If you are installing VMware Tools in a number of Windows virtual machines, you can automate its installation. This silent installation feature uses the Microsoft Windows Installer runtime engine.

Make sure the Microsoft Windows Installer runtime engine version 2.0 or higher is installed in the guest operating system.

Version 2.0 or higher is included with newer versions of Windows. If you are installing VMware Tools in older Windows guest operating systems, check the version of the `%WINDIR%\system32\msiexec.exe` file.

If the file version is not 2.0 or higher, upgrade the engine by running `instmsiw.exe` (`instmsia.exe` for Windows 95 or Windows 98 guests), which is included with the VMware Tools installer.

For more information about using the Microsoft Windows Installer, including command-line options, go to the Windows Installer page on the MSDN Web site.

To automate the installation of VMware Tools in a Windows guest

- 1 Make sure the virtual machine's CD-ROM drive is connected to the VMware Tools ISO image and that it is configured to connect whenever you power on the virtual machine:
 - a Select the virtual machine and choose **VM > Settings > Hardware > CD-ROM**.
 - b In the **Device status** section, select the **Connect at Power On** check box.
 - c In the **Connection** section, select **Use ISO image** and browse to the `windows.iso` file, located in the directory where you installed Workstation.
 - d Click **OK**.
- 2 (Optional) In the guest operating system, suppress prompts about installing unsigned drivers.

If you are installing VMware Tools from a beta or release candidate version of Workstation, you are asked to confirm the installation of unsigned drivers. Follow these steps to suppress these confirmation prompts.

For all Windows systems except Windows Vista and Windows 7:

- a On the virtual machine's desktop or **Start** menu, right-click **My Computer** and choose **Properties**.
- b Click the **Hardware** tab and click **Driver Signing**.
- c In the Driver Signing Options dialog box, click **Ignore** and click **OK**.
- d Click **OK** in the System Properties dialog box.

For Windows Vista:

- a On the **Start** menu, right-click **Computer** and choose **Properties**.
- b Select **Advanced system settings > Hardware > Windows Update Driver Settings**.
- c Click **Never check for drivers when I connect a device** and click **OK**.
- d Click **OK** in the System Properties dialog box.

For Windows 7:

- a On the **Start** menu, right-click **Computer** and choose **Properties**.
 - b Select **Advanced system settings > Hardware > Device Installation Settings > No, let me choose what to do > Never install driver software from Windows Update**.
 - c Click **Save Changes**.
 - d Click **OK** in the System Properties dialog box.
- 3 Open a command prompt and use the following command to install some or all of the VMware Tools components:

```
msiexec -i "D:\VMware Tools.msi" ADDLOCAL=ALL [REMOVE=<component>] /qn  
TRANSFORMS= <path>\1041.msi
```

In this command, you can optionally use **REMOVE=<component>** if you do not want to install a particular component.

Table 5-1. VMware Tools Component Values

Valid Component Values	Description
Toolbox	VMware Tools control panel and its utilities. Excluding this feature prevents you from using VMware Tools in the guest operating system. VMware does not recommend excluding this feature.
Drivers	<p>Includes the SVGA, mouse, BusLogic, and vmxnet drivers.</p> <ul style="list-style-type: none">■ SVGA – VMware SVGA driver. Excluding this feature limits the display capabilities of your virtual machine.■ Mouse – VMware mouse driver. Excluding this feature decreases mouse performance in your virtual machine.■ BusLogic – VMware BusLogic driver. If your virtual machine is configured to use the LSI Logic driver, you might want to remove this feature.■ VMXNet – VMware VMXnet networking driver.
MemCtl	VMware memory control driver. Use this driver if you plan to use this virtual machine with VMware ESX Server. Excluding this feature hinders the memory management capabilities of the virtual machine running on a VMware ESX Server system.
Hgfs	VMware shared folders driver. Use this driver if you plan to use this virtual machine with VMware Workstation. Excluding this feature prevents you from sharing a folder between your virtual machine and the Workstation host.

For example, to install everything but the shared folders driver, type the following on the command line:

```
msiexec -i "D:\VMware Tools.msi" ADDLOCAL=ALL REMOVE=Hgfs /qn
```

The SVGA, Mouse, BusLogic, VMXnet, and MemCtl features are children of the Drivers feature. This means that the following command skips installation of the SVGA, mouse, BusLogic, vmxnet, and MemCtl drivers:

```
msiexec -i "D:\VMware Tools.msi" ADDLOCAL=ALL REMOVE=Drivers /qn
```

To include a feature, use it with the ADDLOCAL option. To exclude a feature, use it with the REMOVE option.

Install VMware Tools in a Linux Guest

Before you begin, make sure the virtual machine is powered on and the guest operating system is running.

To install VMware Tools in a Linux guest

- 1 On the host, select **VM > Install VMware Tools**.

If an earlier version of VMware Tools is installed, the menu item is **Update VMware Tools**. If the current version is installed, the menu item is **Reinstall VMware Tools**.

- 2 On the guest, log in as root.
- 3 If your Linux distribution does not automatically mount CD-ROMs, mount the VMware Tools virtual CD-ROM image.

- a If necessary, create the `/mnt/cdrom` directory:

```
mkdir /mnt/cdrom
```

- b Mount the CD-ROM drive.

Some Linux distributions use different device names or organize the `/dev` directory differently. If your CD-ROM drive is not `/dev/cdrom` or if the mount point for a CD-ROM is not `/mnt/cdrom`, modify the command to reflect the conventions used by your distribution.

```
mount /dev/cdrom /mnt/cdrom
```

- 4 Change to a working directory (for example, `/tmp`):

```
cd /tmp
```

- 5 If a previous installation exists, delete the previous `vmware-tools-distrib` directory.

The location of this directory depends on where you placed it during the previous installation. Often it is placed in `/tmp/vmware-tools-distrib`.

- 6 Uncompress the installer:

```
tar xzpf /mnt/cdrom/VMwareTools-<x.x.x>-<yyyy>.tar.gz
```

The value `<x.x.x>` is the product version number and `<yyyy>` is the build number of the product release.

- 7 If necessary, unmount the CD-ROM image.

If your Linux distribution automatically mounted the CD-ROM, you do not need to unmount the image.

```
umount /dev/cdrom
```

- 8 Run the VMware Tools installer.

```
cd vmware-tools-distrib  
./vmware-install.pl
```

Respond to the questions the command-line wizard displays on the screen. Press Enter to accept the default value. The configuration file, `vmware-config-tools.pl`, runs after the installer file finishes running.

- 9 If you are updating VMware Tools, reboot the virtual machine or manually reload the `pvscsi`, `vmxnet`, and `vmxnet3` Linux kernel modules.

If you reload the modules, networking on the virtual machine is interrupted.

- 10 Enter the following commands to restore the network:

```
/etc/init.d/network stop  
rmmod vmxnet  
modprobe vmxnet  
/etc/init.d/network start
```

- 11 Log out of the root account.

```
exit
```

- 12 (Optional) Start your graphical environment.

- 13 In an X terminal, to start the VMware User process, enter the following command:

```
vmware-user
```

To change the default VMware Tools configuration options, see [“Open the VMware Tools Control Panel”](#) on page 119.

Install VMware Tools in a Solaris Guest

Before you begin, make sure the virtual machine is powered on and the guest operating system is running.

To install VMware Tools in a Solaris guest

- 1 On the host, select **VM > Install VMware Tools**.

If an earlier version of VMware Tools is installed, the menu item is **Update VMware Tools**. If the current version is installed, the menu item is **Reinstall VMware Tools**.

- 2 On the guest, log in as root.
- 3 If necessary, mount the VMware Tools virtual CD-ROM image.

Usually, the Solaris volume manager `vold` mounts the CD-ROM under `/cdrom/vmwaretools`. If the CD-ROM is not mounted, restart the volume manager using the following commands:

```
/etc/init.d/volmgt stop  
/etc/init.d/volmgt start
```

- 4 Change to a working directory (for example, `/tmp`):

```
cd /tmp
```

- 5 Extract VMware Tools:

```
gunzip -c /cdrom/vmwaretools/vmware-solaris-tools.tar.gz | tar xf -
```

- 6 Run the VMware Tools installer:

```
cd vmware-tools-distrib  
./vmware-install.pl
```

Respond to the configuration prompts. Press Enter to accept the default value.

- 7 Log out of the root account:

```
exit
```

- 8 (Optional) Start your graphical environment.

- 9 In an X terminal, to start the VMware User process, enter the following command:

```
vmware-user
```

To change the default VMware Tools configuration options, see [“Open the VMware Tools Control Panel”](#) on page 119.

Install VMware Tools in a FreeBSD Guest

Before you begin, make sure the virtual machine is powered on and the guest operating system is running.

To install VMware Tools in a FreeBSD guest

- 1 On the host, select **VM > Install VMware Tools**.

If an earlier version of VMware Tools is installed, the menu item is **Update VMware Tools**. If the current version is installed, the menu item is **Reinstall VMware Tools**.

- 2 Make sure the guest operating system is running in text mode.

You cannot install VMware Tools while X is running.

- 3 On the guest, log in as root.

- 4 If necessary, mount the VMware Tools virtual CD-ROM image by entering a command similar to the following:

```
mount /cdrom
```

Some FreeBSD distributions automatically mount CD-ROMs. If your distribution uses automounting, skip this step.

- 5 Change to a working directory (for example, /tmp):

```
cd /tmp
```

- 6 Untar the VMware Tools tar file:

```
tar xzpf /cdrom/vmware-freebsd-tools.tar.gz
```

- 7 If necessary, unmount the VMware Tools virtual CD-ROM image:

```
umount /cdrom
```

If your distribution uses automounting, you do not need to unmount the image.

- 8 Run the VMware Tools installer:

```
cd vmware-tools-distrib  
./vmware-install.pl
```

- 9 Log out of the root account:

```
exit
```

- 10 (Optional) Start your graphical environment.
- 11 In an X terminal, to start the VMware User process, enter the following command:

```
vmware-user
```

In minimal installations of the FreeBSD 4.5 guest operating system, sometimes VMware Tools does not start.

To change the default VMware Tools configuration options, see [“Open the VMware Tools Control Panel”](#) on page 119.

Install VMware Tools in a NetWare Guest

Before you begin, make sure the virtual machine is powered on and the guest operating system is running.

To install VMware Tools in a NetWare guest

- 1 On the host, select **VM > Install VMware Tools**.

If an earlier version of VMware Tools is installed, the menu item is **Update VMware Tools**. If the current version is installed, the menu item is **Reinstall VMware Tools**.
- 2 On the guest, load the CD-ROM driver so the CD-ROM device mounts the ISO image as a volume by doing one of the following:
 - For a NetWare 6.5 virtual machine in the system console, enter:

LOAD CDDVD
 - For a NetWare 6.0 or NetWare 5.1 virtual machine, in the system console, enter:

LOAD CD9660.NSS
 - For a NetWare 4.2 virtual machine, in the system console, enter:

load cdrom

Mount the VMware Tools CD-ROM image by entering:

cd mount vmwtools

- 3 In the system console, enter one of the following:

- For NetWare 5.1, 6.0, or 6.5:

vmwtools:\setup.ncf

- For NetWare 4.2:

vmwtools:\setup

When the installation finishes, the message **VMware Tools for NetWare are now running** appears in the Logger Screen (NetWare 6.5 and NetWare 6.0 guests) or the Console Screen (NetWare 4.2 and 5.1 guests).

- 4 If you have a NetWare 4.2 guest, restart the guest operating system, as follows:

- a To shut down the system, in the system console, enter:

down

- b To restart the guest operating system, in the system console, enter:

restart server

- 5 Make sure the VMware Tools virtual CD-ROM image (**netware.iso**) is not attached to the virtual machine.

If it is attached, disconnect it. Right-click the CD-ROM icon in the status bar of the console window and choose **Disconnect**.

Start the VMware User Process Manually If You Do Not Use a Session Manager

One of the executables used by VMware Tools in Linux, Solaris, and FreeBSD guests is **vmware-user**. This program implements the fit-guest-to-window feature and Unity mode, among other features.

Normally, **vmware-user** is started automatically after you configure VMware Tools and then log out of the desktop environment and log back in. You must start the **vmware-user** process manually in the following environments:

- If you run an X session without a session manager (for example, by using **startx** and getting a desktop and not using **xdm**, **kdm**, or **gdm**)
- If you are using certain older versions of GNOME without **gdm** or **xdm**
- If you are using any session manager or environment that does not support the Desktop Application Autostart Specification, available from <http://standards.freedesktop.org>

To start the VMware User process manually if you do not use a session manager

Do one of the following:

- To have `vmware-user` start when you start an X session, add `vmware-user` to the appropriate X startup script, such as the `.xsession` or `.xinitrc` file.

The `vmware-user` program is located in the directory where you selected to install binary programs, which defaults to `/usr/bin`. The startup script that needs to be modified depends on your particular system.

- To start `vmware-user` after a VMware Tools software update or if you notice certain features are not working, open a terminal window and enter the following command:

```
vmware-user
```

VMware Tools Update Process

Workstation checks for VMware Tools updates when you power on a virtual machine. If a newer version is available, Workstation prompts you for permission to download the new version from a VMware Web site.

When you update from a version of VMware Tools included with Workstation 4.x, 5.x, 6.x, the previous version of VMware Tools might be uninstalled.

For VMware Tools updates on Linux and Windows guests, you can set the guest to update automatically, or you can perform a manual update. On other guests, you must manually update.

When you update VMware Tools, any changes you made to the default scripts are overwritten. Any custom scripts you created remain untouched, but do not benefit from any underlying changes that enhance the default scripts.

How Automatic Updates Occur

On Windows and Linux guest systems, you can set VMware Tools to update itself when the virtual machine is powered on. The status bar displays the message **Installing VMware Tools . . .** when an update is in progress. After the update is complete, if you are logged in to a Windows guest, a restart prompt appears for 30 seconds. If you are not logged in, the operating system restarts without prompting.

An auto-update check is performed as part of the boot sequence when you power on a virtual machine. If the virtual machine was suspended and you resume it or restore it to a snapshot during the boot sequence before this check occurs, the automatic update occurs as planned.

If you resume the virtual machine or restore it to a snapshot after the auto-update check occurs, the automatic update does not occur.

For more information about automatic updates, see [“Use Global Settings to Update VMware Tools Automatically”](#) on page 116 and [“Set VMware Tools Update Options for Each Virtual Machine”](#) on page 117.

How You Are Notified to Do a Manual Update

On Windows and Linux guests, you can specify that you want to do manual updates. On other operating systems, performing manual updates is the only option.

The status bar of the guest system displays a message when a new version is available. To install the update, use the same procedure that you used for installing VMware Tools the first time. On Linux guests, the VMware User process (`vmware-user`) does not restart following an update until you launch it manually or log out of your window manager and log in again.

On Windows, you can alternatively open the VMware Tools control panel (double-click the **VMware Tools** icon in the notification area of the taskbar), and on the **Options** tab, click **Update**.

Use Global Settings to Update VMware Tools Automatically

To automatically update VMware Tools for most or all Windows or Linux guests when the virtual machine starts, configure the global preference first and then configure the per-virtual-machine update option to use that global preference.

Before you begin, if you use a Linux host, become root before starting Workstation. On Linux systems, nonroot users are not allowed to modify the preference setting for VMware Tools updates.

To use global settings to update VMware Tools automatically

- 1 Start Workstation.
- 2 Select **Edit > Preferences** and click the **Updates** tab.
- 3 Under the **VMware Tools updates** section, select the check box and click **OK**.

- 4 For each of your virtual machines, do the following:
 - a Select the virtual machine.
 - b Select **VM > Settings**.
 - c Click the **Options** tab and select **Tools**.
 - d Verify that the virtual machine is set to use the global preference and click **OK**.

Set VMware Tools Update Options for Each Virtual Machine

Use this procedure to override global settings for automatically updating VMware Tools on Linux and Windows guests.

Automatic updates work for versions of VMware Tools included in Workstation 5.5 and higher (build 29772 and above). Automatic updates do not work for versions of VMware Tools included in virtual machines created with VMware Server 1.x.

To set VMware Tools update options for each virtual machine

- 1 Select the Linux or Windows virtual machine.
- 2 Select **VM > Settings**.
- 3 Click the **Options** tab and select **Tools**.
- 4 Select an update option and click **OK**.

To install the update, use the same procedure that you used for installing VMware Tools the first time. For the platform-specific installation instructions, see [“Installing VMware Tools”](#) on page 104.

Update VMware Tools in Older Windows Virtual Machines

When a Microsoft installer performs an update, it updates only the components that it finds already installed. It does not add new components. If you update VMware Tools in a Windows virtual machine that was created with Workstation 5.x, some new components are not installed. Specifically, the Workstation 6.x and higher component for file sharing and dragging and dropping files is not installed.

To get the new components, you must uninstall the old version of VMware Tools and install the new version of VMware Tools.

To update VMware Tools in older Windows virtual machines

- 1 To uninstall the old version of VMware Tools, use the **Add/Remove Programs** item in the guest's Control Panel.
- 2 To install the new version of VMware Tools, see [“Installing VMware Tools”](#) on page 104.

Uninstall VMware Tools

Occasionally, an update of VMware Tools is incomplete. You can usually solve the problem by uninstalling VMware Tools and then reinstalling.

To uninstall VMware Tools

Depending on the guest operating system, do one of the following:

- On most Windows guests, log in as an Administrator user use the guest operating system's **Add/Remove Programs** item to remove VMware Tools.

On Windows Vista, Windows 7, and Server 2008 guests, use the guest operating system's **Programs and Features > Uninstall a program** item to remove VMware Tools.

- On Linux, Solaris, FreeBSD, and NetWare guests, log in as root and enter the following command:

```
vmware-uninstall-tools.pl
```

- On a Linux guest where VMware Tools was installed by using an RPM installer, log in as root and enter the following command:

```
rpm -e VMwareTools
```

Workstation 4, 5, and 6 included RPM and tar installers for VMware Tools.

Workstation 7 and later releases include only tar installers.

Repair or Change Installed Modules in a Windows Guest

If features like enhanced file sharing do not work after a VMware Tools update, you might need to change or repair installed modules. Be sure to follow these steps. Do not use the guest's **Add/Remove Programs** item in the Windows Control Panel.

To repair or change installed modules

- 1 In Workstation, select the virtual machine and choose **VM > Reinstall VMware Tools**.
 - 2 On the Welcome page, click **Next** and do one of the following:
 - Click **Change** to repair or modify which modules of VMware Tools are installed.
 - Click **Modify** to specify which modules are installed.

Occasionally, some new modules are not installed during an update. You can manually install new modules by using the **Modify** option.
 - 3 Complete the rest of the pages of the wizard.
- If features still do not work, uninstall VMware Tools and reinstall.

Open the VMware Tools Control Panel

Use the VMware Tools control panel to modify VMware Tools configuration settings, shrink virtual disks, and connect and disconnect virtual devices.

Before you begin, make sure VMware Tools is installed in the guest operating system.

On Windows Vista and Windows 7 guests, log in to the operating system as an Administrator user.

To open the VMware Tools control panel

Do one of the following:

- On Windows guests, double-click **VMware Tools** icon in the notification area of the guest's Windows taskbar.
- If you cannot find the **VMware Tools** icon in the notification area, use the guest's Windows Control Panel to display it.
- On Linux, FreeBSD, and Solaris guests, open a terminal window and enter the following command:


```
/usr/bin/vmware-toolbox
```
 - On NetWare guests, do one of the following:
 - In a NetWare 5.1 or higher guest, choose **Novell > Settings > VMware Tools for NetWare**.
 - In a NetWare 4.2 guest, use VMware Tools commands in the system console. The VMware Tools program is called `vmwtool`.

Use the Windows Control Panel to Display the Taskbar Icon

If VMware Tools is installed in a Windows guest operating system but the **VMware Tools** icon does not appear in the notification area of the Windows taskbar, you can use the Windows Control Panel to display it.

To use the Windows Control Panel to display the taskbar icon

- 1 Go to **Start > Control Panel**.
- 2 Double-click the **VMware Tools** icon.
- 3 On the **Options** tab, select **Show VMware Tools in the taskbar** and click **Apply**.

Options Tab Settings

The **Options** tab of the VMware Tools control panel provides the following options:

- **Time synchronization between the virtual machine and the host operating system** – Sets the time of the guest operating system to be the same as the time of the host and then periodically (every minute) checks whether the guest operating system's time matches that of the host's. If not, the clock on the guest is synchronized to match the clock on the host.

If the clock on the guest falls behind the clock on the host, VMware Tools moves the clock on the guest forward to match the clock on the host. If the clock on the guest is ahead of that on the host, VMware Tools causes the clock on the guest to run more slowly until the clocks are synchronized.

If you use this option, disable all other time synchronization mechanisms. For example, some guests might have NTP or CMOS clock synchronization turned on by default.

Regardless of whether you turn on VMware Tools periodic time synchronization, time synchronization occurs when the VMware Tools daemon is started (such as during a reboot or power on operation), when resuming a virtual machine from a suspend operation, after reverting to a snapshot, and after shrinking a disk. When the operating system starts or reboots, and when you first turn on periodic time synchronization, synchronization can be either forward or backward in time. For other events, synchronization is forward in time.

To disable time synchronization completely, see [“Disable Time Synchronization by Editing the Virtual Machine Configuration File”](#) on page 121.

- **Show VMware Tools in the taskbar** – (Windows guests only) Displays the **VMware Tools** icon in the notification area of the taskbar. The icon indicates whether VMware Tools is running and whether an update is available.

- **Notify if update is available** – (Windows guests only) Displays the **VMware Tools** icon with a yellow caution icon when an update is available.
- **Update** button – (Windows guests only) Becomes enabled when an update is available. Clicking this button has the same effect as choosing **VM > Update VMware Tools** from the Workstation menu bar.

Disable Time Synchronization by Editing the Virtual Machine Configuration File

A virtual machine occasionally synchronizes time with the host even if you use the VMware Tools control panel (**Options** tab) to disable periodic time synchronization. You can disable time synchronization completely by editing the virtual machine configuration file.

You can follow these steps to keep a fictitious time in your guest, so that the guest is never synchronized with the host.

To disable time synchronization by editing the virtual machine configuration file

- 1 Power off the virtual machine.
- 2 Open the virtual machine's configuration file (.vmx) in a text editor and set the following options to FALSE.

Table 5-2. Time Synchronization Options

Option Name	Synchronization Occurs During the Following Event
<code>tools.syncTime</code>	Periodically (normally once per minute). Time synchronization is only forward in time.
<code>time.synchronize.continue</code>	Taking a snapshot. Time synchronization is only forward in time.
<code>time.synchronize.restore</code>	Reverting to a snapshot. Time synchronization is only forward in time.
<code>time.synchronize.resume.disk</code>	Resuming a suspended virtual machine. Time synchronization is only forward in time.
<code>time.synchronize.shrink</code>	Shrinking a virtual disk. Time synchronization is only forward in time.
<code>time.synchronize.tools.startup</code>	Booting the guest operating system. Time synchronization can be either forward or backward in time.

- 3 Save and close the file.

Devices Tab Settings

The **Devices** tab of the VMware Tools control panel provides options for enabling and connecting to removable devices such as floppy drives, DVD/CD-ROM drives, ISO images, USB devices, sound adapters, and network adapters. By default, floppy drive is not connected when the virtual machine powers on.

The controls for connecting and disconnecting devices might not be available, depending on whether your system administrator enabled them.

You might not see a particular network adapter listed that should appear in the list. If this happens, edit the virtual machine settings to remove all network adapters from the list and then add them back to the list.

Besides using the VMware Tools control panel to connect or disconnect a device, you can right-click the device icon in the status bar of the virtual machine window. See [“Use Removable Devices in a Virtual Machine”](#) on page 181.

Scripts Tab Settings

From the **Scripts** tab of the VMware Tools control panel, you can edit, disable, or run scripts that help automate guest operating system operations when you change the virtual machine's power state.

From this tab, you can also specify the location of custom scripts for the **Suspend**, **Resume**, **Power On**, **Power Off**, and **Reset** buttons. On Linux, Solaris, and FreeBSD guests, you must be logged in as root to use this tab.

On most guest operating systems, if VMware Tools is installed and if you configure a virtual machine's power controls to use the guest options, one or more default scripts run on the guest whenever you change the power state of the virtual machine.

For example, if you use the virtual machine settings editor (choose **VM > Settings > Options > Power**) and set the **Power Off** control to use **Shutdown Guest**, then the `poweroff-vm-default` script runs when you click the **Power Off** button in the Workstation toolbar. This script causes the guest operating system to shut down gracefully.

Scripts can be run on most guest operating systems, but not on Windows 95 and NetWare guests. See [“Run or Disable a Script”](#) on page 128.

Shrink Tab Settings

The **Shrink** tab of the VMware Tools control panel provides options for reclaiming unused space in a virtual disk. If your virtual machine cannot be shrunk, this tab displays information explaining why you cannot shrink your virtual disks.

Shrinking a disk is a two-step process: a preparation step and the shrink step. In the first step, VMware Tools reclaims all unused portions of disk partitions (such as deleted files) and prepares them for shrinking. This step takes place in the guest operating system.

The shrink process is the second step, and it takes place outside the virtual machine. The VMware application reduces the size of the disk based on the disk space reclaimed during the preparation step. If the disk has empty space, this process reduces the amount of space the virtual disk occupies on the host drive. See [“Compact a Virtual Disk”](#) on page 240.

On Linux, Solaris, and FreeBSD guests, run VMware Tools as the root user to shrink virtual disks. If you shrink the virtual disk as a nonroot user, you cannot prepare to shrink the parts of the virtual disk that require root-level permissions.

About Tab

The **About** tab displays version (build number) and copyright information. In Windows guests, this tab also shows the status of the VMware Tools service.

Configure VMware Tools in a NetWare Guest

In a NetWare virtual machine, using the system console, you can configure certain virtual machine options such as time synchronization, CPU idling, and device configuration with VMware Tools. The VMware Tools command-line program is called `vmwtool`.

To configure VMware Tools in a NetWare Guest

- 1 Open a terminal window (system console) in the NetWare guest.
- 2 Enter a command that uses the following format:

```
vmwtool <command>
```

`<command>` is one of the commands listed in [Table 5-3](#).

Table 5-3. vmwtool Commands

vmwtool Command	Description
<code>help</code>	Displays a summary of VMware Tools commands and options in a NetWare guest.
<code>partitonlist</code>	Displays a list of all disk partitions in the virtual disk and whether or not a partition can be shrunk.
<code>shrink [<partition>]</code>	Shrinks the listed partitions. If no partitions are specified, all partitions in the virtual disk are shrunk. The status of the shrink process appears at the bottom of the system console.
<code>devicelist</code>	Lists each removable device in the virtual machine, its device ID, and whether the device is enabled or disabled. Removable devices include the virtual network adapter, CD-ROM, and floppy drives. By default, floppy drive is not connected when the virtual machine powers on.
<code>disabledevice [<device name>]</code>	Disables the specified device or devices in the virtual machine. If no device is specified, all removable devices in the virtual machine are disabled.
<code>enabledevice [<device name>]</code>	Enables the specified device or devices in the virtual machine. If no device is specified, all removable devices in the virtual machine are enabled.
<code>synctime [on off]</code>	Lets you turn on or off synchronization of time in the guest operating system with time on the host operating system. By default, time synchronization is turned off. Use this command without any options to view the current time synchronization status.
<code>idle [on off]</code>	Lets you turn the CPU idler on or off. By default, the idler is turned on. The CPU idler program is included in VMware Tools for NetWare guests. The idler program is needed because NetWare servers do not idle the CPU when the operating system is idle. As a result, a virtual machine takes CPU time from the host regardless of whether the NetWare server software is idle or busy.

Customizations to VMware Tools

Customizations include modifying or writing scripts that run when a virtual machine's power state changes, executing commands when you shut down or restart a Linux, Solaris, or FreeBSD guest, and passing commands in strings that run in startup scripts.

How VMware Tools Scripts Affect Power States

When VMware Tools is installed, if you configure a virtual machine's power controls to use the guest, or soft, power options, one or more default scripts run on the guest whenever you change the power state of the virtual machine. You change the power state by using menu commands or by clicking the **Suspend**, **Resume**, **Power On**, and **Power Off** buttons.

What the default scripts do depends in part on the guest operating system:

- On most Microsoft Windows guests, but not windows NT and Windows Me, the default script executed when you suspend a virtual machine releases the IP address of the virtual machine. The default script executed when you resume a virtual machine renews the IP address of the virtual machine (this affects only virtual machines configured to use DHCP). Scripts cannot be run on Windows 95 guests.

In Windows guests, the default scripts are located in the Program Files\VMware\VMware Tools folder.

- On most Linux, Solaris, and FreeBSD guests, the default script executed when you suspend a virtual machine stops networking for the virtual machine. The default script executed when you resume a virtual machine starts networking for the virtual machine. Scripts cannot be run on NetWare and FreeBSD guests.

On Linux, Solaris, and FreeBSD guests, the default scripts are located in the `/etc/vmware-tools` directory.

You can create your own scripts and use them instead of the default scripts shown in [Table 5-4](#).

Table 5-4. Default VMware Tools Scripts

Script Name	Description
<code>poweroff-vm-default</code>	<p>If you configured the power-off operation to shut down the guest, this script runs when the virtual machine is being powered off.</p> <p>If you configured the reset operation to restart the guest, this script runs when the virtual machine is being reset.</p> <p>This script has no effect on networking for the virtual machine.</p>
<code>poweron-vm-default</code>	<p>If you configured the power-on operation to start the guest, this script runs when the virtual machine is being powered on rather than resumed.</p> <p>If you configured the reset operation to restart the guest, this script runs after virtual machine restarts.</p> <p>This script has no effect on networking for the virtual machine.</p>
<code>resume-vm-default</code>	<p>If you configured the power-on operation to start the guest, or the reset operation to restart the guest, this script runs when the virtual machine is resumed after it was suspended.</p> <p>On Windows guests, if the virtual machine is configured to use DHCP, this script renews the IP address of the virtual machine.</p> <p>On Linux, FreeBSD, and Solaris guests, this script starts networking for the virtual machine.</p>
<code>suspend-vm-default</code>	<p>If you configured the suspend operation to suspend the guest, this script runs when the virtual machine is being suspended.</p> <p>On Windows guests, if the virtual machine is configured to use DHCP, this script releases the IP address of the virtual machine.</p> <p>On Linux, FreeBSD, and Solaris guests, this script stops networking for the virtual machine.</p>

Create Scripts to Override Default VMware Tools Scripts

You can create your own scripts to override the default VMware Tools scripts that control power state changes.

Scripts are run by the VMware Tools daemon (`vmtoolsd.exe` on Windows and `vmtoolsd` on Linux, Solaris, and FreeBSD). Because `vmtoolsd` is run as root on Linux, Solaris, and FreeBSD and as System on Windows, the scripts are run in a separate session from the logged-in user's session. The VMware Tools daemon has no knowledge of desktop sessions, which means that it cannot display graphical applications. Do not attempt to use custom scripts to display graphical applications.

Before creating custom scripts, make sure that the following conditions are met in the guest operating system:

- The virtual machine is using the latest version of VMware Tools.
- The VMware Tools service is running in the virtual machine.
- Depending on the operation the script performs, the virtual machine has a virtual network adapter connected. If not, the power operation fails.
- (Linux, Solaris, and FreeBSD guests only) To edit a script by using the **Edit** button on the **Scripts** tab, `xterm` and `vi` must be installed in the guest operating system and must be in your `PATH`. You must be a root user to edit the script.

To create scripts to override default VMware Tools scripts

- 1 Determine whether you want to create your custom script by making changes to the default script and saving it to a new location.

In Windows guests, the default scripts are located in the `Program Files\VMware\VMware Tools` folder.

On Linux, Solaris, and FreeBSD, the default scripts are located in the `/etc/vmware-tools` directory.

- 2 Modify the default script and save it with a different name or write a different script.

On Windows guests, if you write a new script, create the script as a batch file. For Linux, Solaris, and FreeBSD, create the script in any executable format (such as shell or Perl scripts).

You can also use the **Edit** button on the **Scripts** tab of the VMware Tools control panel to edit a custom script. You can also edit scripts manually using any text editor.

- 3 Associate each custom script with its particular power operation:
 - a On the **Scripts** tab of the VMware Tools control panel, select the appropriate script event.
 - b Select the **Use Script** check box, select **Custom script**, and use the **Browse** button to point to the script you want to use.
 - c Click **OK**.

When you reinstall VMware Tools after you update the Workstation software, any changes you made to the default scripts are overwritten. Any custom scripts you created remain untouched, but do not benefit from any underlying changes that enhance the default scripts.

Run or Disable a Script

If you are creating a custom script, run the script before associating it with a power operation.

To run or disable a script

- 1 On the **Scripts** tab of the VMware Tools control panel, select the appropriate script event.
- 2 Do one of the following:

- To disable the script, clear the **Use Script** check box and click **OK**.

Default scripts for suspending and resuming work together. If you disable the script of one of these actions, disable the script for the other action as well.

- To run a script immediately, click **Run Now**.

You can successfully run a script by clicking the **Run Now** button in the VMware Tools control panel, but this same script can fail when run as part of a Workstation power operation. This is because scripts run by clicking **Run Now** are run as the logged-in user and have a different working directory than when scripts are run by the VMware Tools daemon during a power operation.

Execute Commands After You Power Off or Reset a Virtual Machine

In a Linux, Solaris, or FreeBSD guest, you can use the VMware Tools service to execute specific commands when you shut down or restart the guest operating system. This is in addition to any script that you specified to run when you shut down the guest operating system.

- 1 Use a text editor to open the following file:
`/etc/vmware-tools/tools.conf`
- 2 Add one or both of the following commands to the file:

- **halt-command** = <command>

<command> is the command to execute when you shut down the guest operating system.

- **reboot-command** = <command>

<command> is the command to execute when you restart the guest operating system.

Passing a String from the Host to the Guest at Startup

To pass a string from the host to the guest at startup, you pass the string from your virtual machine's configuration file in the host to the guest operating system when you power on the virtual machine.

You can pass items like the Windows system ID (SID), a machine name, or an IP address. Inside the guest operating system startup script, you can have the service retrieve this string. The string can then be used in another script to set your virtual machine's system ID, machine name, or IP address.

Use this strategy, for example, to make copies of the same configuration file, add a different string to each (either in the configuration file itself or at the command line), and use these variations of the same configuration file to launch the same virtual disk in nonpersistent mode multiple times in a training or testing environment.

Passing a string is also useful when you want to deploy virtual machines on a network using a common configuration file while providing each machine with its own unique identity.

You can pass strings to a virtual machine's guest operating system in one of two ways: placing the string in the virtual machine's configuration file or passing the string to the guest from the command line.

Use this feature only if you have a good understanding of a scripting language (for example, Perl or NetShell) and know how to modify system startup scripts.

String in a Configuration File

Place a string in the virtual machine's configuration file (.vmx file) by setting the string to the `machine.id` parameter. For example, you can set this string:

```
machine.id = "Hello World."
```

Following is an example of portions of two configuration files that point to the same virtual disk. Each configuration file contains its own unique string set for the `machine.id` parameter.

`config_file_1.vmx` contains:

```
ide0:0.present = TRUE
ide0:0.fileName = "my_common_virtual_hard_drive.vmdk"
machine.id = "the_string_for_my_first_vm"
```

`config_file_2.vmx` contains:

```
ide0:0.present = TRUE
ide0:0.fileName = "my_common_virtual_hard_drive.vmdk"
machine.id = "the_string_for_my_second_vm"
```

To prevent a string from being passed from the host to the guest through the service, set the following line in your virtual machine's configuration file:

```
isolation.tools.getMachineID.disable = "TRUE"
```

String in a Startup Command

Rather than setting the `machine.id` parameter in the configuration file, you can pass the string to the guest operating system from the command line when you power on the virtual machine. Following is an example of such a startup command (entered on one line):

```
"C:\Program Files\VMware\VMware Workstation\vmware -s
    'machine.id=Hello World'
    C:\Virtual Machines\win2000\win2000.vmx"
```

Use this method to deploy virtual machines on a network using a common configuration file while providing each machine with its own unique identity.

Launch each virtual machine with the **vmware -s** command. Each virtual machine disk file must be copied into its own directory if it shares its filename with another virtual machine disk file.

On a Linux host, the machine ID passed on the command line takes precedence and is passed to the guest operating system if the following conditions are met:

- A virtual machine ID is specified in the virtual machine's configuration (.vmx) file which is used to open the virtual machine.
- You specify a machine ID on the command line.

Use a String in a Startup Script to Set a Name and IP Address

The following example uses a Windows host to illustrate how you can use the service to retrieve a string containing what becomes the virtual machine's machine name and IP address. In this example, W2K-VM is the machine name and 148.30.16.24 is the IP address.

To use a string in a startup script to set a name and IP address

- 1 Define the string by using one of the following methods:
 - On the host machine, add the following line to your virtual machine's configuration file (.vmx file):


```
machine.id = "W2K-VM 148.30.16.24"
```

Open the virtual machine using this configuration file.
 - Open the virtual machine from the command line by entering the following on one line:


```
"C:\Program Files\VMware\VMware Workstation\vmware -s  
'machine.id=W2K-VM 148.30.16.24' C:\Virtual  
Machines\win2000\win2000.vmx"
```
- 2 Do one of the following to retrieve the string in the virtual machine:
 - In a Windows guest, enter the following command to retrieve the string:


```
vmtoolsd --cmd machine.id.get
```
 - In a Linux guest, in the operating system's startup script, add the following command before the network startup section. For example:


```
/usr/sbin/vmtoolsd --cmd 'machine.id.get'
```

The location of `vmtoolsd` depends on the directory you specify at the time of installation.
- 3 Further customize this startup script so that it uses the string the service retrieved during startup to set the virtual machine's network name to W2K-VM and its IP address to 148.30.16.24.
- 4 Place this string in the script before the command to start the network services.

If you're using a Windows 2000 guest operating system, for example, you can call the NetShell utility (`netsh`) and pass it the contents of the string, which uses the string accordingly. That is, it can set a new IP address for the virtual machine, if that is what was passed in the string originally.

Passing Information Between the Guest and Another Program

The VMware Tools service allows you to use VMware programmatic interfaces to manage virtual machines from your own independent programs and from existing frameworks developed by partners and third parties.

For more information about the VMware Infrastructure SDK, go to the VMware APIs and SDKs Documentation page of the VMware Web site.

Use the VMware Tools Service Command-Line Interface

The VMware Tools command-line interface enables you to do the following:

- Configure time synchronization in your Linux guest operating system without running X.
- Upgrade and uninstall VMware Tools, determine the version, and so on.

To use the VMware Tools command-line interface

- 1 On the guest operating system, change directories to the directory that contains the VMware Tools daemon.

Depending on the operating system, the name and default location of the daemon are as follows:

- On Microsoft Windows systems, the daemon is called `vmtoolsd.exe` and the location is:

```
C:\Program Files\VMware\VMware Tools\vmtoolsd.exe
```

- On Linux, Solaris, and FreeBSD systems, the daemon is called `vmtoolsd`. The location of `vmtoolsd` depends on the directory you specify at the time of installation. The default location is:

```
/usr/sbin/vmtoolsd
```

- 2 To configure periodic time synchronization, use the `vmx.set_option` command.

Use the following syntax:

```
<daemon> --cmd "vmx.set_option synctime <old_val> <new_val>"
```

<daemon> is **vmtoolsd** on Linux, Solaris, and FreeBSD systems or **vmtoolsd.exe** on Windows systems.

<old_val> and <new_val> are the old and new values, respectively. Use 0 to mean FALSE and 1 to mean TRUE.

Following is an example of setting time synchronization to TRUE on a Linux guest:

```
./vmtoolsd --cmd "vmx.set_option synctime 0 1"
```

The new setting is written to the `tools.syncTime` property in the virtual machine's configuration (`.vmx`) file. Using this option is equivalent to using the time synchronization option on the **Options** tab of the VMware Tools control panel.

- 3 To use commands other than `--cmd`, use the `--help` command-line command.

Creating a Virtual Machine from a System Image or Another Virtual Machine

6

This chapter describes how to convert a physical machine, virtual machine, or system image to a VMware virtual machine. On Windows hosts, you can convert a virtual machine that was created by using a third-party product.

This chapter includes the following topics:

- [“Conversion Process for Importing from Other Formats”](#) on page 133
- [“VMware Converter Compared to the Conversion Wizard”](#) on page 135
- [“Supported Source Machines”](#) on page 135
- [“Supported Destinations”](#) on page 140
- [“Conversion Impact on Settings”](#) on page 142
- [“Open a Third-Party Virtual Machine or System Image”](#) on page 143
- [“Import a Virtual Machine, Virtual Appliance, or System Image”](#) on page 144

Conversion Process for Importing from Other Formats

On Windows hosts, Workstation 7.0 incorporates the Conversion wizard from the VMware Converter product. Using the Conversion wizard to perform a conversion to VMware virtual machines enables you to do the following:

- Avoid reinstalling operating systems and applications for system configurations you use often.
- Overcome legacy migration barriers. Certain legacy systems might be impossible to recreate through reinstallation.
- Convert a physical machine into a virtual machine.

- Use virtual machines or system images created with products from other companies such as Norton, Symantec, and StorageCraft.
- Convert virtual appliances that use open virtualization format (OVF).

Workstation provides three ways to convert a virtual machine or system image:

- Using the **File > Open** command converts and opens a virtual machine or system image quickly. Workstation uses default settings to make the conversion automatically, with no input required from you. The original Microsoft Virtual PC, Symantec Backup Exec System Recovery, StorageCraft ShadowProtect, or Acronis True Image (.vnc, .spf, .sv2i, or .tib) file is unchanged.

For all supported file types except .ovf and .ova files, the **File > Open** command creates a linked clone when it opens the file. If you open a virtual appliance that uses .ovf or .ova files, Workstation creates a full clone.

If you attempt to open a virtual machine or system image that is password protected, you are prompted for the password, and Workstation creates a full clone.

- Using the **File > Import or Export** command starts the Conversion wizard. It lets you specify the converted virtual machine's location, whether or not the converted virtual machine shares virtual disks with the original virtual machine or system image, and which versions of VMware products the converted virtual machine is to be compatible with.
- Using **File > Import Windows XP Mode VM** command imports a Windows XP Mode virtual machine on Windows 7 hosts. See [“Import a Windows XP Mode Virtual Machine”](#) on page 145.

The wizard creates a completely new VMware virtual machine based on the input virtual machine or system image. The newly migrated VMware virtual machine retains the configuration of the original virtual machine or image.

The migration process can be nondestructive, so you can continue to use the original virtual machine with Microsoft Virtual PC, or the original system image with Symantec Backup Exec System Recovery. However, to run a new VMware virtual machine on the same network as the original Virtual PC virtual machine, you must modify the network name and IP address on one of the virtual machines so the original and new virtual machines can coexist.

For Microsoft Virtual PC and Microsoft Virtual Server virtual machines, you have the option of sharing the source virtual hard disk (.vhd) files. This means that the VMware virtual machine can write directly to the original .vhd files instead of VMware virtual hard disk (.vmdk) files.

VMware Converter Compared to the Conversion Wizard

Workstation 7.0 incorporates the Conversion wizard from the VMware Converter product. VMware Converter is a separate downloadable application for Windows hosts that provides an easy-to-use, scalable solution for migrations of machines, both physical to virtual and virtual to virtual. In addition to the Conversion wizard, VMware Converter provides a task manager that lets you schedule migrations of many machines.

The Conversion wizard included with Workstation lets you create VMware virtual machines from a local or remote physical machine or from virtual machines and system images that were originally created by using other products than VMware products. You can also use the wizard to change a virtual machine using one VMware format to that using another. For example, you can copy a VMware Server virtual machine and use it to create an ESX virtual machine.

To use other features of VMware Converter, such as its task manager, or the ability to import more than one virtual machine at a time, download the VMware Converter.

Supported Source Machines

The VMware Conversion wizard in Workstation allows you to import the following types of physical and virtual machines:

- Physical machines
 - Windows Server 2003 32-bit and 64-bit
 - Windows XP Professional 32-bit and 64-bit
 - Windows Vista 32-bit and 64-bit
- VMware virtual machines (.vmx and .vmtx files)
 - Workstation 4.5, 5.x, 6.x, and 7.0
 - VMware ACE 2.x
 - VMware Fusion 1.x
 - VMware Player 1.x, 2.x, and 3.0
 - ESX Server 3.x

- ESX Server 2.5.x (if the virtual machine is managed with VirtualCenter 2.x)
- VMware Server 1.x and 2.0. x (if the virtual machine is on the local file system)
- VirtualCenter 2.x
- Virtual appliances

Appliances that use open virtualization format (.ovf and .ova files) and that use VMware virtual hard disks (.vmdk files).
- Other virtual machines and system images
 - Acronis True Image 9 (.tib files)
 - StorageCraft ShadowProtect (.spf files)
 - Microsoft Virtual PC 7.x and higher (.vmc files)
 - Any version of Microsoft Virtual Server (.vmc files)
 - Symantec Backup Exec System Recovery (formerly LiveState Recovery) 6.5 and 7.0, LiveState Recovery 3.0 and 6.0 (.sv2i files)
 - Norton Ghost images 9.x and higher (.sv2i files)

For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link.

NOTE Virtual machines from Macintosh versions of Microsoft Virtual PC are not supported.

Importing from Various Sources

Consider these points when using the Conversion wizard.

Physical Machine Source

To import a remote machine, you are prompted to supply the computer name or IP address and the user name and password for logging in to the machine with administrative privileges. The user name must take the form <DOMAIN>\<user_name>.

NOTE Remote physical machines cannot be imported into an ESX-compatible format by the wizard.

Microsoft Virtual PC and Virtual Server Virtual Hard Disks

As of Workstation 7.0, a converted virtual machine can share the source Microsoft virtual hard disk (.vhd files). This means that the VMware virtual machine can write directly to the original .vhd files instead of VMware virtual hard disk (.vmdk) files.

If you select **Share source** the converted virtual machine consists of a VMware virtual machine configuration file (.vmx file) and the original .vhd file, which remains in its original location. VMware modifies the .vhd file, installing VMware-specific video drivers, device drivers for virtual network cards, and so on. The VMware -specific drivers replace the Microsoft drivers.

ShadowProtect and Backup Exec System Recovery Images

You can import ShadowProtect and Backup Exec System Recovery images, but keep the following limitations in mind:

- Dynamic disks are not supported.
- All images for the backup of a machine should be in a single folder, with no other images placed there.
- All volumes in the disk up to the active and system volumes must be backed up. For example, if a disk has four partitions, 1–4, with partition 2 as the active volume and partition 3 as the system volume, the backup must include 1 through 3.
- If it is an incremental image, up to 16 incremental backups are supported.
- For ShadowProtect, images of systems with logical drives are not supported if the logical drive is also a system or active volume.

Appliances That Use Open Virtualization Format

Open virtualization format (OVF) is a platform-neutral, secure, and portable format for packaging and distributing virtual appliances. Although OVF does not rely on a specific virtualization platform, the Conversion wizard supports only OVF appliances that use VMware virtual hard disks (.vmdk files).

In the Conversion wizard, you can select .ovf files, which are the OVF equivalent of a VMware virtual machine configuration file (.vmx file), or you can select .ova files (open virtual appliance files). An .ova file stores the configuration file and virtual hard disk file together, like a .zip file, for easy distribution.

When specifying the location of the OVF appliance, you can browse to a directory or use a URL to download the appliance from a Web server. You can also download the appliance from a secure (HTTPS) Web server.

NOTE When you use a URL, the virtual appliance is downloaded before the conversion process starts. Downloading can take 15 minutes or longer, depending on the size of the file.

The Conversion wizard always makes a full clone when it converts an OVF appliance to a virtual machine. See [“Full or Linked Clones”](#) on page 139.

Dual-Boot System Source

When you import a physical machine that is part of a dual-boot system, you can import only the default operating system to which `boot.ini` points. To import the nondefault operating system, change `boot.ini` to point to the other operating system and reboot before attempting to import. Even if `boot.ini` points to the correct operating system, occasionally, the virtual machine might not be bootable in the default operating system.

Windows NT Virtual Machine Source

If the source virtual machine is Windows NT SMP, the wizard might require files from service packs or hot fixes. The wizard shows which files it requires. You must browse to the required files. They can be on a disk, your local system, or the network.

On Windows NT machines, during the import process, a snapshot driver is downloaded to the machine. This driver handles the copying and moving of files and registry settings. The driver requires a reboot to complete its tasks. When it is finished, the driver is uninstalled.

NOTE Although Windows NT virtual machines are supported as a source, Windows NT physical machines are not supported.

ESX Virtual Machine Source

You must supply the name of the ESX server and the user name and password for logging in.

Password-Protected Virtual Machines

If the virtual machine you want to import is password protected, you must supply the password.

About Page Files and Hibernation Files

You can import all the disks for the physical or virtual machine or, to save space, you can select some of the volumes and leave out others. If you select specific volumes, you can also ignore the page and hibernation files. These files are large and, for volume-based cloning, do not provide information that you need to copy.

Supported Volume Types

Some types of source volumes, or partitions, are unsupported and are skipped during cloning. Virtual machine importing supports basic volumes and all types of dynamic volumes except RAID. Only Master Boot Record (MBR) disks are supported. GUID Partition Table (GPT) disks are not supported.

Disk Space Allocation

As is the case when you use the New Virtual Machine wizard, you must specify whether to allocate all the space at creation time or allow the files to grow. Allocating space at creation time gives you better performance but is a time-consuming process. VMware recommends that you allow the disk to grow.

Select the option **Split disk into 2GB files** if your virtual disk is stored on a file system that does not support files larger than 2GB.

Full or Linked Clones

If the source is a virtual machine, you can create a full or linked clone. On the Virtual Machines Options page of the Conversion wizard, select **Import and Convert** to create a full clone. Select **Share source and store changes separately** to create a linked clone.

NOTE For Microsoft Virtual PC and Virtual Server virtual machines, you have a third option. Instead of creating a full or linked clone, you can have the converted virtual machine use the original Microsoft virtual hard disk. This option modifies the source virtual machine. See [“Microsoft Virtual PC and Virtual Server Virtual Hard Disks”](#) on page 137.

Linked clones can be created from VMware virtual machines, Symantec Backup Exec System Recovery virtual machines (.sv2i files), Microsoft Virtual PC and Virtual Server virtual machines, Acronis True Image (.tib files), and StorageCraft files (.spf files). Creating a linked clone of a VMware virtual machine requires that the virtual hardware version of the destination machine not be higher than the hardware version of the source.



CAUTION For linked clones, the virtual machine created by the wizard becomes corrupted if the source is modified after the import. This is true for linked clones imported from Virtual PC and Virtual Server machines and from Symantec backup images. In the case of Virtual PC and Virtual Server source virtual machines, powering them on in Virtual PC or Virtual Server modifies them.

Supported Destinations

The Conversion wizard can create virtual machines that are compatible with the following products:

- Workstation 4.5, 5.x, 6.x, and 7.0
- VMware ACE 1.x, 2.x, and 2.6
- VMware Fusion 1.x, 2.x, and 3.0
- VMware Player 1.x, 2.x, and 3.0
- ESX Server 3.x (This destination is not supported if you are importing a remote physical machine.)
- ESX Server 2.5.x (This destination is supported only by importing through a VirtualCenter 2.x server that manages the 2.5.x ESX Server.)
- VMware Server 1.x and 2.0.x (if the virtual machine is on the local file system)
- VirtualCenter 2.x

NOTE Workstation 4 virtual machines are compatible with VMware GSX Server 3.0, ESX Server 2.x, and ACE 1.x.

Designating a Destination for a Virtual Machine

Consider these points when using the Conversion wizard to specify a destination for a newly created virtual machine.

ESX Virtual Machine Destination

You must supply the name of the ESX server and the user name and password for logging in.

VirtualCenter Virtual Machine Destination

You must provide the following information:

- Name of the VirtualCenter server and the user name and password for logging in.
- Name of the folder in the VirtualCenter inventory where you want to store the virtual machine.

- Name of the host, cluster, or resource pool within a host or cluster from which the virtual machine is to be run. If you select a cluster in manual mode, you must also choose a specific host.
- Name of the datastore for the virtual machine's configuration files and disks. Use the advanced setting to distribute the virtual machine's disks over multiple datastores.

Network Adapters

You are prompted to choose from the available networks at the destination location. For more information about networking choices for virtual machines used with Workstation rather than ESX or Virtual Center, see [“Common Networking Configurations”](#) on page 286.

Optional Guest Operating System Customization

You can make changes to the identity of the virtual machine (such as computer name and security ID), networking information, and so on with the wizard. For virtual machines that are converted to ESX virtual machines, you can have the wizard install VMware Tools if the guest operating system is Windows 2000 or later.

You can make the following customizations:

- Computer information
 - **Computer name** – Alphanumeric name up to 63 characters. Hyphens and underscores are allowed.
 - **Security ID (SID)** – Optionally, generate a new security ID.
 - **Sysprep file location** – If the wizard can detect the location, the wizard page displays it. Otherwise, you need to supply the location.
- Windows licensing information
 - **Product ID** – Optional.
 - **Windows Server license information** – For Microsoft Windows 2000 Server and 2003 Server only.
- Time zone

- Network information
 - **Network adapter (interfaces)** – Reset to default or make changes.
 - **DHCP** – Choose between using DHCP to obtain IP addresses or entering them manually. You can also use DHCP to obtain a DNS server address or enter it manually.
 - **DNS** – Enter DNS suffixes and customize their order to specify the order in which a virtual machine uses them to make connections.
 - **WINS** – Specify primary and secondary WINS addresses.
 - **Workgroup or domain** – For workgroups, specify the workgroup name, up to 15 characters. For domains, specify the Windows Server domain, along with the appropriate user name and password.

Conversion Impact on Settings

The VMware virtual machine created by the Conversion wizard contains an exact copy of the disk state from your source virtual machine or system image, with the exception of some hardware-dependent drivers and, sometimes, the mapped drive letters.

The following settings from the source computer remain identical:

- Operating system configuration (computer name, security ID, user accounts, profiles and preferences, and so forth)
- Applications and data files
- Each disk partition's volume serial number

Because the target and the source virtual machines or system images have the same identities (name, SID, and so on), running both on the same network can result in conflicts. If you plan to redeploy the source virtual machine or system image, do not run both the source and target images or virtual machines on the same network at the same time.

Alternatively, you can resolve the duplicate ID problem by using additional tools, such as the Windows XP System Preparation Tool (Sysprep). For example, if you use the Conversion to test the viability of running a Virtual PC virtual machine as a VMware virtual machine without first decommissioning the original Virtual PC machine, you need to resolve the duplicate ID problem.

Migration Issues Caused by Hardware Changes

Most migrated applications function correctly in the VMware virtual machine because their configuration and data files have the same location as the source virtual machine. However, applications might not work if they depend on specific characteristics of the underlying hardware such as the serial number or the device manufacturer.

When troubleshooting after virtual machine migration, consider the following potential hardware changes:

- The CPU model and serial numbers (if activated) can be different after the migration. They correspond to the physical computer hosting the VMware virtual machine.
- The network adapter can be different (AMD PCNet or VMXnet) with a different MAC address. Each interface's IP address must be individually reconfigured.
- The graphics card can be different (VMware SVGA card).
- The numbers of disks and partitions are the same, but each disk device can have a different model and different manufacturer strings.
- The primary disk controllers can be different from the source machine's controllers.
- Applications might not work if they depend on devices that are not available from within a virtual machine.

Open a Third-Party Virtual Machine or System Image

The **File > Open** command lets you convert a virtual appliance, system image, or virtual machine created with software from another company into a VMware virtual machine.

To open a third-party virtual machine or system image

- 1 From the Workstation menu bar, choose **File > Open**.
- 2 In the **File name** field, browse to and open the configuration (`.vmx`, `.vmc`, `.spf`, `.ovf`, `.ova`, or `.sv2i`) file for the virtual appliance, virtual machine, or system image to convert.

You can use the field **Files of type** to filter the files displayed by file extension.

3 Click **Open**.

Workstation creates a VMware virtual machine, with a VMware configuration file (.vmx) for the converted virtual machine or system image. The converted virtual machine links to the virtual disks of the original virtual machine or system image unless the source uses open virtualization format (.ovf or .ova files). The original Virtual PC, Symantec Backup Exec System Recovery, or StorageCraft configuration (.vmc, .spf, or .sv2i) file is unchanged.

If you open a virtual appliance that uses .ovf or .ova files, Workstation creates a full clone.

If you attempt to open a virtual machine or system image that is password protected, you are prompted for the password, and Workstation creates a full clone.

Import a Virtual Machine, Virtual Appliance, or System Image

The **File > Import or Export** command enables you to convert a system image or virtual machine into a VMware virtual machine.

Before you begin, review the restrictions and requirements for source and destination virtual machines. See [“Supported Source Machines”](#) on page 135 and [“Supported Destinations”](#) on page 140.

To import a virtual machine, virtual appliance, or system image

- 1 If you are importing a virtual machine, make sure the virtual machine is powered off.
- 2 Choose **File > Import or Export** to launch the VMware Conversion wizard.
- 3 Complete the wizard pages.

The text on the wizard pages changes, depending on the selections you make. For example, on the Source Type page, when you select a source type from the drop-down list, the text below the list changes to describe which types of virtual machines are included in that source type.

As you proceed through the wizard, the navigation pane on the left side of the wizard helps track your progress.

Whenever you start a new phase or step, a list expands to display the names of the wizard pages included in that step. When you complete an entire step, the next step expands.

To go back to a previous page, click its name in the navigation pane.

Import a Windows XP Mode Virtual Machine

When you import a Windows XP Mode virtual machine, Workstation creates a linked clone from the parent virtual machine. You cannot use the linked clone if you delete the parent Windows XP Mode virtual machine. For more information on cloning, see [“Cloning a Virtual Machine”](#) on page 219.

Changes made to the original Windows XP Mode virtual machine through Virtual PC do not affect the virtual machine imported in VMware Workstation. Before you begin, make sure you complete the following tasks:

- Review the restrictions and requirements for source and destination virtual machines and importing from different sources. See [“Supported Source Machines”](#) on page 135 and [“Supported Destinations”](#) on page 140.
- You must have Windows 7 Professional, Enterprise, or Ultimate version of operating system running on your host. Windows XP Mode does not work on unsupported hosts.
- Download and install the Windows XP Mode virtual machine.

To import a Windows XP Mode virtual machine

Select **File > Import Windows XP Mode VM**.

A virtual machine is created in the default virtual machine directory. You can power on only one Windows XP Mode virtual machine at a time.

Getting Started with Virtual Machines

7

This chapter includes the following topics:

- [“Starting a Virtual Machine”](#) on page 148
- [“Shut Down a Virtual Machine”](#) on page 151
- [“Download Components”](#) on page 153
- [“Pausing a Virtual Machine”](#) on page 154
- [“Encrypting a Virtual Machine”](#) on page 155
- [“Delete a Virtual Machine”](#) on page 158
- [“Controlling the Virtual Machine Display”](#) on page 158
- [“Configuring Video and Sound”](#) on page 172
- [“Install New Software in a Virtual Machine”](#) on page 179
- [“Use Host Printers in a Virtual Machine”](#) on page 180
- [“Use Removable Devices in a Virtual Machine”](#) on page 181
- [“Configure the Appliance View for a Virtual Machine”](#) on page 182
- [“Create a Screenshot of a Virtual Machine”](#) on page 183
- [“Create and Play Back a Movie of a Virtual Machine”](#) on page 184
- [“Advanced Options for Application Developers”](#) on page 185

Starting a Virtual Machine

Starting a virtual machine means displaying its running console so that you can interact with it. Depending on the situation, starting a virtual machine can involve any of the following:

- To start a virtual machine from the Workstation user interface, you must open the virtual machine and power it on.
- To start a virtual machine that is running in the background when Workstation is not running, you must open its console from the taskbar on the host.
- To start a virtual machine that is available from a Web server, you must use a command-line command to begin streaming the virtual machine and then start it from the Workstation window.
- To start a virtual machine from the command line, you must use the platform-specific program and startup options. See [“Startup Options for Workstation and Virtual Machines”](#) on page 485.

Start a Virtual Machine from the Workstation User Interface

Before you begin, make sure that all of the virtual machine files are accessible to the host where Workstation is installed.

You can add the name of the virtual machine to the **Favorites** list so that you do not need to browse to the file to open the virtual machine. See [“Favorites List in the Sidebar”](#) on page 63.

To start a virtual machine from the Workstation user interface

- 1 Start Workstation.

For instructions, see [“Start Workstation on a Windows Host”](#) on page 53.

- 2 Choose **File > Open** and browse to the configuration file (.vmx file) for the virtual machine.

See [“Virtual Machine Location”](#) on page 150.

- 3 Choose **VM > Power > Power On**.

If you need to enter the BIOS setup for the guest operating system, choose **VM > Power > Power On to BIOS**.

- 4 Click anywhere inside the virtual machine console to give the virtual machine control of your mouse and keyboard.
- 5 To log on to the operating system in the virtual machine, type your name and password just as you would on a physical computer.

Start a Virtual Machine That Is Running in the Background

If you do not power off a virtual machine when you exit Workstation, the virtual machine continues to run in the background. To start the virtual machine, use the power status icon on the host to open the virtual machine's console.

By default Workstation is configured to display a power status icon in the notification area of the host's taskbar even when Workstation is not running.



If this icon is not visible, before you begin, use the **Workspace** tab of the Workstation preferences editor to display it. See [“Introduction to Workstation Preferences”](#) on page 67.

To start a virtual machine that is running in the background

- 1 Click the power status icon in the notification area of the host's taskbar.
- 2 Select a virtual machine from the list that appears in the tooltip.

The list contains the virtual machines and teams that belong to the user who is logged in.

Workstation starts and displays the console view of the virtual machine.

Start a Virtual Machine by Using VM Streaming

Beginning with Workstation 7.0, you can now stream a virtual machine from a Web server. You can start the virtual machine shortly after the download process begins.

Before you begin, determine the URL of the virtual machine and verify that the Web server on which it resides is correctly configured. See [“Make Virtual Machines Available for Streaming from a Web Server”](#) on page 230.

To start a virtual machine by using VM streaming

- 1 Open a command prompt or terminal window.
- 2 Use the platform-specific command with the URL of the virtual machine:

- On Windows hosts, use **vmware.exe http://<path_to_vm>.vmx**.
- On Linux hosts, use **vmware http://<path_to_vm>.vmx**.

HTTPS is also supported.

- 3 When a tab for the virtual machine opens in the Workstation window, choose **VM > Power > Power On**.

Virtual disk data is fetched on demand so that you can begin using the virtual machine before the download completes.

The status bar indicates the progress of the download. Point to the icon on the status bar for VM streaming and a tooltip indicates whether streaming is active and provides the URL of the Web server.

- 4 (Optional) To save the virtual machine so that you can use it when you do not have access to the Web server, choose **VM > Save for Offline Use**.

Using this setting also allows you to pause downloading by powering off the virtual machine before streaming is finished. You can restart later by powering on the virtual machine. It also allows you to use the **File > Open** command to open the virtual machine after you close it.

When you power off a streamed virtual machine, you are prompted to save or discard changes. If you discard changes, the directory that was created on your local machine and all the virtual machine data are deleted.

Virtual Machine Location

By default, virtual machine files are stored in the virtual machine's working directory:

- On Windows hosts, Workstation stores virtual machines in the **My Documents** folder of the user who is logged in at the time the virtual machine is created.

On Windows Server 2003 and Windows XP, the default folder is:

```
C:\Documents and Settings\<username>\My Documents\My Virtual
Machines\<guestOSname>
```

On Windows Vista and Windows 7, the default folder is:

```
C:\Users\<username>\Documents\Virtual Machines\<guestOSname>
```

- On Linux hosts, Workstation stores virtual machines in:

`<homedir>/vmware/<guestOSname>`

Here `<homedir>` is the home directory of the user who is logged in at the time the virtual machine is created.

The working directory is also where Workstation stores suspended state (`.vmss`), snapshot (`.vmsn`), and redo log files. The **General** tab of the virtual machine settings editor displays the path to the working directory. See [“Introduction to Virtual Machine Settings”](#) on page 69.

Shut Down a Virtual Machine

As with physical computers, you can shut down a guest operating system before you power off the virtual machine or team.

You are not required to shut down the guest before you exit Workstation. To exit Workstation but leave the virtual machine running in the background, see [“Closing Virtual Machines and Exiting Workstation”](#) on page 71.

To shut down a virtual machine

- 1 In the guest system, shut down the operating system as you would if you were using a physical machine rather than a virtual machine.

For example, in Windows XP, click **Start > Shut Down**.

- 2 In the Workstation menu bar, choose **VM > Power Options > Power Off** to turn off the virtual machine.

If you use the **Power Off** command before you shut down the guest operating system, the virtual machine is powered off abruptly. The effect is like using the power button on a physical machine. You can, however, configure the **Power Off** button in the toolbar to shut down the operating system before powering off. See [“Configure Power Off and Reset Options for a Virtual Machine”](#) on page 152.

Configure Power Off and Reset Options for a Virtual Machine

You can configure the **Power Off** toolbar button to power off the virtual machine abruptly or to send a signal that gracefully shuts down the guest operating system.

Before you begin, make sure VMware Tools is installed in the guest operating system. To perform a graceful shutdown, the VMware Tools service component issues a **Shutdown Guest** command and runs a script to shut down gracefully.



CAUTION Powering off abruptly works the same way a power switch works on a power supply. The power is cut off with no consideration for work in progress. If a virtual machine is writing to disk when it receives a **Power Off** command, data corruption might occur.

Similarly, you can configure the **Reset** button to work the same way as a reset switch, so that it resets the virtual machine abruptly. Or you can configure the **Reset** button so that the VMware Tools service sends a restart signal to the guest operating system. It then shuts down gracefully and restarts.

Not all guest operating systems respond to a shutdown signal from the **Power Off** button or to a restart signal from the **Reset** button. If your operating system does not respond to the signal, shut down or restart from the operating system, as you would with a physical machine.

To configure the Power Off and Reset options for a virtual machine

- 1 Select the virtual machine.
The virtual machine can be powered on or off.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab and select **Power**.
- 4 In the **Power Controls** section of the dialog box, set the **Power Off** button to shut down the guest gracefully or to abruptly power the virtual machine off.
The selection you make is reflected in the tooltip you see when you point to the **Power Off** button.
- 5 Specify how you want the **Reset** button to work.
- 6 If you want to change any of the other settings and need more information, click **Help**.

For UNIX guests, to pass X toolkit options when you power on a virtual machine, see [Appendix A, "Appendix: Workstation Command-Line Reference,"](#) on page 485.

Download Components

Workstation lists the components that must be installed to improve the user experience of the product. Before you begin, upgrade to the latest version of Workstation. Check to make sure you have network connectivity.

- 1 Power on the virtual machine.

The Software Updates dialog box appears with a list of components ready for download. If you are connected to the Internet you can decide whether to download the updates or receive a reminder to download later.

- 2 If you are using a proxy to connect to the Internet, complete the following tasks:

- a Select **VM > Install VMware Tools**.

The Software Updates dialog box appears.

- b Complete the proxy credentials to continue, and click **OK**.

The Software Updates dialog box appears with a list of components ready for download.

- 3 Download the component.

- Select **Download** to download the component.

Click **Hide** to minimize the Downloads dialog box in the Workstation status bar. You can click the arrow in the status bar to open the download progress window.

- Select **Do Not Download** to bypass the download.

- Select **Remind Later** to bypass the download now and receive a reminder later to download the component.

- 4 (Optional) Click the **Always do the selected action** check box to apply your preference for future component downloads.

Your preference is saved under **Edit > Preferences > Updates**.

- 5 Power on and log in to the virtual machine.

If you have not downloaded the component yet, VMware recommends that you do so at this time. On Windows, an info bar appears to remind you to install the component.

If the component you downloaded is a new or upgraded version of VMware Tools, click either **Update Tools**, **Install Tools**, or **Re-install Tools** and proceed with your installation based on your guest operating system requirements.

For more information on installing VMware Tools on various guest operating systems, see [“Installing VMware Tools”](#) on page 104.

Pausing a Virtual Machine

The pause feature causes a virtual machine to cease operation temporarily, without powering off or suspending. Use the pause feature when a virtual machine is engaged in an lengthy, processor-intensive activity that prevents you from using your computer to do a more immediate task.

When you pause a virtual machine, the display dims and a play button appears, which you can click to unpause the virtual machine. On paused virtual machines that are configured to display on more than one monitor, each monitor has a play button.

For virtual machines that belong to a team, you must pause and unpause each virtual machine separately, while it is active. The play button appears just as it does in virtual machines that do not belong to a team. The play button also appears in the thumbnail images of paused team virtual machines that are not currently active.

Pause Feature Limitations

The pause feature has the following restrictions:

- The pause feature does not work when a virtual machine is in Unity mode. You cannot switch to Unity mode when a virtual machine is paused.
- You cannot switch to exclusive mode when a virtual machine is paused.
- The pause feature does not work when you are using the record/replay feature or when the replay debugger is attached. The record/replay feature does not work when a virtual machine is paused.
- When paused, a virtual machine does not send or receive network packets. If a virtual machine is paused for more than a few minutes, some network connections might be interrupted.

- If you take a snapshot when the virtual machine is paused, the virtual machine is not paused when you restore that snapshot. Similarly, if you suspend a virtual machine while it is paused, it is not paused when you resume the virtual machine.
- If you initiate soft power operations when a virtual machine is paused, those operations do not take effect until the virtual machine is unpaused.
- While a virtual machine is paused, LEDs and devices remain enabled, but device connection changes do not take effect until the virtual machine is unpaused.

Pause and Unpause a Virtual Machine

You can pause a virtual machine multiple times ranging from a few seconds to several minutes. Before you begin, make sure you read the feature limitations. For more information, see [“Pause Feature Limitations”](#) on page 154.

To pause and unpause a virtual machine

- Select **VM > Pause** to pause the virtual machine.
The virtual machine display dims and a play button appears over the display.
- Click the play button on the virtual machine display, or deselect **VM > Pause** to unpause the virtual machine.

Encrypting a Virtual Machine

You can secure a virtual machine from unauthorized use by encrypting it and assigning a password to it. After the virtual machine is encrypted, you must enter the password to open the encrypted virtual machine, or to remove encryption from it.



CAUTION Be sure to record the password you assign to an encrypted virtual machine. To ensure the security of encrypted virtual machines, Workstation does not provide a way to retrieve a password.

In the virtual machine summary tab and in Favorites, encrypted virtual machines are displayed with a lock icon until you enter the password to open the virtual machine.

Encryption applies to all snapshots in a virtual machine. If you restore a snapshot in an encrypted virtual machine, the virtual machine remains encrypted, whether or not it was encrypted when the snapshot was taken. If you change the password for an encrypted virtual machine, the new password applies to any snapshot you restore, regardless of the password in effect when the snapshot was taken.

Restrictions on Encryption

The encryption feature has the following restrictions:

- A virtual machine must be powered off before you can add or remove encryption, or change the encryption password.
- The encryption feature works only with virtual machines of virtual hardware version 5.x or later.
- You can create a linked clone from an encrypted virtual machine, but you cannot encrypt or remove encryption from a virtual machine that is the parent of a linked clone.

There is one exception to this restriction. If you use the Conversion wizard (**File > Import or Export**) to create a linked clone, you can create a linked clone without disabling the encryption feature for the parent virtual machine. If you create a linked clone this way and then encrypt the parent virtual machine, the linked clone cannot read data from the virtual disk of the encrypted parent virtual machine. To fix this problem, unencrypt the parent virtual machine.

If you plan to use the encryption feature, VMware recommends that you avoid this potential problem by using **VM > Clone** to create a linked clone. Workstation disables the encryption feature for the parent of a linked clone that is created with the **VM > Clone** option.

- You cannot encrypt virtual machines that are members of a team, and you cannot add an encrypted virtual machine to a team.
- If more than one unencrypted virtual machines share the same virtual disk, and you encrypt one of the virtual machines, the virtual disk becomes unusable for the unencrypted virtual machines.
- You cannot encrypt a virtual machines that has a recording.
- You cannot encrypt ACE virtual machines. If you have an encrypted virtual machine you cannot enable ACE features.

Encrypt a Virtual Machine

If you forget your password, Workstation does not provide a way to retrieve it. Before you begin, power off the virtual machine. Make sure you read the feature limitations. For more information, see [“Restrictions on Encryption”](#) on page 156.

To encrypt a virtual machine

- 1 Select **VM > Settings**.
- 2 Click the **Options** tab, and select **Encryption**.
- 3 Select **Encrypt**.
- 4 Enter the password, and enter the password again to confirm it.
Be sure to record the password.
- 5 Select **Encrypt**.

Remove Encryption from a Virtual Machine

Removing encryption from a virtual machine authorizes users who log in to the host with your credentials to start the virtual machine. Before you begin, power off the virtual machine. Make sure that you remove any sensitive information from the virtual machine.

To remove encryption from a virtual machine

- 1 Select **VM > Settings**.
- 2 Click the **Options** tab, and select **Encryption**.
- 3 Select **Remove Encryption**.
- 4 Enter your password.
- 5 Select **Remove Encryption**.

Change the Password for an Encrypted Virtual Machine

If you forget your new password, Workstation does not provide a way to retrieve it. Before you begin, power off the virtual machine.

To change the password for an encrypted virtual machine

- 1 Select **VM > Settings**.
- 2 Click the **Options** tab, and select **Encryption**.
- 3 Select **Change Password**.
- 4 Enter your current password and the new password, and enter the new password again to confirm it.
Be sure to record the new password.

Delete a Virtual Machine

You can use a Workstation command to delete a virtual machine and all of its files from the host file system.

If, instead of deleting the virtual machine altogether, you want to remove it from the **Favorites** list or from a team, see [“Remove an Item from the Favorites List”](#) on page 64 or [“Remove a Virtual Machine from a Team”](#) on page 277.



CAUTION Do not delete a virtual machine if it was used to make a linked clone virtual machine and you still want to use the linked clone. If the linked clone cannot find the virtual disk files from the parent virtual machine, the linked clone stops working.

To delete a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Delete from Disk**.

Controlling the Virtual Machine Display

You can control the way Workstation displays virtual machines and their applications. For example, you can use full screen mode to hide the host user interface altogether, or you can use Unity mode so that applications from the virtual machine appear on the host desktop and hide the rest of the virtual machine user interface.

Using Unity Mode

In virtual machines with Linux or Windows 2000 or later guest operating systems, you can switch to Unity mode to display applications directly on the host desktop. The taskbar displays items for open applications in Unity mode just as it does for open host applications.

The virtual machine console view is hidden, and you can minimize the Workstation window.

You can use keyboard shortcuts to copy, cut, and paste images, plain text, formatted text, and email attachments between applications on your host machine and virtual machine applications displayed in Unity mode. You can also drag and drop and copy and paste files between host and guest. See [“Using the Copy and Paste Feature”](#) on page 189 and [“Using the Drag-and-Drop Feature”](#) on page 187.

NOTE If you save a file or attempt to open a file from an application in Unity mode, the file system you see is the file system inside the virtual machine. You cannot open a file from the host operating system or save a file to the host operating system.

When a virtual machine is in Unity mode, you can access the virtual machine’s **Start** menu (for Windows virtual machines) or **Applications** menu (for Linux virtual machines) by pointing to one of the following locations:

- On Windows hosts, point to the **Start** menu.
- On Linux hosts, point to the upper-left corner of the primary monitor.

For some guest and host operating systems, if you have multiple monitors, application windows in Unity mode can appear only on the monitor that is set as the primary display. If the host and guest are Windows XP or later, the application windows can appear on additional monitors

On Windows, Unity mode is not available in the full screen mode. When you cycle through virtual machines, all the virtual machines that are in Unity mode do not appear.

NOTE On Linux guests, Unity mode is supported experimentally.

Set Preferences for Unity Mode

You can configure Unity mode so that you can access a virtual machine’s **Start** or **Applications** menu from the host’s desktop. You can also specify the border color around applications that run in Unity mode on the desktop.

Accessing a virtual machine’s **Start** or **Applications** menu from the host’s desktop enables you to start applications in the virtual machine that are not open in Unity mode. If you do not enable this feature, you must exit Unity mode to display the virtual machine’s **Start** or **Applications** menu in the console view.

To help distinguish between the application windows that belong to various virtual machines, you can give them different colors. For example, you can set the applications for one virtual machine to have a blue border and set the applications for another virtual machine to have a yellow border.

You can also set a Workstation preference to minimize the Workstation window when you enter Unity mode.

To set preferences for Unity mode

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab and select **Unity**.
- 4 Complete the settings panel and click **OK**.

Use the following information to determine which features to enable:

- To identify the application as belonging to this virtual machine rather than the host, use the **Show borders** check box to set a window border. Use the **Show badges** check box to display a logo in the title bar.
- To use a custom color, click the colored rectangle to access the color chooser on Linux hosts. On Windows hosts, click **Choose color**.
- If you select the **Enable applications menu** check box, one of the following menus appears when you point to correct location on the host's desktop:
 - A **Start** menu appears on Windows guests.
 - An **Applications** menu appears on Linux guests.

On Windows hosts, point to the **Start** menu. On Linux hosts, point to the upper-left corner of the primary monitor. The menu has the same color border as the virtual machine application windows.

- 5 Repeat this process for each virtual machine that you plan to use in Unity mode.
- 6 (Optional) To automatically minimize the Workstation window when you enter Unity mode, do the following:
 - a Choose **Edit > Preferences**.
 - b Click the **Display** tab.
 - c Select **Minimize Workstation when entering Unity** and click **OK**.

This Workstation preference is used for all virtual machines.

Enter and Exit Unity Mode

In Unity mode, a virtual machine's applications look like other application windows on the host, except that they have a colored window border and a VMware logo in the window's title bar.

Before you begin, make sure the virtual machine meets these requirements:

- The virtual machine must be a Workstation 6.x or higher virtual machine.
- VMware Tools must be installed and running in the virtual machine's guest operating system. The version of VMware Tools must be the version included in Workstation 7.0. For instructions, see [“Installing VMware Tools”](#) on page 104.
- The guest operating system in the virtual machine must be Linux or Windows 2000 or later.
- For Linux guests and hosts, VMware recommends that you use a modern version of Metacity or KDE. Performance on Linux depends on a combination of variables such as the system, the applications that are running, and the amount of RAM.

To enter and exit Unity mode

- 1 In the virtual machine, open the applications to use in Unity mode.
- 2 From the Workstation menu bar, choose **View > Unity**.

A check mark appears next to **Unity** in the menu.

The virtual machine's console view in the Workstation window is hidden, and the guest's open applications appear in application windows on the host's desktop.

- 3 To exit Unity mode, display the Workstation window and choose **View > Unity** to remove the check mark next to **Unity**, or click **Exit Unity** in the virtual machine's console view.

Access a Virtual Machine's Start or Applications Menu in Unity Mode

If configured to do so, a virtual machine in Unity mode can display a **Start** or **Applications** menu above the host's **Start** or **Applications** menu. This feature enables easy access to applications in the virtual machine that are not open in Unity mode.

Before you begin, verify that the virtual machine is configured to use this feature. See [“Set Preferences for Unity Mode”](#) on page 159.

To access a virtual machine's Start or Applications menu in Unity mode


- 1 To enter Unity mode, power on a virtual machine, open one or more applications, and choose **View > Unity** from the Workstation menu bar.
- 2 To display the virtual machine's **Start** or **Applications** menu on the host, do one of the following:
 - Point to the **Start** menu on Windows hosts or to the upper-left corner of the primary monitor on Linux hosts.
 - Press Ctrl+Shift+U.

If you have multiple virtual machines in Unity mode, you can navigate between multiple **Start** and **Applications** menus by using standard navigation keys such as arrow keys, Tab, and Shift+Tab. You can select one by using standard keys such as Enter and the space bar.

Use Full Screen Mode

In full screen mode, the virtual machine display fills the screen, so that you cannot see the borders of the Workstation window.

Figure 7-1. Full Screen Toolbar on a Windows Host



Before you begin, make sure the guest operating system has VMware Tools installed. See [“Installing VMware Tools”](#) on page 104.

NOTE If you plan to run the virtual machine in full screen mode on a laptop computer, also set the guest to report battery information. See [“Report Battery Information in the Guest”](#) on page 180.

To use full screen mode

- 1 Select the virtual machine and make sure it is powered on.
- 2 If you have multiple monitors, move the Workstation window into the monitor to use for full screen mode.

3 Choose **View > Full Screen**.

If you cannot enter full screen mode when the guest's display mode is smaller than the host's display mode, try adding the following line to the virtual machine's configuration (.vmx) file:

```
mks.maxRefreshRate=1000
```

For more information about the configuration file, see [“Files That Make Up a Virtual Machine”](#) on page 97.

4 (Optional) You can perform the following optional tasks:

- To switch from full screen mode back to windowed mode, which shows the virtual machine inside a Workstation window again, press Ctrl+Alt+Enter.
- To hide the full screen toolbar and menus while you are using full screen mode, click the push pin icon and move the mouse pointer off of the toolbar.

This action unpins the toolbar. The toolbar slides up to the top of the monitor and disappears. To display the toolbar again, point to the top of the screen until the toolbar appears.

If you cannot display the full screen toolbar, see [“Set Preferences for Autofit, Full Screen Mode, and Unity Mode”](#) on page 164.

- To switch from one powered-on virtual machine to another while in full screen mode, do one of the following:
 - To go to a specific powered-on virtual machine, click the virtual machine arrow, as shown in [Figure 7-1](#), and select the virtual machine.
 - To go to the next virtual machine, press Ctrl+Alt+right arrow, or press Ctrl+Alt+left arrow to go to the previous virtual machine.
- Use the **VM** menu on the toolbar to access the Workstation **VM** menu commands.
- Use the **System** menu to switch to exclusive mode or to use the autofit command to adjust screen resolution on Windows hosts. Use the **View** menu to switch to Unity mode or exclusive mode, or to use the autofit command to adjust screen resolution on Linux hosts.
- To display the virtual machine across two or more monitors in full screen mode, see [“Use Multiple Monitors for One Virtual Machine”](#) on page 166.

Set Preferences for Autofit, Full Screen Mode, and Unity Mode

You can set preferences for how the display settings of all virtual machines adjust to fit the Workstation window. These adjustments occur when you resize the Workstation window or when you change the display settings inside the guest.

You can also configure how the host and guest display settings interact when you enter full screen mode and Unity mode.

Before you begin, make sure that VMware Tools is installed in the guest operating systems in the virtual machines.

To set preferences for autofit, full screen mode, and Unity mode

- 1 Choose **Edit > Preferences**.
- 2 Click the **Display** tab.
- 3 Select one or more check boxes in the **Autofit** section.
- 4 Use the following information to help you complete the **Full Screen** section:
 - Select **Autofit guest** to change the guest's resolution settings to match the display settings of the host while you are in full screen mode.
 - Select **Stretch guest** to retain the guest's resolution settings but still have the display fill the full screen.

This setting is useful if you need to retain a guest's low-resolution settings. For example, use this setting to play older computer games that run only at low resolutions.
 - Select **Center guest** to have both host and guest retain their own display settings while you are in full screen mode.
 - If you deselect **Show toolbar edge when unpinned**, the edge of the full screen toolbar does not appear. When you place your pointer cursor near the top of the screen the full screen toolbar appears for a few seconds. To display the edge of the full screen toolbar, use the preferences editor and select **Show toolbar edge when unpinned** again.
- 5 If you plan to have multiple virtual machines running, with some in Unity mode and some accessible only in the Workstation window, do not select the **Minimize Workstation when entering Unity** check box.
- 6 Click **OK**.

Use Quick Switch Mode

In quick switch mode, the virtual machine's screen is resized to fill the screen completely, except for the space that the tabs occupy.

Before you begin, make sure the guest operating system has VMware Tools installed. See [“Installing VMware Tools”](#) on page 104.

Quick switch mode is similar to full screen mode with the addition of tabs at the top of the screen for switching from one virtual machine to another. The other difference is that you can use quick switch mode with virtual machines that are powered on or off.

To use quick switch mode

- 1 Select the virtual machine.
- 2 Choose **View > Quick Switch**.
- 3 (Optional) To view the Workstation menu and toolbar while using quick switch mode, point to the top of the screen.
- 4 (Optional) To resize a guest operating system's display so that it fills as much of the screen as possible in quick switch mode, choose **View > Fit Guest Now**.
- 5 To exit quick switch mode, point to the top of the screen and choose **View > Quick Switch**.

Use Exclusive Mode


You might want to use exclusive mode to run graphics-intensive applications, such as games, in full screen mode.

Before you begin, make sure the guest operating system has VMware Tools installed. See [“Installing VMware Tools”](#) on page 104.

Like full screen mode, exclusive mode causes the Workstation virtual machine display to fill the screen. Drawbacks to using exclusive mode include the following:

- The full screen toolbar is not available in exclusive mode. To configure any virtual machine settings, you need to exit exclusive mode (press Ctrl+Alt).
- On Windows, exclusive mode does not use multiple monitors.
- Exclusive mode causes the host resolution to resize, which can cause items on the host desktop to be moved.

To use exclusive mode

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered on.
- 3 If you have multiple monitors, move the Workstation window onto the monitor you want to use.
- 4 Press Ctrl+Alt+Enter.
- 5 On the full screen toolbar, do one of the following:
 - On Windows hosts, click the **Workstation** icon to display the system menu and choose **Exclusive Mode**.

 - On Linux hosts, click the **View** menu on the full screen toolbar and choose **Exclusive Mode**.
- 6 To exit exclusive mode and return to windowed mode, do the following:
 - a Press Ctrl+Alt to exit exclusive mode and return to full screen mode.
 - b Press Ctrl+Alt+Enter to exit full screen mode and return to the windowed mode.

Use Multiple Monitors for One Virtual Machine

If your host has a multiple-monitor display, you can configure a virtual machine to use two or more monitors.

On Windows guests, you do not need to use the Windows display properties settings to configure multiple monitors.

Before you begin, make sure the virtual machine meets these requirements:

- The virtual machine is a Workstation 6.x or higher virtual machine.
- VMware Tools is installed and running in the virtual machine's guest operating system. The version of VMware Tools must be the version included in Workstation 7.0. For instructions, see ["Installing VMware Tools"](#) on page 104.
- The guest operating system in the virtual machine is Windows XP, Windows Vista, Windows 7, or Linux.

- On the host, the display settings for monitors must be set in a compatible topology. For example, the left-most monitor cannot be placed lower than any other monitor in the display topology. It does not matter if the monitors have different resolutions or orientations. When entering full screen mode, the monitor that contains the Workstation window cannot be lower than another monitor.

Put another way: When you use the Windows display properties controls, if you select a monitor icon and begin to drag it to a new location, a tooltip displays the coordinates. If a coordinate shown for the new location of the icon is a negative number, that location will not work.

To use multiple monitors for one virtual machine

- 1 Choose **Edit > Preferences**.
- 2 Click the **Display** tab and in the **Full Screen** section, select **Autofit guest** and click **OK**.
- 3 Select a virtual machine.
- 4 Make sure the virtual machine is powered off.
- 5 Choose **VM > Settings**.
- 6 On the **Hardware** tab, select **Display**.

If **Display** does not appear in the list on the **Hardware** tab, it probably means that the virtual machine is a Workstation 4 or 5.x virtual machine. Only Workstation 6.x or higher virtual machines have this feature.

- 7 On the settings panel for the **Display** tab, specify how to determine the number of monitors.

In most cases, select **Use host setting for monitors**. If the virtual machine is run on a host that is using one monitor, the virtual machine detects only one monitor. But if the same virtual machine is moved to a host that is using two monitors, the virtual machine detects two monitors.

The number of monitors depends on the number of monitors that the host recognizes at startup. For example, if you power on a laptop that is undocked, the host setting is one monitor, even if you later place the running laptop in a docking station that uses two monitors.

Similarly, if the host has one monitor and you suspend the virtual machine and change the host to have two monitors, when you resume the virtual machine, it is still configured to use one monitor. You must restart the virtual machine to detect the new settings.

You might want to set a specific number of monitors if, for example, you are writing an application to be displayed on multiple monitors but the host you are using has only one monitor.

- 8 If you set a specific number of monitors, specify a sufficient maximum resolution.

The resolution of a host monitor that you use to display the virtual machine must not exceed the **Maximum resolution** setting that you specify.

- 9 Power on the virtual machine and choose **View > Full Screen**.

For more information, see [“Use Full Screen Mode”](#) on page 162.

Make sure the virtual machine is completely powered on. If when you power on the virtual machine, it is set to be restored from a snapshot and if background snapshots are enabled, powering on might take longer. In this case, displaying the virtual machine to two monitors might not work correctly at first. If you see this issue, go to **Edit > Preferences > Priority** and deselect the check box called **Take and restore snapshots in the background**.

- 10 On the full screen toolbar, click the **Cycle Multiple Monitors** button.

This button is available only if the host has multiple monitors. This button is shown in [Figure 7-1, “Full Screen Toolbar on a Windows Host,”](#) on page 162.

Clicking the **Cycle Multiple Monitors** button causes the guest operating system's desktop to extend to the additional monitor or monitors.

If the virtual machine does not appear correctly, use the system menu (on Windows hosts) or the **View** menu (on Linux hosts) and select **Autofit Guest**.

- 11 If you have more than two monitors, and you want the virtual machine to use them, click the **Cycle Multiple Monitors** button again.

The order in which the monitors are used depends on the order in which the monitors were added to the host operating system.

- 12 To return to using only one monitor, click the **Cycle Multiple Monitors** button until the display returns to one monitor.

Use Multiple Monitors for Multiple Virtual Machines

If your host has a multiple-monitor display, you can run a different virtual machine on each monitor.

Before you begin, make sure the guest operating system has VMware Tools installed. See [“Installing VMware Tools”](#) on page 104.

To use multiple monitors for multiple virtual machines

- 1 To open multiple Workstation windows, choose **File > New > Window**.

On Linux hosts, although you can have multiple Workstation windows, the windows operate in a single Workstation process, which saves memory and allows preferences and **Favorites** list items to be shared.

- 2 (Optional) On Linux hosts, to run separate Workstation processes in different X servers, start the second instance of Workstation with the `-W` flag.

In a terminal window, enter the following command:

```
vmware -W &
```

- 3 Start one or more virtual machines in each Workstation window.

If you have a virtual machine running in one window and you want to run that virtual machine in another Workstation window, close the virtual machine in the first window before you attempt to open it in another.

- 4 Drag each Workstation window to the monitor on which you want to use it.
- 5 To switch mouse and keyboard input from the virtual machine on the first monitor to the virtual machine on the second monitor, move the mouse pointer from one screen to the other and click inside the second monitor.

Fitting the Workstation Console to the Virtual Machine Display

The **Autofit** and **Fit** commands in the **View** menu allow you to match the Workstation console with the guest operating system display size.

With both **Autofit** commands toggled off, Workstation does not automatically match window sizes as you work. Scroll bars appear in the console when the Workstation console is smaller than the guest operating system display. A black border appears in the console when the console is larger than the guest operating system display.

The **Autofit** and **Fit** commands are described in [Table 7-1](#).

Table 7-1. Autofit and Fit Commands

View Menu Command	Description
Autofit Window	Causes the Workstation console to maintain the size of the virtual machine's display resolution. If the guest operating system changes its resolution, the Workstation console resizes to match the new resolution.
Autofit Guest	Causes the virtual machine to resize the guest display resolution to match the size of the Workstation console.
Fit Window Now	Causes the Workstation console to match the current display size of the guest operating system.
Fit Guest Now	Causes the guest operating system display size to match the current Workstation console.

An **Autofit** command is toggled on or off each time you select it. If **Autofit Window** and **Autofit Guest** are toggled on, you can manually resize the Workstation console, but the guest operating system can also resize the Workstation console.

The **Fit Window Now** or **Fit Guest Now** command is redundant if the corresponding Autofit command is active because the console and the guest operating system display are the same size.

Display Resizing in Linux Guests

For Linux guests, the following considerations apply to display resizing:

- If you have virtual machines that were suspended under a version of VMware Tools earlier than version 5.5, display resizing does not work until the virtual machines are completely powered off and powered on again. (Rebooting the guest operating system is not sufficient.)
- Update VMware Tools to the latest version in the guest for the display resizing options to work.
- Before you can use the **Autofit Guest** and **Fit Guest Now** options, VMware Tools must be running.

- All the restrictions for resizing that the X11 Windows system imposes on physical hosts apply to guests:
 - You cannot resize to a mode that is not defined. The VMware Tools configuration script can add a large number of mode lines, but you cannot resize in 1-pixel increments as you can in Windows. VMware Tools adds modelines in 100-pixel increments. This means you cannot resize a guest larger than the largest mode defined in your X11 configuration file. If you attempt to resize larger than that mode, a black border appears and the guest stops increasing.
 - The X server always starts up in the largest resolution that is defined. You cannot avoid this restriction. The XDM/KDM/GDM login screen always appears at the largest size. But Gnome and KDE allow you to specify your preferred resolution, so that you can reduce the guest display size after you log in.

Display Resizing in Solaris Guests

For Solaris 10 guests, the following considerations apply to display resizing:

- Update VMware Tools to version 7.0 in the guest for the display resizing options to work.
- Before you can use the **Autofit Guest** and **Fit Guest Now** options, VMware Tools must be running.
- Solaris 10 guests must be running an Xorg X server and JDS/Gnome.

Working with Nonstandard Resolutions

A guest operating system and its applications might react unexpectedly when the Workstation console size is not a standard VESA resolution (640×480, 800×600, 1024×768, and so on).

For example, the **Autofit Guest** and **Fit Guest Now** commands allow your guest operating system screen resolution to be set smaller than 640×480, but some installers do not run at resolutions smaller than 640×480. Programs might refuse to run. Error messages might include such phrases as *VGA Required to Install* or *You must have VGA to install*.

Use one of the following strategies to work around this problem with nonstandard resolutions:

- If your host computer's screen resolution is high enough, you can enlarge the window and choose **Fit Guest Now**.
- If your host computer's screen resolution does not allow you to enlarge the Workstation console sufficiently, you can manually set the guest operating system's screen resolution to 640×480 or larger.

Configuring Video and Sound

For best color and graphics display, you must coordinate host and guest color settings. Workstation also supports games and applications that use DirectX 9 accelerated graphics, but you must perform some 3-D preparation tasks on the host and guest.

With regards to sound support, Workstation usually installs the necessary drivers, but on some of the oldest and newest guest operating systems, you must manually install a driver.

Setting Screen Color Depth

The number of screen colors available in the guest operating system depends on the screen color setting of the host operating system.

Virtual machines support:

- 16-color (VGA) mode
- 8-bit pseudocolor
- 16 bits per pixel (16 significant bits per pixel)
- 32 bits per pixel (24 significant bits per pixel)

If the host is in 15-bit color mode, the guest operating system's color setting controls offer 15-bit mode in place of 16-bit mode.

If the host is in 24-bit color mode, the guest operating system's color setting controls offer 24-bit mode in place of 32-bit mode.

If you run a guest operating system set for a greater number of colors than your host operating system is using, you can encounter problems. In some cases, for example, the colors in the guest are not correct. In others, the guest operating system cannot use a graphical interface.

You can try either of the following solutions:

- Increase the number of colors available on the host.
- Decrease the number of colors used in the guest.

For best performance, use the same number of colors in the guest and on the host.

Changing Screen Color Depth on the Host

If you choose to change the color settings on the host operating system, shut down all guest operating systems, power off the virtual machines, and close Workstation.

Follow standard procedures for changing the color settings on your host operating system and restart Workstation and the virtual machines.

Changing Screen Color Depth in the Guest

The approach you take to change the color settings in the guest operating system depends on the guest operating system.

Follow the process for changing screen colors in the guest operating system:

- In a Windows guest, the Display Properties control panel offers only those settings that are supported.
- In a Linux or FreeBSD guest, you must change the color depth before you start the X server, or you must restart the X server after making the changes.

Support for Direct3D Graphics

To take advantage of the 3-D capabilities of Workstation, the virtual machine must be running the version of VMware Tools included with Workstation 7.0. If you move the virtual machine and want to use the 3-D capabilities, be sure you have the correct version of VMware Tools installed.

Accelerated 3-D Restrictions

Support for applications that use DirectX 9 accelerated graphics applies only to Windows XP guests, on hosts running Windows XP, Windows Vista, Windows 7, or Linux.

This feature currently has the following restrictions:

- Workstation now offers support for DirectX games and applications with DirectX versions 9 and lower.
- Support for 3-D applications is not optimized for performance.

- OpenGL applications run in software emulation mode.
- You cannot use the record/replay feature to record a 3-D application.

Prepare a Host for Accelerated 3-D

By default, Direct3D technology is enabled for Workstation 6.x and later virtual machines. You must prepare the host first, the virtual machine second, and the guest operating system last.

Before you begin, make sure the host operating system is Windows XP, Windows Vista, Windows 7, or Linux. For Windows hosts, make sure you have a video card that supports DirectX 9 and the latest DirectX Runtime. For Linux hosts, make sure the host has a video card that can run accelerated OpenGL 2.0. If you are unsure, check with your hardware manufacturer.

To prepare a host for accelerated 3-D

- 1 Upgrade the host's video drivers to the latest version available:
 - a ATI Graphics drivers are available from the AMD Web site.
 - b NVIDIA drivers are available from the NVIDIA Web site.
- 2 If you are using a Windows host, turn up hardware acceleration in the display properties:
 - On Windows XP, right-click the desktop and choose **Properties > Settings > Advanced > Troubleshoot**.
 - On Windows Vista, right-click the desktop and choose **Personalize > Display Settings > Advanced Settings > Troubleshoot > Change settings**.
 - On Windows 7, right-click the desktop and choose **Personalize > Screen resolution > Advanced Settings > Troubleshoot > Change settings**.

Move the **Hardware Acceleration** slider all the way to the **Full** position.

- 3 If you are using Linux, test your Linux host for compatibility:
 - a To verify that direct rendering is enabled, run:


```
glxinfo | grep direct
```
 - b To ensure that 3-D applications work on your host, run:


```
glxgears
```

After your host is configured, configure a virtual machine for accelerated 3-D.

Prepare a Virtual Machine for Accelerated 3-D

Before you begin, make sure the guest operating system is Windows XP, Windows Vista, or Windows 7.

To prepare a virtual machine for accelerated 3-D

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off rather than suspended.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, select **Display**.
- 5 In the **Monitors** section, if the virtual machine is set to use more than one monitor, set it to use only one monitor.
- 6 In the **3D Graphics** section, make sure the check box is selected and click **OK**.

Prepare the Guest Operating System for Accelerated 3-D

Before you begin, make sure the guest operating system is Windows XP, Windows Vista, or Windows 7 and make sure the latest version of VMware Tools is installed. See [“Installing VMware Tools”](#) on page 104.

To prepare the guest operating system for accelerated 3-D

- 1 Power on the virtual machine.
- 2 Install DirectX 9.0c End User Runtime.
This download is available from Microsoft Download Center.
- 3 Install and run your 3-D applications.

Configuring Sound

Workstation provides a sound device compatible with the Sound Blaster AudioPCI and supports sound in Windows 95, Windows 98, Windows Me, Windows NT, Windows XP, Windows Vista, Windows 7, Windows Server 2003, and Linux guest operating systems. The Workstation sound device is enabled by default.

Sound support includes pulse code modulation (PCM) output and input. For example, you can play .wav files, MP3 audio, and Real Media audio. MIDI output from Windows guests is supported by the Windows software synthesizer. MIDI input is not supported, and no MIDI support is available for Linux guests.

Workstation 7.0 for Linux supports Advanced Linux Sound Architecture (ALSA).

Windows XP, Windows Vista, Windows 7 and most recent Linux distributions detect the sound device and install appropriate drivers for it.

For Windows Vista or Windows 7, when you install VMware Tools in a 64-bit Windows Vista or Windows 7 guest operating system, a sound driver is installed. For 32-bit Windows Vista and Windows 7 guests and Windows 2003 Server guests, use Windows Update to install a 32-bit driver.

Installing Sound Drivers in Windows 9x and NT Guests

Windows 95, Windows 98, Windows 98SE, and Windows NT 4.0 do not have drivers for the Sound Blaster AudioPCI adapter. To use sound in these guest operating systems, download the driver from the Creative Labs Web site and install it in the guest operating systems.

Creative Labs has Web sites that serve different regions of the world. The adapter name varies, depending on the region, but usually includes PCI 128.

Using Advanced Linux Sound Architecture (ALSA)

Workstation 7.0 supports Advanced Linux Sound Architecture (ALSA). Earlier versions of Workstation used the Open Sound System (OSS) interface for sound playback and recording in virtual machines running on Linux hosts. Unlike OSS, ALSA does not require exclusive access to the sound device. The host machine and multiple virtual machines can play sound at the same time.

Before you can use ALSA in a VMware virtual machine, your system must meet the following requirements.

- The ALSA library version on the host system must be version 1.0.16 or later.
- The sound card on your host machine must support ALSA. The alsa-project.org Web site maintains a current listing of sound cards and chipsets that support ALSA.
- The current user must have the appropriate permissions to access the sound device.
- The sound device on the host must not be muted. You can use the `alsamixer` graphical mixer program to ensure that the sound device is not muted. Enter `alsamixer` from a command prompt. Documentation for the `alsamixer` program is available on the Internet.

Obtaining Sound Card Information

You can obtain information about the sound cards on your Linux host system from the command line.

To obtain sound card information by using the command line

At a command prompt, enter one of the following commands.

Command	Description
<code>lspci grep -i audio</code>	To list the name and type of the sound chipset on your host machine
<code>cat /proc/asound/cards</code>	To list the sound cards on your host machine
<code>alsamixer</code>	To determine whether the current user has the appropriate permissions to access the sound device

If the current user does not have permissions, an error similar to the following message appears:

```
alsamixer: function snd_ctl_open failed for default: No such device.
```

Give the user read, write, and execute permissions to the directory containing the ALSA sound device. Typically, the ALSA sound device is found in `/dev/snd/`, but this location may vary, depending on your distribution of Linux.

Using ALSA in a Virtual Machine

You can configure your virtual machine to use ALSA in the Virtual Machine Settings dialog box.

To use ALSA in a virtual machine

- 1 Select **VM > Settings**.
- 2 On the **Hardware** tab, select **Sound Card**.
- 3 Make sure that the **Connected** and **Connect at power on** check boxes are checked.
- 4 Select one of the **Connection** check boxes.

Command	Description
Use default host sound card	To have Workstation detect the host sound card
Specify host sound card	To choose a sound card. Make a selection from the drop-down menu. The drop-down menu displays PCM devices for every sound card on the host system.

- 5 Click **Save**.

Using an ALSA Sound Device that Does Not Appear in Virtual Machine Settings

Follow this procedure to use an ALSA sound device that does not appear in Virtual Machine Settings.

To use an ALSA sound device that does not appear in Virtual Machine Settings

- 1 Determine the name of the ALSA sound device.
Using the `alsa-utils` package, at a command prompt, enter `aplay -L` to list ALSA sound devices on your system.
- 2 Select **VM > Settings**.
- 3 On the **Hardware** tab, select **Sound Card**.
- 4 Make sure the **Connected** and **Connect at power on** check boxes are checked.
- 5 Select **Specify host sound card** and enter the name of the ALSA sound device to use, for example **front:CARD=Intel,DEV=0**
- 6 Click **Save**.

Overriding the ALS Library Version Requirement

If your host system does not meet ALSA requirements or for some other reason cannot use ALSA, Workstation uses the OSS API for sound playback and recording.

Depending on the sound card in the host computer, the sound quality might not be as good with an older version of the ALSA library. VMware recommends that you upgrade the host system to use newer sound drivers and libraries.

If the host system has an older version of the ALSA library, you can override the requirement for version 1.0.16.

To override the ALSA library version requirement

- 1 Open the `.vmx` virtual machine configuration file with a text editor.
- 2 Add the option `sound.skipAlsaVersionCheck = "TRUE"`.

Install New Software in a Virtual Machine

Installing new software in a virtual machine is like installing it on a physical computer. Only a few additional steps are required.

To install new software in a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Removable Devices** and verify that the virtual machine has access to the CD-ROM drive, ISO image file, or floppy drive where the installation software is located.

For more information, see [“Add DVD or CD Drives to a Virtual Machine”](#) on page 250.

- 3 Choose **VM > Settings** and use the **Memory** settings panel on the **Hardware** tab to set the final memory size for the virtual machine.

Some applications use a product activation feature that creates a key based on the virtual hardware in the virtual machine where it is installed. Changes in the configuration of the virtual machine might require you to reactivate the software. To minimize the number of significant changes, set the memory size.

- 4 Install VMware Tools in the guest operating system.

See [“Installing VMware Tools”](#) on page 104. Installing VMware Tools before installing the new application also minimizes the likelihood of requiring you to reactivate the software.

- 5 Install the new application according to the manufacturer’s instructions.

Disable Acceleration If a Program Does Not Run

Occasionally, when you install or run software inside a virtual machine, Workstation appears to stop responding. In many cases, you can get past the problem by temporarily disabling acceleration in the virtual machine.

If this problem occurs, it usually occurs early in the program’s execution.

To disable acceleration

- 1 Select the virtual machine.
The virtual machine can be powered off or on.
- 2 Choose **VM > Settings**.

- 3 On the **Hardware** tab, select **Processors**.
- 4 In the **Execution Mode** section, select **Disable acceleration for binary translation** and click **OK**.

This setting slows down virtual machine performance. VMware recommends that you use the setting only for getting past the problem with running the program.

- 5 After you pass the point where the program encountered problems, repeat [Step 2](#) through [Step 4](#) and deselect **Disable acceleration for binary translation**.

Report Battery Information in the Guest

If you run a virtual machine on a laptop in full screen mode, configure the option to report battery information in the guest. This way, you can determine when the battery is running low.

To report battery information in the guest

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 Click the **Options** tab and select **Power**.
- 5 Select the **Report battery information to guest** check box and click **OK**.

Use Host Printers in a Virtual Machine

You can print from the virtual machine to any printer available to the host computer without installing additional drivers in the virtual machine. The Workstation virtual printer feature uses ThinPrint technology to replicate the host machine printer mapping in the virtual machine. When you enable the virtual printer, Workstation configures a virtual serial port to communicate with the host printers.

To use host printers in a virtual machine

- 1 Select the virtual machine.
- 2 Select **VM > Settings**.
- 3 On the **Hardware** tab, select **Add**.
- 4 In the Add Hardware Wizard dialog box, select **Virtual Printer** and **Finish**.

The default device setting is to connect the virtual printer when the virtual machine is powered on.

When the ACE Virtual Printer policy is enabled, **Virtual Printer** is available and cannot be removed until the ACE Virtual Printer policy is disabled.

Use Removable Devices in a Virtual Machine

You can configure a number of removable devices for use in a virtual machine, including floppy drives, DVD/CD-ROM drives, USB devices, smart card readers, and network adapters.

Some devices cannot be used by the host and guest or by multiple guests at the same time. For example, if the host is using a floppy drive, you must connect it to the virtual machine before you can use it in the virtual machine. To use it on the host again, you must disconnect it from the virtual machine. By default, floppy drive is not connected when the virtual machine powers on.

For information about how to add or configure specific devices, see [Chapter 16, “Connecting Devices,”](#) on page 331 and [Chapter 11, “Using Disks and Disk Drives,”](#) on page 235.

To use removable devices in a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered on.
- 3 Choose **VM > Removable Devices > <Device_Name>** and then **Connect**, **Disconnect**, or one of the other choices.

If you choose **Settings**, a dialog box appears. Make the needed changes and click **OK**. If you need assistance, click **Help** to display online help.

If the device is a USB device, you can change which icon is used to represent this device in the status bar. You can also choose not to display an icon for this device.

- 4 (Optional) To connect, disconnect, or change settings for a device, click or right-click the device icon in the notification area of the taskbar and choose a command from the context menu.

Using the device icon in the virtual machine taskbar is especially useful if you run the virtual machine in full screen mode.

Configure the Appliance View for a Virtual Machine

To have a virtual machine function as an appliance, such as a Web server with a browser-based interface, set the virtual machine to display its appliance view when starting up.

Before you begin, verify that the virtual machine is a Workstation 6.x or higher virtual machine. For instructions on upgrading, see [“Change the Version of a Virtual Machine”](#) on page 94.

The appliance view does the following:

- Displays a brief description of the type of server or appliance
- Provides a link that opens the browser on the host system and connects to the appliance's management console

NOTE The appliance view cannot be displayed for virtual machines that are part of a team, just as the summary view is not displayed for individual members of a team.

To configure the appliance view for a virtual machine

- 1 (Optional) To use a logo in the appliance view, create a PNG or BMP image file that is no larger than 256 × 256 pixels and place it in the directory that contains the .vmx file for the virtual machine.
- 2 Select the virtual machine.
The virtual machine can be powered on or off.
- 3 Choose **VM > Settings**.
- 4 Click the **Options** tab and select **Appliance View**.
- 5 Select the **Enable appliance view** check box.

- 6 Complete the fields on this settings panel to create the text and images that users see when the virtual machine starts up.

Use the following information to configure the settings on this panel:

- Only the **Name** field is required.
- Specify the TCP/IP port number for the appliance to use to serve HTTP content.
- If you do not select **Switch to appliance view at power on**, the console view appears instead of the appliance view. Often the console view shows only a simple display of the virtual machine's IP address and tells the user to open a browser.

- 7 Click **OK**.

When a user starts this virtual machine, the appliance view appears. A “powering on” message appears, followed by a link to access the appliance's management console.

Create a Screenshot of a Virtual Machine

You can capture a screenshot of a virtual machine and save it to the clipboard, to a file, or both. On Linux hosts, saving to the clipboard works only on systems running Gnome 2.12 or higher.

By default, the image is saved as a portable network graphics (.png) file. On Windows hosts, you can also save it as a bitmap (.bmp) file.

To create a screenshot of a virtual machine

- 1 Specify your preferences for taking screenshots:
 - a From the Workstation menu bar, choose **Edit > Preferences**.
 - b On the **Workspace** tab, use the **Save screenshots to** check boxes to specify whether to save the screenshot to the clipboard, a file, or both.
 - c If you select **File**, specify whether to save the file to your desktop or to be prompted for the location when you take the screenshot.

If you select **Save to desktop**, the filename is generated automatically from the virtual machine name and the time at which the screenshot is taken. The file format is .png file.

On Windows hosts, if you select **Ask for location**, when you are prompted for the filename and path, you can also change the file format to bitmap.

- d Click **OK**.

2 To take the screenshot, do one of the following:

- From the Workstation menu bar, choose **VM > Capture Screen**.
- Press Ctrl+Alt+PrtScr (on Windows hosts) or Shift+Ctrl+PrtScr (on Linux hosts).

The keyboard shortcut works regardless of whether mouse and keyboard input is currently grabbed by the virtual machine or the host.

The key combination Ctrl+Alt+PrtScr assumes that your virtual machine is configured to ungrab keyboard and mouse input if you press Ctrl+Alt. If you configured a different shortcut for ungrabbing input, use that shortcut with the PrtScr key. See [“Change the Hot-Key Combination”](#) on page 74.

Create and Play Back a Movie of a Virtual Machine

You can capture a movie of your screen activity within a virtual machine.

Before you begin, make sure you have the VMware movie decoder. Although you can capture a movie on Linux, you need to play it back on a Windows machine. The VMware CODEC (coder-decoder) is automatically installed with Workstation on Windows hosts. A separately downloadable installer is also available to play back movies on Windows machines without Workstation. Go to the Downloads page on the VMware Web site and click the **Tools & Drivers** tab on the VMware Workstation download page.

NOTE To actually record the execution of the virtual machine instead of creating a movie, see [Chapter 12, “Recording and Replaying Virtual Machine Activity,”](#) on page 257. You might want to record virtual machine execution for debugging purposes or to exactly reproduce the steps that cause a certain behavior.

To create and play back a movie of a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered on.
- 3 Choose **VM > Capture Movie**.

- 4 In the Save File dialog box, enter information for your movie and click **Save**.

Use the following guidelines:

- The **Quality** setting determines the compression and therefore the file size of the resulting movie.
- If you select **Omit frames in which nothing occurs**, the movie includes only those periods when something is actually happening in the virtual machine. This reduces the file size and length of the movie.

While movie capture is active, a red circle (a virtual LED) appears in the notification area of the taskbar.



- 5 In the virtual machine, perform the actions to appear in the movie.
- 6 To stop the movie, choose **VM > Stop Movie Capture**.

If you do not want to use the menu bar or if you are using the virtual machine in full screen mode, right-click the movie capture icon and choose **Stop Movie Capture**.

Workstation saves this image as an `.avi` file on the host.

- 7 Play the movie back in any compatible media player.

Advanced Options for Application Developers

Application developers can use the following APIs, SDKs, and IDEs when writing and debugging applications that run in virtual machines:

- **VIX API for writing programs to automate virtual machine operations** – The API is high-level, easy to use, and practical for both script writers and application programmers. API functions allow you to register, power on or off virtual machines, and run programs in the guest operating systems. Additional language bindings are available for Perl, COM, and shell scripts (`vmrun`). For more information, see the VMware VIX API Release Notes.
- **VAssert API for inserting replay-only code to debug applications** – The experimental VAssert feature enables you to use virtual assertions as you would regular assertions in the applications you develop. VAsserts appear only when you replay a recording of using the application and so are overhead free. This API is currently available only for Windows guests. See the *VAssert Programming Guide*.

- **VProbes tool for investigating guest behavior** – You can write VProbes scripts that inspect and record activities in the guest, VMM, VMX, and virtual device state, without modifying that state. For example, VProbes can track which applications are running or indicate which processes are causing page faults. See the *VProbes Programming Reference*.
- **VMCI Sockets interface** – This feature is a sockets interface for the Virtual Machine Communication Interface, which provides a faster means of communication among applications running on the host and in virtual machines. This feature is well-suited for developers who want to write client-server applications. See the *VMCI Sockets Programming Guide*.
- **Integrated Virtual Debuggers for Visual Studio and Eclipse** – The integrated development environment (IDE) plug-ins provide a configurable interface between virtual machines and Visual Studio or Eclipse that lets you test, run, and debug programs in virtual machines. See the *Integrated Virtual Debugger for Eclipse Developer's Guide* and *Integrated Virtual Debugger for Visual Studio Developer's Guide*.

Transferring Files and Text Between the Host and Guest

8

This chapter discusses how to transfer files between the host and guest. This chapter includes the following topics:

- [“Using the Drag-and-Drop Feature”](#) on page 187
- [“Using the Copy and Paste Feature”](#) on page 189
- [“Using Shared Folders”](#) on page 190
- [“Using a Mapped Drive”](#) on page 198

Using the Drag-and-Drop Feature

Using the drag-and-drop feature, you can move files and directories, email attachments, plain text, and formatted text between Linux and Windows hosts and Linux, Windows, and Solaris 10 guests. You can also move images between Windows hosts and guests. To use the drag-and-drop feature, VMware Tools must be installed on the virtual machine. This feature requires Linux hosts and guests to run X Windows and Solaris 10 guests to run an Xorg X server and JDS/Gnome.

You can drag files or directories between the following locations:

- A file manager, such as Windows Explorer, on the host to a file manager in the virtual machine and the reverse.
- A file manager to an application that supports drag-and-drop.
- Applications such as zip file managers that support drag-and-drop extraction of individual files.
- One virtual machine to another.

When you drag a file or folder from host to virtual machine or the reverse, Workstation copies the file or folder to the location where you drop it. For example, if you drop a file on the desktop icon of a word processor, the word processor opens with a copy of the original file. The original file does not reflect any changes you make to the copy.

Initially, the application opens using a copy of the file that is stored in your temp directory. On Windows, this is the directory specified in the %TEMP% environment variable, and on Linux and Solaris, it is the /tmp/VMwareDnD directory. To protect any changes you make, select **File > Save As** from the application menu and save the file in a different directory.

You can drag images between applications on Windows hosts and applications only on Windows guests, in either direction. You can also drag plain text, formatted text, and email attachments between applications on Windows and Linux hosts and guests in any combination, in either direction. Dragging email attachments is especially useful in Unity mode.

The drag-and-drop feature has the following restrictions:

- Dragging email attachments is restricted to images or files smaller than 4MB.
- Dragging plain text and formatted text (including the formatting) is restricted to amounts less than 4MB.
- Dragging text is restricted to text in languages that can be represented by Unicode characters.
- Workstation uses the PNG format to encode images that are dragged. Dragging images is restricted to images smaller than 4MB after conversion to PNG format.
- Dragging images is not supported for Linux hosts or guests.
- On Windows 95 and Windows 98 guests, the drag-and-drop feature is supported only for files and directories.

Enable or Disable the Drag-and-Drop Feature

To prevent dragging and dropping between virtual machines and the host, disable the drag-and-drop feature. Before you begin, make sure VMware Tools is installed on the virtual machine.

To enable or disable the drag-and-drop feature

- 1 Start Workstation and select the virtual machine.
- 2 Choose **VM > Settings**.

- 3 Click the **Options** tab and select **Guest Isolation**.
- 4 Select or deselect the **Enable drag and drop** check box and click **OK**.

Using the Copy and Paste Feature

To use the copy and paste feature, VMware Tools must be installed on the virtual machine. This feature requires Linux hosts and guests to run X Windows and Solaris 10 guests to run an Xorg X server and JDS/Gnome. The copy and paste feature works with Linux and Windows hosts and Linux, Windows, and Solaris 10 guests.

You can cut, copy, and paste text from one virtual machine to another, and you can cut, copy, and paste text between applications in two virtual machines. You can also cut, copy, and paste images, plain text, formatted text, and email attachments between applications on Windows and Linux hosts and guests in any combination, in either direction. Copying and pasting email attachments is especially useful in Unity mode. Use the normal hot keys or menu choices to cut or copy and paste.

The copy and paste feature has the following restrictions:

- Copying and pasting email attachments is restricted to images or files smaller than 4MB.
- Copying and pasting plain text and formatted text (including the formatting) is restricted to amounts less than 4MB.
- Copying and pasting text is restricted to text in languages that can be represented by Unicode characters.
- Workstation uses the PNG format to encode images that are copied and pasted. Copying and pasting images is restricted to images smaller than 4MB after conversion to PNG format.
- You cannot copy and paste files between virtual machines.
- On Windows 95 and Windows 98 guests, copying and pasting is restricted to plain text in amounts less than 64KB.

Enable or Disable the Copy and Paste Feature

To prevent copying and pasting between virtual machines and the host, disable the copy and paste feature. Before you begin, VMware Tools must be installed on the virtual machine.

To enable or disable the copy and paste feature

- 1 Select the virtual machine.
- 2 Select **VM > Settings**.
- 3 Click the **Options** tab and select **Guest Isolation**.
- 4 Select or deselect the **Enable copy and paste** check box and click **OK**.

Using Shared Folders

With shared folders you can share files among virtual machines and the host computer. You choose a directory on the host or on a network directory that is accessible to the host, and you give it the name you want to use on the guest.

You can use shared folders with virtual machines running the following guest operating systems and on all supported host systems:

- Windows Server 2003
- Windows XP
- Windows 2000
- Windows NT 4.0
- Windows Vista
- Windows 7
- Linux with a kernel version of 2.6 or higher
- Solaris x86 10
- Solaris x86 10 Update 1 and higher

Set Up Shared Folders

Shared folders provide an easy way to share files among virtual machines, and between virtual machines and the host. The directories you add as shared folders can be on the host computer or they can be network directories accessible from the host computer.

Before you begin, make sure the following prerequisites are satisfied:

- Make sure the virtual machines use a guest operating system that supports shared folders. For a list of supported guest operating systems, see [“Using Shared Folders”](#) on page 190.
- Verify that the current version of VMware Tools is installed in the guest. See [“Installing VMware Tools”](#) on page 104.
- Check permission settings. Access to files in the shared folder is governed by permission settings on the host computer. For example, if you are running Workstation as a user named User, the virtual machine can read and write files in the shared folder only if User has permission to read and write them. For information about how permission settings are mapped between Linux and Windows, see [“Improved Handling of Permissions”](#) on page 198.

To set up a folder for sharing between virtual machines, configure each virtual machine to use the same directory on the host system (or on the network).

To set up shared folders

- 1 Start Workstation and select a virtual machine.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab and select **Shared Folders**.
- 4 Select **Always enabled** or **Enabled until next power off or suspend**.

You can select **Enabled until next power off or suspend** only when the virtual machine is powered on. This setting enables folder sharing temporarily, until you shut down, suspend, or restart the virtual machine. You must select this option or **Always enabled** to enable or disable specific folders in the **Folders** section.

- 5 (Optional) For easy access, select the **Map as a network drive in Windows guests** check box to map a drive to the Shared Folders directory.

This directory contains all the shared folders you enable. The drive letter is selected automatically.

6 Click **Add**.

On Windows, clicking **Add** starts the Add Shared Folder wizard. On Linux, it opens the Shared Folder Properties dialog box.

7 Use the following information to complete the wizard or Properties dialog box:

- **Name** – Name that appears inside the virtual machine.

Characters that the guest operating system considers illegal in a share name appear differently when viewed inside the guest. For example, if you use an asterisk in a share name, you see %002A instead of * in the share name on the guest. Illegal characters are converted to their ASCII hexadecimal value.

- **Host folder** – Path on the host to the directory that you want to share.

If you specify a directory on a network share, such as D:\share, Workstation always attempts to use that path. If the directory is later connected to the host on a different drive letter, the shared folder cannot be located.

- **Enabled** or **Enable this share** – Deselect this option to disable a shared folder without deleting it from the virtual machine configuration. You can enable the folder by selecting the check box next to its name in the list.

To enable a folder at a later time select its name in the list, click **Properties**, and enable the folder in the Properties dialog box.

- **Read-only** – Select this option to prevent the virtual machine from changing the contents of the shared folder in the host file system. Access to files in the shared folder is also governed by permission settings on the host computer.

To change these properties, use the Properties dialog box. On Windows, after you select **Shared Folders** on the **Options** tab, click **Properties**.

8 (Optional) To enable shared folders for a virtual machine after a shared folder is created, on the **Shared Folders** settings panel, use the **Folder Sharing** section:

- Select **Enabled until next power off or suspend** to enable folder sharing temporarily, until you power off or suspend the virtual machine.

If you select **Enabled until next power off or suspend** and restart the guest or use the guest operating system to shut down, shared folders are not disabled when you restart the virtual machine.

- Select **Always enabled** to enable or disable specific folders in the **Folders** section.

- 9 Access the enabled shared folder:
 - For Windows guests, see [“View Shared Folders in a Windows Guest”](#) on page 195.
 - On Linux guests, shared folders appear under `/mnt/hgfs`.
 - On Solaris guests, shared folders appear under `/hgfs`.

Enabling and Disabling Shared Folders

You can enable shared folders for virtual machines created by other users, enable or disable all folder sharing for a specific virtual machine, and enable a specific shared folder for a virtual machine.



CAUTION Enabling all shared folders can pose a security risk because a shared folder might enable existing programs inside the virtual machine to access the host file system without your knowledge.

Enable Shared Folders for Virtual Machines Created By Other Users

A shared folder is disabled by default if it was not created by the user who powers on the virtual machine. This is a security precaution.

Folder sharing is also disabled by default for Workstation 4 and 5.x virtual machines regardless of who created the folder.

To enable shared folders for virtual machines created by other users

- 1 Choose **Edit > Preferences**.
- 2 On the **Workspace** tab, in the **Virtual Machines** section, select **Enable all shared folders by default**.

This setting applies to shared folders on all virtual machines that are created by other users, such as appliance developers.

You can now specify which virtual machines can share folders and which folders can be shared.

Enable or Disable Folder Sharing for Specific Virtual Machines

To reduce the security threat of enabling all shared folders, you must specify whether a specific virtual machine is allowed to share folders and then specify which folders to share.

To enable or disable folder sharing for specific virtual machines

- 1 Select a virtual machine.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab and select **Shared Folders**.
- 4 Use the buttons in the **Folder Sharing** section to enable or disable shared folders and click **OK**.

You can select **Enabled until next power off or suspend** only when the virtual machine is powered on. This setting enables folder sharing temporarily, until you shut down, suspend, or restart the virtual machine. You must select this option or **Always enabled** to enable or disable specific folders in the **Folders** section.

- 5 If the virtual machine has a Windows operating system, select whether to map a network drive.

On Windows, if you disable shared folders, after you power on a virtual machine and attempt to select a mapped drive to the shared folder, you receive a message that the connection cannot be made.

After you enable folder sharing for a virtual machine, specify which folders can be shared.

Specify Which Folders to Share

Before you begin, make sure the virtual machine is allowed to share folders. See [“Enable or Disable Folder Sharing for Specific Virtual Machines”](#) on page 193.

To specify which folders to share

- 1 Select the virtual machine.
- 2 Choose **VM > Settings > Options > Shared Folders**.
- 3 In the **Folders** list for the virtual machine, select the check box next to the name of the shared folder that you want to enable.
- 4 (Optional) To make the shared folder read-only, select the shared folder and click **Properties**, select the read-only check box and click **OK**.

Viewing a Shared Folder

Viewing shared folders in a guest varies based on whether the guest operating system is Windows, Solaris, or Linux. You can use shared folders to share any type of files.

To determine which folders on the host are being shared with a virtual machine, choose **VM > Settings > Options > Shared Folders** to see a list of the shared folders and the directory paths to them.



CAUTION Do not open a file in a shared folder from more than one application at a time. For example, do not open the same file using an application on the host operating system and another application in the guest operating system. If one of the applications writes to the file, data corruption can occur.

View Shared Folders in a Windows Guest

In a Windows guest operating system, you can view shared folders using desktop icons.

NOTE If your guest operating system has VMware Tools from Workstation 4.0, shared folders appear as folders on a designated drive letter.

To view shared folders in a Windows guest

- Look in **My Network Places > Entire Network** (**Network Neighborhood** for a Windows NT guest, or **Network** for Windows Vista and Windows 7) under **VMware Shared Folders**.

If you have trouble finding a shared folder using the desktop icon, open Windows Explorer and look in **My Network Places** (or **Network Neighborhood**).

- To view a specific shared folder, do one of the following:
 - Navigate to it on the guest system by opening **My Network Places > Entire Network > VMware Shared Folders > vmware-host > Shared Folders > <shared_folder_name>**.
 - Go directly to the folder using the UNC path
`\\vmware-host\Shared Folders\<shared_folder_name>`.

View Shared Folders in a Linux or Solaris 10 Guest

For information about permission settings on the files you view, also see [“Permissions and Folder Mounting for Shared Folders on Linux Guests”](#) on page 196.

To view shared folders in a Linux or Solaris 10 guest

- On a Linux virtual machine, shared folders appear under `/mnt/hgfs`.
- On a Solaris virtual machine, shared folders appear under `/hgfs`.

Permissions and Folder Mounting for Shared Folders on Linux Guests

The version of VMware Tools included in Workstation 7.0 contains performance improvements, support for symbolic links if you use a Linux host, a new mechanism for mounting shared folders, and permissions enhancements.

Performance Improvements

Host-guest file sharing is integrated with the guest page cache. Files in shared folders are cached for reading and can be written to asynchronously. However, you do not experience the read caching benefits on files that are being actively written to from the guest.

To speed performance, use the `ttl` (time to live) option to the `mount` command. Use this option to specify the interval used by the `hgfs` (host-guest file system) driver for validating file attributes. For example, if you use the following command, attributes are validated every 3 seconds instead of every 1 second, which is the default:

```
mount -o ttl=3 -t vmhgfs .host:/<share> <mountpoint>
```

NOTE Lengthening the interval involves some risk. If a process in the host modifies a file's attributes, the guest might not get the modifications as quickly, and the file can become corrupted.

Folder Mounting

This mechanism allows you to mount one or more directories or subdirectories in a shared folder to any location in your file system in addition to the default location of `/mnt/hgfs`. You can use the `mount` program to mount all shares, one share, or a subdirectory within a share to any location in your file system. The following table provides examples.

Command	Description
<code>mount -t vmhgfs .host:/ /home/user1/shares</code>	Mounts all shares to <code>/home/user1/shares</code>
<code>mount -t vmhgfs .host:/foo /tmp/foo</code>	Mounts the share named <code>foo</code> to <code>/tmp/foo</code>
<code>mount -t vmhgfs .host:/foo/bar /var/lib/bar</code>	Mounts the subdirectory <code>bar</code> within the share <code>foo</code> to <code>/var/lib/bar</code>

When you use the `mount` program, you can use VMware-specific options in addition to the standard `mount` syntax. To see usage information for the host-guest file system options, enter this command:

```
/sbin/mount.vmhgfs -h
```

NOTE When you install VMware Tools, an entry is made to `etc/fstab` to specify the location of shared folders. You can edit this file to change or add entries.

To use `mount` in this way, you must use the virtual machine settings editor in Workstation to set up and enable a shared folder. After the share exists, you can mount the shared folder to other locations besides the default.

In previous versions of VMware Tools, when a Linux guest attempted to mount a shared folder, the `vmware-guestd` program attempted to perform the mount. If it failed, the only evidence of the failure was an empty folder.

With the new version of VMware Tools, the Tools services script loads a driver that performs the mount. If the mount fails, a message appears regarding mounting HGFS shares.

The mount can fail if shared folders are disabled or if the share does not exist. You are not prompted to re-run the VMware Tools configurator (the `vmware-config-tools.pl` file).

Improved Handling of Permissions

Many refinements have been made for Linux guests on both Linux and Windows hosts:

- If you use a Linux host and create files that you want to share with a Linux guest, the file permissions shown on the guest are exactly the same as those on the host.

Use `fmask` and `dmask` to mask permissions bits for files and directories.

- If you use a Windows host and create files that you want to share with a Linux guest, read-only files are displayed as having read and execute permission for everyone, and other files are shown as fully writable by everyone.
- If you use a Linux guest to create files for which you want to restrict permissions, use the `mount` program with the following options in the guest: `uid`, `gid`, `fmask`, `dmask`, `ro` (read-only), and `rw` (read-write). Note that `rw` is the default.

If you are using a virtual machine created with the Windows version of Workstation or a previous release of the Linux version of Workstation, you can change only the owner permissions. This behavior is the same as in previous releases.

Using a Mapped Drive

You can map a virtual disk to a host instead of using shared folders or copying data between a guest and host. In this case, you can map a virtual disk in a host file system as a separate mapped drive. Using a mapped drive lets you connect to the virtual disk without going into a virtual machine.

After you map the virtual disk to a drive on the host, you cannot power on any virtual machine that uses that disk until you disconnect it from the host.

You can use Workstation to map the disk to a drive on the host, and to disconnect the drive. On Windows, if you attempt to use the host's **My Computer > Tools > Disconnect Network Drive** command, you will not see the mapped drive letter in the list of network drives.

Map or Mount a Virtual Disk to a Drive on the Host

Before you begin to map a virtual disk, make sure that all virtual machines that use the disk are powered off. Also, take the following considerations into account:

- You can mount volumes formatted with FAT (12/16/32) or NTFS only. If the virtual disk has a mix of partitions (volumes) where, for example, a partition is unformatted or is formatted with a Linux operating system and another partition is formatted with a Windows operating system, you can mount the Windows partition only.
- You can mount a virtual disk that has a snapshot, but if you write to the disk, you can irreparably damage a snapshot or linked clone previously created from the virtual machine.
- You cannot mount a virtual disk if any of its `.vmdk` files are compressed or have read-only permissions. Change these attributes before mounting the virtual disk.
- You cannot map or mount a virtual disk that is encrypted.



CAUTION VMware recommends that you leave the check box **Open file in read-only mode** selected in the Map a Virtual Disk dialog box. This setting prevents you from accidentally writing data to a virtual disk that might be the parent of a snapshot or linked clone. Writing to such a disk might make the snapshot or clone unusable.

To map or mount a virtual disk to a drive on the host

- 1 Open the menu to mount a virtual disk to a drive on the host.
 - On Windows, select **File > Map or Disconnect Virtual Disks**.
 - On Linux, select **File > Mount or Unmount Virtual Disks**.
- 2 Map or mount a virtual disk.
 - On Windows, in the Map or Disconnect Virtual Drives dialog box, click **Map**.
 - On Linux, in the Mount or Unmount Virtual Drives dialog box, click **Mount Disk**.
- 3 In the dialog box, click **Browse**, navigate to a disk file (`.vmdk` file), select it, and click **Open**.

- 4 Select the volume to map or mount, and select a drive letter that is not being used on your host.
- 5 Click **OK** or **Mount**.
The drive appears on your host. From the host, you can read from or write to files on the mapped virtual disk.
- 6 (Optional) To view a mapped drive, do one of the following:
 - On Windows, select **File > Map or Disconnect Virtual Disks**.
 - On Linux, select **File > Mount or Unmount Virtual Disks**

When you are ready to unmap or unmount the drive, see [“Disconnect the Host from the Virtual Disk”](#) on page 200.

Disconnect the Host from the Virtual Disk

To access the mapped virtual disk from a virtual machine again, you must disconnect it. You can disconnect the host from the virtual disk using two different methods.

To disconnect the host from the virtual disk

Do one of the following:

- Use the **File** menu in Workstation:
 - a Choose **File > Map or Disconnect Virtual Disks** or **Mount or Unmount Virtual Disks**.
 - b In the dialog box, select a volume to disconnect and click **Disconnect** or **Unmount**.
 - c If you receive an error message asking whether to forcibly disconnect, click **Yes**.
 - d Click **OK**.
- Use the **VM** menu for a selected virtual machine:
 - a Choose **VM > Settings > Hardware**.
 - b Select the hard disk and click **Utilities > Disconnect** or **Unmount**.

You can now power on any virtual machine that uses this disk.

Preserving the State of a Virtual Machine

9

Suspending a virtual machine lets you save the current state so that you can continue work later from the same state. Taking a snapshot lets you preserve the state of the virtual machine so you can return to the same state repeatedly. This chapter includes the following topics:

- [“Using the Suspend and Resume Features”](#) on page 201
- [“Using Snapshots”](#) on page 203

Using the Suspend and Resume Features

You can use the suspend and resume features to save the current state of a virtual machine. When you resume, any applications you were running when you suspended the virtual machine are resumed in their running state, and the content is the same as when you suspended the virtual machine.

The speed of the suspend and resume operations depends on how much data changed since the virtual machine started. In general, the first suspend operation takes longer than later suspend operations.

When you resume and do additional work in the virtual machine, you cannot return to the state the virtual machine was in at the time you suspended. To preserve the state of the virtual machine so that you can return to the same state repeatedly, take a snapshot, as described in [“Using Snapshots”](#) on page 203.

Use Hard Suspend or Soft Suspend

You can configure the **Suspend** button or menu command to run a VMware Tools script in the guest operating system before doing the suspend operation. This configuration is called a soft suspend.

Before you begin, make sure VMware Tools is installed in the guest operating system. See [“Installing VMware Tools”](#) on page 104.

On Windows guests, when you do a soft suspend, a script releases the IP address if the guest operating system is using DHCP. On Linux, FreeBSD, and Solaris guests, the script stops networking for the virtual machine. When you use the **Resume** command on Windows guests, a script gets a new IP address from DHCP. On Linux, FreeBSD, and Solaris guests, networking restarts.

To use hard suspend or soft suspend

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab, and select **Power**.
- 4 In the **Power controls** section, specify a hard suspend (**Suspend**) or a soft suspend (**Suspend Guest**) operation.
- 5 Click **OK**.

Suspend or Resume a Virtual Machine

The suspend and resume features let you save the current state of your virtual machine and continue work later from the same state.

Before suspending a virtual machine, specify whether to stop networking before suspending. See [“Use Hard Suspend or Soft Suspend”](#) on page 201.

To suspend or resume a virtual machine

Do one of the following:

- To suspend a virtual machine, choose **VM > Power > Suspend**.

If the virtual machine is running in exclusive full screen mode, which hides the toolbar, return to windowed mode by pressing the Ctrl+Alt+Enter key combination.

When you suspend a virtual machine, a file with a `.vmss` extension is created in the working directory.

- To resume a suspended virtual machine, select the virtual machine and choose **VM > Power > Resume**.

When you resume the virtual machine, its state is restored from the `.vmss` file.

Using Snapshots

Taking snapshots lets you preserve the state of the virtual machine so that you can return to the same state repeatedly.

Scenarios for Using Multiple Snapshots

You can take multiple snapshots of a virtual machine.

Snapshots in a Linear Process

Taking snapshots in a linear process means taking a snapshot, continuing to use the virtual machine from that point, taking another snapshot at a later point, and so on. Each snapshot is a restoration point in a single long sequence.

Figure 9-1. Snapshots as Restoration Points in a Linear Process



Workstation supports more than 100 snapshots for each linear process.

Use snapshots in a linear process for the following situations:

- You plan to make risky changes in a virtual machine, such as by testing new software or examining a virus. Before adding new, untested code to a project, take a snapshot.

You can always revert to a previous known working state of the project if the new code does not work as expected. If the new code causes no problems, you can take another snapshot of the virtual machine in its new state.

NOTE You can configure a virtual machine to take a snapshot any time it is powered off, preserving a virtual audit trail as work progresses. See [“Take or Revert to a Snapshot at Power Off”](#) on page 213.


- You create a training course and want to save the state of the virtual machine in a snapshot at each lesson’s starting point. You can use the snapshots to skip lengthy computer preparation time.

You can also configure the virtual machine to revert to a snapshot any time it is powered off. Each time a new class begins a lesson, the previous student’s work is discarded. See [“Revert at Power Off”](#) on page 211.

Snapshots in a Process Tree

You can save a number of sequences as branches from a single baseline, as [Figure 9-2](#) shows. This strategy is often used in testing software. You can take a snapshot before installing different versions of a program to ensure that each installation begins from an identical baseline.

Figure 9-2. Snapshots as Restoration Points in a Process Tree



Although Workstation supports more than 100 snapshots for each branch in a process tree, keeping more than 99 might cause the guest operating system to have problems booting. Delete some snapshots or make a full clone of the virtual machine.


Snapshot Relationships

The relationship between snapshots is like a parent-child relationship:

- In a linear process, each snapshot has one parent and one child, except for the last snapshot, which has no children.
- In a process tree, each snapshot has one parent, but one snapshot can have more than one child. Many snapshots have no children.

The parent snapshot of a virtual machine is the snapshot on which the current state (the You Are Here position in [Figure 9-3](#)) is based. After you take a snapshot, that stored state is the parent snapshot of the virtual machine. If you revert or go to an earlier snapshot, the earlier snapshot becomes the parent snapshot of the virtual machine.

Figure 9-3. Parent-Child Relationship Between Snapshots



Information Captured by Snapshots

A snapshot captures the entire state of the virtual machine at the time you take the snapshot which includes the following configurations.

- **Memory state** – Contents of the virtual machine memory
- **Settings state** – Virtual machine settings
- **Disk state** – State of all the virtual disks

The state of a physical disk is not preserved when you take a snapshot. However, the state of an independent disk is not affected by snapshots.

Snapshots operate on individual virtual machines. If you select a team of virtual machines and take a snapshot, only the state of the active virtual machine is preserved. See [“Summary and Console Views for Teams and Their Virtual Machines”](#) on page 276.

When you revert to a snapshot, you return the memory, settings, and virtual disks of the virtual machine to the state they were in when you took the snapshot. To suspend, power on, or power off the virtual machine when you launch it, be sure it is in that state when you take the snapshot.

Snapshot Conflicts

Avoid taking a snapshot when applications in the virtual machine are communicating with other computers, especially in production environments.

Suppose you take a snapshot while the virtual machine is downloading a file from a server on the network. After you take the snapshot, the virtual machine continues downloading the file, communicating its progress to the server. If you revert to the snapshot, communications between the virtual machine and the server are confused and the file transfer fails.

Or consider a case in which you take a snapshot while an application in the virtual machine is sending a transaction to a database on a separate machine. If you revert to that snapshot after the transaction starts but before it is committed, the database is likely to be confused.

Enable or Disable Background Snapshots

When you set a preference to take snapshots in the background, you can continue working while the state of the virtual machine is being preserved. A progress indicator for the background snapshot is displayed in one of the corners of the Workstation window.

Before you begin, on Linux hosts, run Workstation as the root user. Only root users are allowed to change this preference setting.

If you take another snapshot or revert to a snapshot before Workstation completes a pending snapshot operation, a progress dialog box appears. You must wait for the pending snapshot operation to finish before the next snapshot or resume operation begins.

Enabling background snapshots for a host with slow hard disks can adversely affect performance. If you experience significant performance problems when taking or restoring snapshots, disable background snapshots.

To enable or disable background snapshots

- 1 Choose **Edit > Preferences**.
- 2 Click the **Priority** tab.
- 3 Use the check box in the **Snapshots** section to enable or disable background snapshots.
- 4 Click **OK** and restart the virtual machine.

Exclude a Virtual Disk from Snapshots

In certain configurations, you might want to revert some disks to a snapshot while other disks retain all changes. For example, you might want a snapshot to preserve a disk with your operating system and applications, while always keeping the changes to a disk with your documents.

You can exclude virtual disks from a snapshot by changing the disk mode. Before you begin, power off the virtual machine and delete any existing snapshots.

To exclude a virtual disk from snapshots







- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select the drive to exclude and click **Advanced**.
- 4 Select **Independent** and select one of the following options:
 - **Persistent** – Disks in persistent mode behave like conventional disks on a physical computer. All data written to a disk in persistent mode is written permanently to the disk.
 - **Nonpersistent** – Changes to disks in nonpersistent mode are discarded when you power off or reset the virtual machine. Nonpersistent mode enables you to restart the virtual machine with a virtual disk in the same state every time. Changes to the disk are written to and read from a redo log file that is deleted when you power off or reset.

Snapshot Manager Overview

You can review all snapshots for the active virtual machine and act on them directly in the snapshot manager.

[Table 9-1](#) identifies the icons that you might see in the snapshot tree of the snapshot manager.

Table 9-1. Snapshot Manager Icons

	Snapshot of a virtual machine that is powered off
	Snapshot of a virtual machine that is powered on
	Snapshot used to create a linked clone
	Recording of a virtual machine
	AutoProtect snapshot
	You Are Here icon

The snapshot tree shows all snapshots for the virtual machine and the relationship between snapshots. The **You Are Here** icon is not a snapshot. It shows the current state of the virtual machine. See [“Snapshot Relationships”](#) on page 204.

NOTE Point to a snapshot (without clicking) to display the complete name of that snapshot.

Most snapshot manager actions are available as menu commands from the **VM > Snapshot** menu. The following actions, however, are available only from the snapshot manager:

- **Renaming a snapshot** – The **Name** text box is editable. If you rename a snapshot for a cloned virtual machine, use the **Description** field for future identification.
- **Changing or adding a description** – The **Description** text box is editable.
- **Deleting a snapshot** – See [“Delete a Snapshot or a Recording”](#) on page 212.

On Linux hosts, the snapshot manager has a slightly different appearance. On Linux hosts, right-click the toolbar to change the icon style. You can display icons and text, icons only, text only, and so on.

Open and Use the Snapshot Manager

Use the snapshot manager to review all snapshots for the active virtual machine and work on them directly.

To open and use the snapshot manager

- 1 Select the virtual machine.
- 2 Choose **VM > Snapshot > Snapshot Manager**.
- 3 Select a snapshot or recording and click the button for the needed action.

To select more than one snapshot or recording, Ctrl+click the needed snapshots and recordings.

If the **Take Snapshot** button is disabled, it might be because the virtual machine has multiple disks in different disk modes. For example, if you have a special purpose configuration that requires you to use an independent disk, you must power off the virtual machine before taking a snapshot.

Take a Snapshot

You can usually take a snapshot while a virtual machine is powered on, powered off, or suspended.

Following are the prerequisites for taking a snapshot:

- Any suspend operations must be complete.
- The virtual machine is not communicating with another computer. See [“Snapshot Conflicts”](#) on page 206.

- If your use of virtual machines is strongly performance oriented, the guest operating system's drives are defragmented. See [“Defragment Virtual Disks”](#) on page 239.
- If the virtual machine has multiple disks in different disk modes, the virtual machine is powered off. For example, if a special purpose configuration requires you to use an independent disk, you must power off the virtual machine before taking a snapshot.
- If the virtual machine was created with Workstation 4 delete any existing snapshots or upgrade the virtual machine to Workstation 5.x or higher. See [“Change the Version of a Virtual Machine”](#) on page 94.

To take a snapshot

- 1 Choose **VM > Snapshot > Take Snapshot**.
- 2 Enter a unique name.
- 3 (Optional) Enter a description.

Use this field to record notes about the virtual machine state captured in the snapshot.

- 4 Click **OK**.

Rename a Snapshot or Recording

Use the snapshot manager to change the name of a snapshot or its description at any time.

To rename a snapshot or recording

- 1 Choose **VM > Snapshot > Snapshot Manager**.
- 2 Select the snapshot or recording.
- 3 Edit the text in the **Name** text box and click **Close**.

If you rename a snapshot for a cloned virtual machine, use the **Description** field to specify which virtual machine was cloned.

Restore an Earlier State from a Snapshot

Restore a snapshot in Workstation by using the **Revert** and **Go to** commands.

The **Revert** command has the same effect as using the **Go to** command and selecting the parent snapshot of the virtual machine. It reverts to the parent snapshot of the current state. This state corresponds to the You Are Here position in the snapshot manager. See “[Snapshot Relationships](#)” on page 204.

The **Go to** command is not limited to the parent snapshot of the current state. You can choose any existing snapshot of the virtual machine.



CAUTION If you add an independent disk to a virtual machine and take a snapshot, reverting to the snapshot will not affect the state of the independent disk.

But if you take a snapshot of a virtual machine and then add any kind of disk, reverting to the snapshot will remove the disk from the virtual machine. If associated disk (.vmdk) files are not used by another snapshot, the disk files are deleted.

To restore an earlier state from a snapshot

Do one of the following:

- To revert to the parent snapshot, choose **VM > Snapshot > Revert to Snapshot**.
- To revert to a snapshot that is not the parent, choose **VM > Snapshot** and select the snapshot name.
- To set the virtual machine to revert to the parent snapshot every time the virtual machine is powered off, see “[Revert at Power Off](#)” on page 211.

NOTE The list of snapshots in **VM > Snapshot** does not show an AutoProtect snapshot until you restore that snapshot in the snapshot manager. Use the snapshot manager (**VM > Snapshot > Snapshot Manager**) to display and restore AutoProtect snapshots.

Revert at Power Off

You can set the virtual machine to revert to the parent snapshot any time it is powered off. The parent snapshot of a virtual machine is the snapshot on which the current state (the You Are Here position) is based.

To set a virtual machine to revert to a snapshot at power off

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.

- 3 Click the **Options** tab and select **Snapshot/Replay**.
- 4 In the **When powering off** section, select **Revert to snapshot**.

Delete a Snapshot or a Recording

In most cases, deleting a snapshot or recording does not affect other snapshots, recordings, or the current state of the virtual machine. Use the snapshot manager to delete a snapshot.



CAUTION If a snapshot is used to create a clone, the snapshot becomes locked. If you delete a locked snapshot, the clones created from that snapshot no longer operate.

You cannot delete a snapshot if the associated virtual machine is designated as a template for cloning. See [“Enable Template Mode for a Parent Virtual Machine of Linked Clones”](#) on page 221.

To delete a snapshot or recording

- 1 Select **VM > Snapshot > Snapshot Manager**.
- 2 (Optional) To delete AutoProtect snapshots, make sure that **Show AutoProtect snapshots** is selected.
- 3 Select an option to delete a snapshot or recording:
 - To delete a single snapshot or recording, select it and click **Delete**.
 - To delete a snapshot or recording and all of its children, right-click it and select **Delete Snapshot/Recording and Children**.

If the children of the snapshot include AutoProtect snapshots, the AutoProtect snapshots are deleted only if **Show AutoProtect snapshots** is selected.
 - To delete all snapshots and recordings, right-click a snapshot or recording, select **Select All**, and click **Delete**.
- 4 When prompted to confirm the deletion, click **OK**, and click **Close** in the snapshot manager.

Take or Revert to a Snapshot at Power Off

You can set a virtual machine to automatically revert to a snapshot or to take a new snapshot whenever you power off the virtual machine.

To take a snapshot or revert to one at power off

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 Click the **Options** tab and select **Snapshot/Replay**.
- 4 Select an option in the **When powering off** section:
 - **Just power off** – Powers off without making any changes to snapshots.
 - **Revert to snapshot** – Reverts to the parent snapshot of the current state of the virtual machine (that is, the parent snapshot of the You Are Here position in the Snapshot Manager window).

An instructor might use this setting to discard student answers for a computer lesson when a virtual machine is powered off at the end of class.
 - **Take a new snapshot** – Takes a snapshot of the virtual machine state after it is powered off. This is useful to preserve milestones automatically. The snapshot appears in the snapshot manager. The name of this snapshot is the date and time the virtual machine was powered off. The description is “Automatic snapshot created when powering off.”
 - **Ask me** – Prompts you, every time you power off a virtual machine, to choose to power off, revert, or take a snapshot.
- 5 Click **OK**.

Using AutoProtect Snapshots

The AutoProtect feature preserves the state of your virtual machine by taking snapshots at regular intervals that you specify. This process is in addition to manual snapshots, which you can take at any time.

You can set AutoProtect options in the **Options** tab of the Virtual Machine Settings window (**VM > Settings**). You select the interval of time between AutoProtect snapshots and the maximum number of snapshots that will be retained. After the maximum number of AutoProtect snapshots is reached, Workstation deletes the oldest AutoProtect snapshot each time a new AutoProtect snapshot is taken. Based on the settings you enter, Workstation retains a selection of AutoProtect snapshots over a range of time. Workstation displays this selection in the Virtual Machine Settings window, along with an estimate of the minimum amount of disk space taken by AutoProtect snapshots. This minimum is affected by the Memory setting in Virtual Machine Settings. The more virtual memory your virtual machine has, the more disk space is available for AutoProtect snapshots.

The interval between AutoProtect snapshots is measured only when the virtual machine is powered on. For example, suppose you set AutoProtect to take snapshots hourly, and then power off the virtual machine five minutes later. The next AutoProtect snapshot takes place 55 minutes after you power on the virtual machine again, regardless of the length of time the virtual machine was powered off.

AutoProtect Restrictions

The AutoProtect feature has the following restrictions:

- Because AutoProtect takes snapshots only while a virtual machine is powered on, AutoProtect snapshots cannot be cloned. You can clone a virtual machine only if it is powered off.
- AutoProtect snapshots are not taken in VMware Player, even if AutoProtect was enabled for the virtual machine in Workstation.
- AutoProtect snapshots are not taken while you are using the Record/Replay feature.

Set Up Automatic Snapshots with AutoProtect

You can set Workstation to take snapshots of your virtual machine at regular intervals, with the AutoProtect feature.

To set up automatic snapshots with AutoProtect

- 1 Select the virtual machine.
- 2 Select **VM > Settings**.
- 3 On the **Options** tab, under Settings, select **AutoProtect**.
- 4 Select **Enable AutoProtect**.
- 5 Select the interval between snapshots.
- 6 Select the maximum number of AutoProtect snapshots to retain.

This setting does not affect the number of regular snapshots you can take and keep.

- 7 Select **OK**.

Preserve AutoProtect Snapshots from Being Deleted

After Workstation has taken the maximum number of AutoProtect snapshots that you specify when you set up AutoProtect, Workstation deletes the oldest AutoProtect snapshot each time a new AutoProtect snapshot is taken. In the snapshot manager, you can preserve AutoProtect snapshots from this deletion.

To preserve AutoProtect snapshots from being deleted

- 1 Select **VM > Snapshot Manager**.
- 2 Select **Show AutoProtect snapshots**.
- 3 Select the AutoProtect snapshot to preserve.
- 4 Select **Keep**.

Snapshots and Workstation 4 Virtual Machines

Workstation 4 virtual machines do not support multiple snapshots. For full Workstation 7 functionality, you must upgrade. See [“Change the Version of a Virtual Machine”](#) on page 94.

If a Workstation 4 virtual machine has a snapshot, you must remove the snapshot before you upgrade. Use your earlier, Workstation 4 application to remove the snapshot, and then upgrade to Workstation 7.

Cloning, Moving, and Sharing Virtual Machines

10

Cloning a virtual machine is faster and easier than copying it. This chapter provides instructions and information on how to move your virtual machines from one host to another, or elsewhere on the same host, plus recommendations on how to share virtual machines with other users. This chapter includes the following topics:

- [“The Virtual Machine’s Universal Unique Identifier”](#) on page 217
- [“Cloning a Virtual Machine”](#) on page 219
- [“Moving a Virtual Machine”](#) on page 223
- [“Moving an Older Virtual Machine”](#) on page 226
- [“Moving Linked Clones”](#) on page 227
- [“Sharing Virtual Machines with Other Users”](#) on page 227
- [“Using VNC for Remote Connections to a Virtual Machine”](#) on page 228
- [“Make Virtual Machines Available for Streaming from a Web Server”](#) on page 230
- [“Sharing Virtual Machines with VMware Player”](#) on page 231

The Virtual Machine’s Universal Unique Identifier

To ensure all virtual machines are identified properly, each virtual machine is automatically assigned a universal unique identifier (UUID).

Use the UUID of a virtual machine for system management in the same way you use the UUID of a physical computer. The UUID is stored in the SMBIOS system information descriptor. It can be accessed by standard SMBIOS scanning software, such as SiSoftware Sandra or the IBM utility `smbios2`.

This UUID is generated when you initially power on the virtual machine. As long as you do not move or copy the virtual machine to another location, the UUID remains constant. To set a specific UUID, see [“Specify a UUID for a Virtual Machine”](#) on page 218.

UUID Options When You Move a Virtual Machine

When you power on a virtual machine that was moved or copied to a new location, a message appears, asking whether you moved or copied the virtual machine. If you indicate that you copied the virtual machine, a new UUID is generated.

Suspending and resuming a virtual machine does not trigger the process that generates a UUID. The UUID in use at the time the virtual machine was suspended remains in use when the virtual machine is resumed, even if it was copied or moved. The next time the virtual machine is rebooted, the message appears.

Set the Virtual Machine to Always Keep or Always Create a UUID

If a virtual machine is set to always keep or always create a UUID, users are not prompted when a virtual machine is moved or copied. You can set this property by editing the virtual machine's configuration file.

To set the virtual machine to always keep or always create a UUID

- 1 Power off the virtual machine.
- 2 Open the configuration (.vmx) file with a text editor.
- 3 Add the following line:

```
uuid.action = "<action>"
```

The value for <action> can be either **create**, to always generate a new UUID, or **keep**, to always retain the UUID.

Specify a UUID for a Virtual Machine

Although UUIDs are automatically assigned to virtual machines, you can override the generated UUID value and assign a specific UUID.

The UUID is a 128-bit integer. The 16 bytes of this value are separated by spaces, except for a dash between the eighth and ninth hexadecimal pairs. Following is an example of a UUID:

```
00 11 22 33 44 55 66 77-88 99 aa bb cc dd ee ff
```

To specify a UUID for a virtual machine

- 1 Power off the virtual machine.
- 2 Open the configuration (.vmx) file with a text editor.
- 3 Search for the line that contains `uuid.bios`.

The format of the line is `uuid.bios = "<uuid_value>"`, with quotation marks around the parameter value. Following is an example of the configuration setting:

```
uuid.bios = "00 11 22 33 44 55 66 77-88 99 aa bb cc dd ee ff"
```

- 4 Replace the existing UUID value with the specific UUID value.
- 5 Save and close the file.
- 6 Power on the virtual machine.

The new UUID is used when the virtual machine boots.

Cloning a Virtual Machine

Installing a guest operating system and applications can be time consuming. With clones, you can make many copies of a virtual machine from a single installation and configuration process.

Clones are useful when you must deploy many identical virtual machines to a group. For example:

- An MIS department can clone a virtual machine for each employee, with a suite of preconfigured office applications.
- A virtual machine can be configured with a complete development environment and then cloned repeatedly as a baseline configuration for software testing.
- A teacher can clone a virtual machine for each student, with all the lessons and labs required for the term.

- With clones you can make copies of a virtual machine without browsing a host file system or worrying if you have located all the configuration files. The existing virtual machine is called the parent of the clone. When the cloning operation is complete, the clone becomes a separate virtual machine. These are the main characteristics of a clone:
 - Changes made to a clone do not affect the parent virtual machine. Changes made to the parent virtual machine do not appear in a clone.
 - A clone's MAC address and UUID are different from the parent virtual machine.

Although a clone is a separate virtual machine, if the clone is a linked clone, it shares virtual disks with the parent virtual machine. See [“Types of Clones”](#) on page 220.

Types of Clones

Two types of clones are available: full and linked.

Full Clones

A full clone is a complete and independent copy of a virtual machine. It shares nothing with the parent virtual machine after the cloning operation. Ongoing operation of a full clone is entirely separate from the parent virtual machine.

Because a full clone does not share virtual disks with the parent virtual machine, full clones generally perform better than linked clones. However, full clones take longer to create than linked clones. Creating a full clone can take several minutes if the files involved are large.

The full clone duplicates only the state of the virtual machine at the instant of the cloning operation. Thus the full clone does not have access to any snapshots that might exist of the parent virtual machine.

Linked Clones

A linked clone is a copy of a virtual machine that shares virtual disks with the parent virtual machine in an ongoing manner. A linked clone is made from a snapshot of the parent. See [“Scenarios for Using Multiple Snapshots”](#) on page 203. This conserves disk space and allows multiple virtual machines to use the same software installation.



CAUTION You cannot delete the linked clone snapshot without destroying the linked clone. You can safely delete this snapshot only if you also delete the clone that depends on it.

All files available on the parent at the moment you take the snapshot continue to remain available to the linked clone. Ongoing changes to the virtual disk of the parent do not affect the linked clone, and changes to the disk of the linked clone do not affect the parent.

A linked clone must have access to the parent. Without access to the parent, you cannot use a linked clone. You can make a linked clone from a linked clone, but keep in mind that the performance of the linked clone degrades. When possible, make a linked clone of the parent virtual machine.

If you make a full clone from a linked clone, however, the full clone is an independent virtual machine that does not require access to the linked clone or its parent.

Linked clones are created swiftly, so you can easily create a unique virtual machine for each task. You can also easily share a virtual machine with other users by storing the virtual machine on your local network, where other users can quickly make a linked clone. This facilitates collaboration. For example, a support team can reproduce a bug in a virtual machine, and an engineer can quickly make a linked clone of that virtual machine to work on the bug.

Creating Clones

If you decide to create a linked clone and you want to prevent the parent virtual machine from being accidentally deleted, enable template mode before using the Clone Virtual Machine wizard.

Enable Template Mode for a Parent Virtual Machine of Linked Clones

To prevent anyone from deleting the parent virtual machine for a linked clone, designate the parent as a template. When template mode is enabled, a virtual machine cannot be deleted or added to a team, and the virtual machine's snapshots cannot be deleted.

To enable template mode for a parent virtual machine of linked clones

- 1 Select the virtual machine to use as a parent of your linked clone.
- 2 Verify that the parent has at least one snapshot.

Open the snapshot manager and create a snapshot if none exists. See [“Snapshot Manager Overview”](#) on page 208.

- 3 Choose **VM > Settings**.

- 4 Click the **Options** tab, and select **Advanced**.
- 5 In the **Settings** section, click **Enable Template mode (to be used for cloning)** and click **OK**.

Use the Clone Virtual Machine Wizard

The Clone Virtual Machine wizard guides you through the process of making a clone. You do not need to locate and manually copy the parent virtual machine files.

Before making a linked clone, defragment the guest operating system's drives on the parent virtual machine. Use the tools in the guest operating system to run a defragmentation utility. See [“Defragment Virtual Disks”](#) on page 239.

For information about preventing a linked clone's parent virtual machine from being deleted, see [“Enable Template Mode for a Parent Virtual Machine of Linked Clones”](#) on page 221.

NOTE Workstation 4.x virtual machines, and virtual machines created with other VMware products that are compatible with Workstation 4.x, must be upgraded to at least Workstation 5.x virtual machines before you can clone them. See [“Change the Version of a Virtual Machine”](#) on page 94.

To use the Clone Virtual Machine wizard

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Clone** to open the Clone Virtual Machine wizard.
- 4 On the Welcome page, click **Next**.
- 5 On the Clone Source page, select the state of the parent from which you want to create a clone and click **Next**.

You can choose to create a clone from the parent's current state or from any existing snapshot of the parent. If you select the current state, Workstation creates a snapshot of the virtual machine before cloning it.

The wizard does not allow you to clone from the current state when template mode is enabled.

- 6 On the Clone Type page, specify whether to create a linked clone or a full clone and click **Next**.

- 7 On the Name of the New Virtual Machine page, enter a name and a path for the cloned virtual machine and click **Finish**.

A full clone can take many minutes to create, depending on the size of the virtual disk that is being duplicated.

- 8 Click **Close** to exit the Clone Virtual Machine wizard.

The Clone Virtual Machine wizard automatically creates a new MAC address and UUID for the clone. Other configuration information is identical to that of the parent virtual machine. For example, a machine's name and static IP address configuration are not altered by the Clone Virtual Machine wizard.

- 9 To prevent conflict with static IP addressing, change the clone's static IP address before the clone connects to the network.

See [“Selecting IP Addresses on a Host-Only Network or NAT Configuration”](#) on page 304.

Moving a Virtual Machine

You can take a virtual machine that was created by using Workstation and move it to a different computer or to a different location on the same computer. You can even move a virtual machine to a host with a different operating system. For example, you can move a virtual machine from a Windows host to a Linux or ESX Server host.

In general, moving a virtual machine means moving the files that make up the virtual machine. The path names for all files associated with a Workstation virtual machine are relative, meaning the path to each file is relative to the virtual machine directory. For example, if you are in the virtual machine directory, the relative path to the virtual disk file is `<machine_name>.vmdk`.



CAUTION Always make backup copies of all the files in a virtual machine's directory before you move a virtual machine.

Hosts with Different Hardware

The guest operating system might not work correctly if you move a virtual machine to a host with significant hardware differences, such as from a 64-bit host to a 32-bit host or from a multiprocessor host to a uniprocessor host.

Moving Between 64-Bit and 32-Bit Hosts

You can move a virtual machine from a 32-bit host to a 64-bit host but not from a 64-bit host to a 32-bit host unless the 32-bit host has a supported 64-bit processor.

NOTE Workstation supports 64-bit guest operating systems only in Workstation 5.5 and higher, and only on host machines with supported processors. When you power on a virtual machine with a 64-bit guest operating system, Workstation performs an internal check. If the host CPU is not a supported 64-bit processor, you cannot power on the virtual machine. For the list of processors Workstation supports for 64-bit guest operating systems, see [“PC Hardware”](#) on page 23.

Moving Between Multiprocessor and Uniprocessor Hosts

For all supported configurations of 32-bit and 64-bit host and guest operating systems running on multiprocessor host machines, Workstation 5.5 and higher virtual machines support four-way virtual symmetric multiprocessing (SMP). This support enables you to assign up to four virtual processors to a virtual machine. This is supported only for host machines with at least two logical processors. See [“Use Four-Way Virtual Symmetric Multiprocessing”](#) on page 366.

NOTE If the host is a uniprocessor machine, assigning two processors is not supported. A warning message appears. You can disregard this message and assign two processors to the virtual machine, but when you finish creating the virtual machine, you cannot power it on unless you move it to a host machine with at least two logical processors.

Open a Virtual Machine Created in ESX Server That Has More Than Two Processors

You can use Workstation 5.5 or higher, running on a multiprocessor host machine, to open a virtual machine created in VMware ESX Server that has one or more virtual processors. However, in Workstation you cannot power on or resume a virtual machine that has more than two virtual processors assigned, even if more processors were assigned when the virtual machine was created in ESX Server.

You can see this setting in the virtual machine's summary view or by using the virtual machine settings editor.

To open a virtual machine created in ESX Server that has more than two processors

- 1 Select the virtual machine and choose **VM > Settings > Hardware > Processors**.
- 2 Note that **Number of Processors** is set to **Other (x)**, where **x** is the number of processors originally assigned in ESX Server.

Workstation preserves this original configuration setting for the number of processors, even though two is the maximum number of processors supported.

- 3 Change this setting to two processors so that you can power on the virtual machine in Workstation.

After you commit a change to this setting, the original setting for number of processors is discarded, and no longer appears as an option in the virtual machine settings editor.

Move a Virtual Machine to a New Location or a New Host

You can move the virtual machine to a different location on the same host or move it to a new host.

For more information about compatibility between VMware products, see the *VMware Virtual Machine Mobility Planning Guide*.

To move a virtual machine to a new location or a new host

- 1 Make sure that all the virtual machine files are stored in the virtual machine directory.

For example, if you configured the working directory to reside in a different location on the host, move it into the virtual machine directory and use the virtual machine settings editor (**VM > Settings > Options > General**) to point to this location.

If the virtual machine you want to move is a linked clone, see [“Moving Linked Clones”](#) on page 227.

- 2 Shut down the guest operating system and power off the virtual machine.

- 3 Copy all the files in the virtual machine directory to the new location.

To move the virtual machine's files to another host, if you do not have a network connection to the new host, use a shared network directory, burn the files onto a DVD, or use some other storage media that has enough disk space.

For more information about the files that you are moving, see [“Files That Make Up a Virtual Machine”](#) on page 97.

- 4 On the new host, start Workstation, choose **File > Open**, and browse to the virtual machine's configuration (.vmx) file in its new location.
- 5 (Optional) If you are moving the virtual machine to a different location on the same host, remove the virtual machine from the **Favorites** list and add it again using the new location.
- 6 When you are certain that the virtual machine in the new location works correctly, delete the virtual machine files from the old location, if needed.

If the virtual machine in the new location is not working correctly, examine the virtual machine in the original location to determine if you missed copying some files. Some files might reside outside of the virtual machine directory.

Use the virtual machine settings editor (**VM > Settings > Hardware**) to select devices and determine whether any associated files point to locations that cannot be accessed from the new location.

Workstation generates a different MAC address for the virtual network adapter when you move a virtual machine to a new host computer or to a different directory on the same host computer. A new MAC address is also generated when you rename a directory in the path to the virtual machine's configuration file. See [“Maintaining and Changing the MAC Address of a Virtual Machine”](#) on page 308.

Moving an Older Virtual Machine

If you created a virtual machine by using Workstation 2.x or 3.x, you must upgrade it to at least Workstation 4. Workstation 7.0 does not support Workstation 2 or 3 virtual machines.

Moving Linked Clones

You can move a linked clone as you do an ordinary Workstation virtual machine. However, if you move a linked clone (or if you move its parent virtual machine), make sure the clone can access the parent virtual machine. Place the parent in shared directory or on a networked file server.

For example, if you put a linked clone on a laptop and the parent remains on another machine, you can use the clone only when the laptop connects to the network or drive where the parent is stored. To use a cloned virtual machine on a disconnected laptop, you must use a full clone or you must move the parent virtual machine to the laptop.

You cannot power on a linked clone if Workstation cannot locate the original virtual machine.

Sharing Virtual Machines with Other Users

If you want other users to be able to access your virtual machines, consider the following points:

- Only one user can run a virtual machine at a time. Other users can also share a virtual machine by making a linked clone of it. A linked clone is a copy that uses the same virtual disks as the parent virtual machine it was copied from. See [“Cloning a Virtual Machine”](#) on page 219.
- On Windows hosts, relocate the virtual machine files to a directory that is accessible to all appropriate users. The default location for a Windows host is not typically accessible to other users:
 - On Windows XP: `C:\Documents and Settings\<user_name>\My Documents\My Virtual Machines`
 - On Windows Vista and Windows 7: `C:\Users\<user_name>\Documents\Virtual Machines`

When you configure the virtual machine in the New Virtual Machine wizard, you can specify a location for the virtual machine elsewhere on your system or on a network volume.

- On Linux hosts, set permissions for the virtual machine files appropriately.

Permissions settings are especially important for the configuration file (`.vmx`) and virtual disks (`.vmdk`). For example, if you want users to run a virtual machine but not be able to modify its configuration, do not make the configuration file writable.

Using VNC for Remote Connections to a Virtual Machine

Virtual network computing (VNC) software enables you to view and interact with one computer from any other computer or mobile device anywhere on the Internet.

VNC software is cross-platform, allowing remote control between different types of computers. For example, you can use VNC to view a Linux machine on your Windows PC. Open-source versions of VNC are freely and publicly available.

You can use Workstation to set a virtual machine to act as a VNC server, and users on other computers can install a VNC client (also called a VNC viewer) to connect to the virtual machine. After you set up a virtual machine as a VNC server, you can see a list of users who are remotely connected to the virtual machine and find out how long they have been connected.

Workstation does not need to be running when VNC connections are made. Only the virtual machine needs to be running, and it can be running in the background.

Configure a Virtual Machine as a VNC Server

You do not need to install specialized VNC software in a virtual machine to set it up as a VNC server.

To configure a virtual machine as a VNC server

- 1 Select the virtual machine and choose **VM > Settings**.
- 2 Click the **Options** tab and select **Remote Display**.
- 3 Click **Enable remote display**.

After remote display is enabled and users connect to the virtual machine with a VNC client, use the **View Connected Users** button on Remote Display settings panel to see a list of the connected users.

- 4 (Optional) Change the port number.

To connect to multiple virtual machines on the same host with a VNC client, specify a unique port number for each virtual machine. VMware suggests that you use a port number in the range from 5901 to 6001.

Keep in mind that other applications use certain port numbers, and some port numbers are privileged (only the root or Administrator user can listen). For example, the VMware Management Interface uses ports 8333 and 8222. On Linux, only the root user can listen to ports up to port number 1024.

- 5 (Optional) Set a password for connecting to the virtual machine from a VNC client.

The password can be up to 8 characters long. Because it is not encrypted when the VNC client sends it, do not use a password that you use for other systems.

- 6 Click **OK**.

After you set up a virtual machine as a VNC server, you can see a list of users who are remotely connected to the virtual machine and find out how long they have been connected. To see the list, right-click the VNC icon in the status bar and choose **Connected Users**.

Use a VNC Client to Connect to a Virtual Machine

You can install a VNC client on your host and connect to a running virtual machine.

Before you begin, determine the machine name or IP address of the host on which the virtual machine is running and, if applicable, the VNC port number and password. See [“Configure a Virtual Machine as a VNC Server”](#) on page 228.

For information about mapping the keyboard to languages other than U.S. English, see [“Specify a Language Keyboard Map for VNC Clients”](#) on page 341.

The following issues are known to occur when you connect to virtual machines with a VNC client:

- You cannot take or revert to snapshots.
- You cannot change the power state of the virtual machine. That is, you cannot power on, power off, suspend, or resume. Although you cannot power off, you can shut down the guest operating system, and shutting down might power off the virtual machine.
- You cannot copy and paste text between the host and guest operating system.
- You cannot configure the virtual machine with the virtual machine settings editor.
- Remote display does not work well if you are also using the 3-D feature. This feature is described in [“Support for Direct3D Graphics”](#) on page 173.

To use a VNC client to connect to a virtual machine

- 1 On a local or remote computer, start a VNC client.
 You can use any VNC client, but not a Java viewer in a browser. To download and install a VNC client, check one of the many Web sites where you can buy or get one for free.
- 2 Make sure the client is set for hextile encoding.
 For example, if you use RealVNC Viewer, under the **Preferred Encoding** option, select **Hextile**.
- 3 Set the client to use all colors.
 For example, if you use RealVNC Viewer, under the **Colour Level** option, select **Full (all available colours)**.
- 4 When prompted for the VNC server name, enter the name or IP address of the host computer and the port number.
 Use the format:
 <machine_name>:<port_number>
- 5 Enter a password if you are prompted to do so.

Make Virtual Machines Available for Streaming from a Web Server

With virtual machine (VM) streaming, virtual disk data is fetched on demand. You can power on a virtual machine soon after you begin downloading it from a Web server.

Downloading a virtual machine in a .zip or .tar file from a Web server can take a considerable amount of time, depending on the size of the virtual machine. To use VM streaming, you place the virtual machine directory on the Web server without zipping it. VMware recommends that you configure the Web server to support persistent connections (HTTP keep-alive connections).

To make virtual machines available for streaming from a Web server

- 1 If the virtual machine has any snapshots, delete them.
 See [“Delete a Snapshot or a Recording”](#) on page 212.
- 2 (Optional) To improve streaming performance, use Virtual Disk Manager to compress the virtual disk files (.vmdk files) for a virtual machine.
 See the *Virtual Disk Manager User's Guide*, in the Virtual Disk Development Kit.

- 3 Depending on the type of Web server, use the following keep-alive settings:
 - For Apache HTTP Server 1.2 and higher, turn the **KeepAlive** option on, set **MaxKeepAliveRequest** to 2000 to 5000, and set **KeepAliveTimeout** to 2000 to 5000 seconds, depending on server load.
 - For Microsoft Internet Information Services (IIS) 6.0 and higher, set the connection timeout to a value above 300 seconds and load **HTTP Keep-Alives**.
- 4 On proxy servers, set the proxy connection to **Keep-alive**.
- 5 Upload the virtual machine directory to the Web server.

After a virtual machine is placed on a Web server, users can use a URL to stream it and start it with Workstation or VMware Player. See “[Start a Virtual Machine by Using VM Streaming](#)” on page 149.

Sharing Virtual Machines with VMware Player

VMware Player is a free application that opens and plays virtual machines created with other VMware products. On Windows hosts, VMware Player also opens and plays Microsoft Virtual PC and Virtual Server virtual machines and Symantec LiveState Recovery and system images.

VMware Player is included with Workstation 5.5 and higher. “Standalone” Player is also freely available for download at <http://www.vmware.com/products/player/>.

With VMware Player you can create virtual machines and make your VMware virtual machines accessible to colleagues, partners, customers, and clients who do not own other VMware products.

NOTE Use of VMware Player is subject to the VMware Player End User License terms, and VMware does not provide technical support for VMware Player.

Start and Exit VMware Player

VMware Player is included in the Workstation distribution. When you install Workstation, the application file (`vmplayer.exe` on Windows or `vmplayer` on Linux), is stored with the rest of your Workstation program files.

To start and exit VMware Player

- 1 Open VMware Player, either from the graphical user interface (GUI) or from the command line:
 - From the GUI, on Windows, choose **VMware Player** from the **Start > Programs > VMware** menu.
 In a Linux X session, choose **VMware Player** from the corresponding program menu, such as the **System Tools** menu.
 - From the command line, open a command prompt, and enter one of the following commands:
 - On Windows, enter `<path>vmplayer.exe`
 The `<path>` value is the path on your system to the application file.
 - On Linux, enter `vmplayer &`
 - To stream the virtual machine, use the command with the virtual machine URL (for example, `vmplayer http://server.acme.com/myVM.vmx`).
 For more information, see [“Make Virtual Machines Available for Streaming from a Web Server”](#) on page 230.

From the Welcome page, you can:

- Browse to a virtual machine file.
 - Open a recently used virtual machine.
 - Download a virtual appliance from the VMTN (VMware Technology Network) Web site.
- 2 Open a virtual machine.
 For instructions on using and configuring VMware Player, see the online help provided in VMware Player. From the VMware Player menu bar, choose **Help > Help Topics**.

3 To exit VMware Player, do one of the following:

- Shut down the guest operating system in the virtual machine.

VMware Player closes after the guest operating system shuts down.

- In VMware Player, choose **File > Exit** (Windows) or **File > Quit** (Linux).

VMware Player either suspends or powers off the virtual machine, depending on the preference you set for exit behavior in **File > Preferences**.

When you exit VMware Player that is using a streamed virtual machine, you are prompted to save or discard changes. If you discard changes, the directory that was created on your local machine and all the virtual machine data are deleted.

Setting Up Virtual Machines for Use with VMware Player

When you create a virtual machine that you intend to distribute to other users, configure the virtual machine for maximum compatibility with all expected host systems. Because the configuration options for VMware Player are limited, users are limited in their ability to make changes in a virtual machine so that it is compatible with their host systems.

Following are recommendations to help you configure virtual machines for maximum compatibility with VMware Player and with the widest range of host machines:

- Determine which virtual devices are actually required, and do not include any that are not needed or useful for the software you are distributing with the virtual machine and VMware Player. For example, generic SCSI devices are typically not appropriate.
- To connect a physical device to a virtual device, use the **Auto detect** options when configuring the virtual machine. The **Auto detect** options allow the virtual machine to adapt to the user's system, and they work whether the host operating system is Windows or Linux. Users who have no physical device receive a warning message.
- To connect a CD-ROM or floppy to an image file that you ship with the virtual machine, make sure the image file is in the same directory as the virtual machine. This way, a relative path, rather than an absolute path, is used.
- For both a physical CD-ROM and an image, provide two virtual CD-ROM devices in the virtual machine. VMware Player does not provide an option in the user interface to switch a single CD-ROM device between a physical CD-ROM and an image. This also means that if you want to ship multiple images, the user cannot switch between them.

- Choose a reasonable amount of memory to allocate to the virtual machine. If the user's host machine does not have enough physical memory to support the memory allocation, VMware Player cannot power on the virtual machine.
- Install VMware Tools in the virtual machine. VMware Tools significantly improves the user's experience working with the virtual machine.
- Choose a reasonable screen resolution for the guest. A user is likely to find it easier to increase the resolution manually than to deal with a display that exceeds the user's physical screen size.
- Some host operating systems do not support CD-ROMs in non-legacy mode. To ensure that CD-ROMs work properly in virtual machines that you intend to distribute and play on VMware Player, configure CD-ROM devices in legacy mode. See ["Legacy Emulation for DVD and CD Drives"](#) on page 252.
- Select an appropriate setting in **VM > Settings > Options > Snapshots > When powering off**. Set this option to **Just power off** or **Revert to snapshot**. VMware Player does not allow taking snapshots.

The option **Revert to snapshot** is useful if you want to distribute a demo that resets itself to a clean state when powered off.

Using Disks and Disk Drives

This chapter provides information about how to configure virtual hard disk storage to best meet your needs. This chapter includes the following topics:

- [“Virtual Machine Disk Storage”](#) on page 235
- [“Virtual Disk Maintenance Tasks”](#) on page 238
- [“Adding Virtual and Physical Disks to a Virtual Machine”](#) on page 241
- [“Adding DVD/CD-ROM and Floppy Drives to a Virtual Machine”](#) on page 250
- [“Using VMware Virtual Disk Manager”](#) on page 254
- [“Using Dual-Boot Computers with Virtual Machines”](#) on page 254
- [“Legacy Virtual Disks”](#) on page 254

Virtual Machine Disk Storage

Like a physical computer, a VMware Workstation virtual machine stores its operating system, programs, and data files on one or more hard disks. Unlike a physical computer, Workstation provides ways to undo changes to the virtual machine’s hard disk.

The New Virtual Machine wizard creates a virtual machine with one disk drive. Use the virtual machine settings editor (choose **VM > Settings**) to add more disk drives to your virtual machine, to remove disk drives from your virtual machine, and to change certain settings for the existing disk drives.

Benefits of Using Virtual Disks

In most cases, it is best to configure virtual machines to use virtual hard disks rather than physical hard disks. A virtual disk is a file or set of files that appears as a physical disk drive to a guest operating system. The files can be on the host machine or on a remote computer. When you configure a virtual machine with a virtual disk, you can install a new operating system onto the virtual disk without repartitioning a physical disk or rebooting the host.

Portability

A key advantage of virtual disks is their portability. Because the virtual disks are stored as files on the host machine or a remote computer, you can move them easily to a new location on the same computer or to a different computer. You can also use Workstation on a Windows host to create virtual disks, move them to a Linux computer, and use them with Workstation for Linux, and the reverse. See [“Moving a Virtual Machine”](#) on page 223.

Disk Size and Files

Virtual disks can be as large as 950GB (IDE or SCSI). Depending on the size of the virtual disk and the host operating system, Workstation creates one or more files to hold each virtual disk. These files include information such as the operating system, program files, and data files. The virtual disk files have a .vmdk extension.

By default, the actual files that the virtual disk uses start small and grow to their maximum size as needed. The main advantage of this approach is the smaller file size. Smaller files require less storage space and are easier to move to a new location. However, it takes longer to write data to a disk configured in this way.

You can also configure virtual disks so that all of the disk space is allocated when the virtual disk is created. This approach provides enhanced performance and is useful if you are running performance-sensitive applications in the virtual machine.

Regardless of whether you allocate all disk space in advance, you can configure the virtual disk to use a set of files limited to 2GB per file. Use this option if you plan to move the virtual disk to a file system that does not support files larger than 2GB.

Lock Files

A running virtual machine creates lock files to prevent consistency problems on virtual disks. Without locks, multiple virtual machines might read and write to the disk, causing data corruption.

Lock files are created in subdirectories with a `.lck` suffix. The locking subdirectories reside in the same directory as the virtual machine's `.vmdk` files. A locking subdirectory and lock file are created for `.vmdk` files, `.vmx` files, and `.vmem` files.

Since the Workstation 6.0 release, a unified locking method is used on all host operating systems, so files shared between them are fully protected. For example, if one user on a Linux host tries to power on a virtual machine that is already powered on by another user with a Windows host, the lock files prevent the second user from powering on the virtual machine.

When a virtual machine powers off, it removes the locking subdirectories and their lock files. If it cannot remove these locking controls, one or more stale lock files might remain. For example, if the host machine fails before the virtual machine removes its locking controls, stale lock files remain.

When the virtual machine restarts, it scans any locking subdirectories for stale lock files and, when possible, removes them. A lock file is considered stale if both of the following conditions are true:

- The lock file was created on the same host that is now running the virtual machine.
- The process that created the lock is no longer running.

If either of these conditions is not true, a dialog box warns you that the virtual machine cannot be powered on. You can delete the locking directories and their lock files manually.

Locks also protect physical disk partitions. However, the host operating system is not aware of this locking convention and thus does not recognize it. For this reason, VMware recommends that the physical disk for a virtual machine not be installed on the same physical disk as the host operating system.

IDE and SCSI Disk Types

Virtual disks can be set up as IDE disks for any guest operating system. They can be set up as SCSI disks for any guest operating system with a driver for the LSI Logic or BusLogic SCSI adapter available in a Workstation virtual machine. You determine which SCSI adapter to use at the time you create the virtual machine.

NOTE To use SCSI disks in a 32-bit Windows XP virtual machine, download a special SCSI driver from the Downloads page of the VMware Web site. Follow the instructions on the Web site to use the driver with a fresh installation of Windows XP.

A virtual disk of either type can be stored on either type of physical hard disk. That is, the files that make up an IDE or SCSI virtual disk can be stored on an IDE hard disk or a SCSI hard disk. They can also be stored on other types of fast-access storage media.

Physical Disks

In some circumstances, you might need to give your virtual machine direct access to a physical hard drive on the host computer. A physical disk directly accesses an existing local disk or partition. You can use physical disks to run one or more guest operating systems from existing disk partitions.



CAUTION Do not attempt physical disk configurations unless you are an expert user.

Although virtual disks are limited to 950GB, physical disks can be set up on both IDE and SCSI devices of up to 2TB capacity. Booting from an operating system already set up on an existing SCSI disk or partition is currently not supported.



CAUTION Running an operating system natively on the host computer and switching to running it inside a virtual machine is like pulling the hard drive out of one computer and installing it in a second computer with a different motherboard and hardware. The steps you take depend on the operating system you want to use inside the virtual machine. See the VMware technical note *Dual-Boot Computers and Virtual Machines* on the VMware Web site.

You can also create a new virtual machine that uses a physical disk. See [“Using Physical Disks in a Virtual Machine”](#) on page 244. In most cases, however, it is better to use a virtual disk. If you use a physical disk, the .vmdk file stores information about the physical disk or partition that the virtual machine uses.

After you configure a virtual machine to use one or more partitions on a physical disk, do not modify the partition tables by running `fdisk` or a similar utility in the guest operating system.

If you use `fdisk` or a similar utility on the host operating system to modify the partition table of the physical disk, you must re-create the virtual machine's physical disk. All files that were on the physical disk are lost when you modify the partition table.

Virtual Disk Maintenance Tasks

Defragmenting virtual disks can improve performance. Compacting virtual disks reclaims any unused space. Expanding virtual disks adds storage space to your virtual machine.

Defragment Virtual Disks

Like physical disk drives, virtual disks can become fragmented. Defragmenting disks rearranges files, programs, and unused space on the virtual disk so that programs run faster and files open more quickly.

Before you defragment a virtual disk, make sure you have adequate free working space on the host computer. If your virtual disk is contained in a single file, for example, you need free space equal to the size of the virtual disk file. Other virtual disk configurations require less free space.

Make sure the virtual disk is not mapped (on Windows guests) or mounted (on Linux guests). You cannot defragment a virtual disk while it is mapped or mounted.

Defragmenting does not reclaim unused space on a virtual disk. To reclaim unused space, compact the disk. See [“Compact a Virtual Disk”](#) on page 240.

To defragment a virtual disk

- 1 Run a disk defragmentation utility inside the guest operating system.

For example, in a virtual machine with a Windows XP guest operating system, use the Windows XP Disk Defragmenter tool from within the virtual machine.

Defragmenting disks can take considerable time.
- 2 If the virtual disk is “growable” rather than preallocated, defragment it by using the Workstation defragmentation tool:
 - a Select the virtual machine.
 - b Make sure the virtual machine is powered off.
 - c Choose **VM > Settings**.
 - d On the **Hardware** tab, select **Hard Disk**, and do one of the following:
 - On Linux hosts, click **Defragment**.
 - On Windows hosts, click **Utilities** and choose **Defragment**.
 - e When the process is finished, click **OK**.
- 3 Run a disk defragmentation utility on the host computer.

Defragmenting disks can take considerable time.

Compact a Virtual Disk

Compacting a virtual disk reclaims unused space in the virtual disk. If a disk has empty space, this process reduces the amount of space the virtual disk occupies on the host drive.

Make sure the following prerequisites are met:

- The virtual machine is powered off.
- The virtual disk is not mapped (on Windows guests) or mounted (on Linux guests). You cannot compact a virtual disk while it is mapped or mounted.
- The disk space is not preallocated for the virtual hard disk. Use the virtual machine settings editor to view the disk information for this virtual hard disk. If the disk space was preallocated, you cannot compact the disk.
- If the virtual hard disk is an independent disk, it is in persistent mode.

To change the mode, see [“Exclude a Virtual Disk from Snapshots”](#) on page 207 for a description of independent disks.

To compact a virtual disk

- 1 Select **VM > Settings**.
- 2 On the **Hardware** tab, select **Hard Disk** for the virtual hard disk you want to compact.
- 3 Select **Utilities > Compact**.
- 4 Click **OK** after the disk compacting process is complete.

Expand a Virtual Disk

Expanding a virtual disk adds storage space to your virtual machine. However, the added space is not available to your virtual machine immediately. To make the added space available, you must use a disk management tool to increase the size of the existing partition on your virtual disk to match the expanded virtual disk size. The disk management tool you use depends on the operating system of your virtual machine. Many operating systems, including Windows Vista, Windows 7, and some versions of Linux, provide built-in disk management tools that can resize partitions. A number of third-party disk management tools are also available, such as Symantec/Norton PartitionMagic, EASEUS Partition Master, Acronis Disk Director, and the open-source tool GParted.

As an alternative to expanding your virtual disk, you can add a new virtual disk to your virtual machine. See [“Add a New Virtual Disk to a Virtual Machine”](#) on page 242.

Make sure the following prerequisites are met:

- The virtual machine is powered off.
- The virtual disk is not mapped (on Windows guests) or mounted (on Linux guests). You cannot expand a virtual disk while it is mapped or mounted.
- The virtual machine has no snapshots.
- The virtual machine is not a linked clone or the parent of a linked clone.

To determine whether the virtual machine has snapshots, is a linked clone, or is the parent of a linked clone, check the information at the top of the **Summary** tab for the virtual machine.

To expand a virtual disk

- 1 Select **VM > Settings**.
- 2 On the **Hardware** tab, select **Hard Disk** for the virtual hard disk to expand.
- 3 Select **Utilities > Expand**.
- 4 Set the new maximum size for the virtual disk.
- 5 Select **Expand**.
- 6 Click **OK** after the disk expansion process is complete.

After you expand the virtual disk, you must use a disk management tool to increase the disk partition size to match the expanded virtual disk size.

Adding Virtual and Physical Disks to a Virtual Machine

This provides instructions for creating virtual disks, removing disks, adding existing disks to virtual machines, and using physical disks in a virtual machine.

You can connect other SCSI devices to a virtual machine by using the generic SCSI driver for the host operating system. See [“Add a Generic SCSI Device to a Virtual Machine”](#) on page 363.

Add a New Virtual Disk to a Virtual Machine

To increase storage space, you can add a new virtual disk to a virtual machine. Virtual disks are stored as files on the host computer or on a network file server. A virtual IDE drive or SCSI drive can be stored on a physical IDE drive or SCSI drive.

NOTE If you have a Windows NT 4.0 guest with a SCSI virtual disk, you cannot add both an additional SCSI disk and an IDE disk to the configuration.

As an alternative to adding a new virtual disk to your virtual machine, you can expand your existing virtual disk. See [“Expand a Virtual Disk”](#) on page 240.

To add a new virtual disk to a virtual machine

- 1 Select the virtual machine and choose **VM > Settings**.
- 2 On the **Hardware** tab, click **Add** to start the Add Hardware wizard.
- 3 On the Hardware Type page, select **Hard Disk** and click **Next**.
- 4 On the Select a Disk page, select **Create a new virtual disk** and click **Next**.
- 5 On the Select a Disk Type page, choose **IDE** disk or **SCSI**.

See [“IDE and SCSI Disk Types”](#) on page 237.

Workstation 7.0 virtual machines can use up to 4 IDE devices and up to 60 SCSI devices. Any of these devices can be a virtual or physical hard disk or DVD or CD-ROM drive.

- 6 (Optional) To exclude disks from snapshots, in the **Mode** section, select **Independent** for the mode and choose one of the following options:
 - **Persistent** – Disks in persistent mode behave like conventional disks on a physical computer. All data written to a disk in persistent mode is written permanently to the disk.
 - **Nonpersistent** – Changes to disks in nonpersistent mode are discarded when you power off or reset the virtual machine. Nonpersistent mode enables you to restart the virtual machine with a virtual disk in the same state every time. Changes to the disk are written to and read from a redo log file that is deleted when you power off or reset the virtual machine.

See [“Information Captured by Snapshots”](#) on page 205.

- 7 On the Specify Disk Capacity page, set the capacity for the new virtual disk.

You can set a size between 0.1GB and 950GB for a virtual disk. See [“Disk Size and Files”](#) on page 236.

- 8 On the Specify Disk File page, accept the default filename and location or browse to and select a different location and click **Finish**.

The wizard creates the new virtual disk. It appears to your guest operating system as a new, blank hard disk.

- 9 In the virtual machine settings editor, click **OK**.
- 10 Use the guest operating system tools to partition and format the new drive for use.

Add an Existing Virtual Disk to a Virtual Machine

You can reconnect an existing virtual disk that was removed from a virtual machine.

Workstation 7.0 virtual machines can use up to 4 IDE devices and up to 60 SCSI devices. Any of these devices can be a virtual or physical hard disk or DVD or CD-ROM drive.

To map an existing virtual disk drive to a Windows host machine, rather than adding it to a virtual machine, see [“Using a Mapped Drive”](#) on page 198.

To add an existing virtual disk to a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, click **Add** to start the Add Hardware wizard.
- 4 On the Hardware Type page, select **Hard Disk** and click **Next**.
- 5 On the Select a Disk page, select **Use an existing virtual disk** and click **Next**.
- 6 On the Select an Existing Disk page, specify the path name and filename for the existing disk file and click **Finish**.
- 7 In the virtual machine settings editor, click **OK**.

Remove a Virtual Disk from a Virtual Machine

Removing a virtual disk disconnects it from a virtual machine. Removing the virtual disk does not delete files from the host file system.

After you remove the disk from the virtual machine, you can map or mount it to a host and copy data from the guest to the host without powering on the virtual machine or starting Workstation.

To remove a virtual disk from a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select a virtual disk and click **Remove**.

After you remove the disk from the virtual machine, you can do either of the following:

- Map the disk to the host. See [“Using a Mapped Drive”](#) on page 198.
- Add the disk to another virtual machine. See [“Add an Existing Virtual Disk to a Virtual Machine”](#) on page 243.

Using Physical Disks in a Virtual Machine

You can install a guest operating system directly on an unused physical disk or unused partition. However, an operating system installed in this setting probably cannot boot outside of the virtual machine, even though the data is available to the host.



CAUTION Do not use a physical disk to share files between host and guest operating systems. It is not safe to make the same partition visible to both host and guest. You can cause data corruption if you do this. To share files between host and guest operating systems, use shared folders. See [“Using Shared Folders”](#) on page 190.

For information about using an operating system that can also boot outside of the virtual machine, see the VMware *Dual-Boot Computers and Virtual Machines* technical note on the VMware Web site.

Physical disks are an advanced feature. Do not configure them unless you are an expert user. To use a physical disk in a virtual machine, you can add the physical disk to an existing virtual machine, or create a virtual machine and specify which physical disk the virtual machine uses.

NOTE Using a physical disk rather than a virtual disk is not an appropriate option for a virtual machine you intend to distribute as an ACE instance.

Prerequisites for Using a Physical Disk

Before you run the New Virtual Machine wizard or use the virtual machine settings editor to add a physical (raw) disk, perform the following tasks:

- Because the virtual machine and guest operating system access a physical disk partition while the host continues to run its operating system, verify that the partition is not mounted by the host or in use by another virtual machine.

Corruption is possible if you allow the virtual machine to modify a partition that is simultaneously mounted on the host operating system.
- Check the guest operating system documentation regarding the type of partition on which the operating system can be installed.
 - On Windows Vista and Windows 7 hosts, you cannot use the system partition or the physical disk that contains it in a virtual machine.
 - DOS, Windows 95, and Windows 98 operating systems must be installed on the first primary partition.
 - Other operating systems, such as Linux, can be installed on a primary or an extended partition on any part of the drive.
- Make sure the physical partition or disk does not have data you need in the future. If it does, back up the data.
- On Windows hosts:
 - If you use a Windows host's IDE disk in a physical disk configuration, make sure it is not configured as the slave on the secondary IDE channel if the master on that channel is a CD-ROM drive.
 - If your host is running Windows XP or Windows Server 2003, do not use a dynamic disk as a physical disk in a virtual machine. Use the disk management tool to check the disk type and change a dynamic disk to a basic disk, which destroys all data. See [“Change a Windows Disk Type from Dynamic to Basic”](#) on page 246.
- On Linux hosts, set the device group membership or device ownership appropriately. See [“Set Permissions on Linux Hosts”](#) on page 247.

After you determine that the physical disk meets these prerequisites, use either of the following strategies to use the physical disk in a virtual machine:

- [“Create a Virtual Machine That Uses a Physical Disk”](#) on page 247
- [“Add a Physical Disk to an Existing Virtual Machine”](#) on page 249

Change a Windows Disk Type from Dynamic to Basic

To use a hard disk in a virtual machine whose host is running Windows XP or Windows Server 2003, the virtual machine must use a basic disk.

To change a Windows disk type from dynamic to basic

- 1 On the host, choose **Start > Settings > Control Panel > Administrative Tools > Computer Management > Disk Management**.

The disk management tool opens.

- 2 Delete all logical volumes on the disk.

This action destroys all data on the disk.

- 3 Right-click the disk icon and select **Revert to Basic Disk**.

- 4 Partition the disk.

Unmap a Partition That Is Mapped to a Windows Server 2003 or Windows XP Host

Corruption can occur if you allow the virtual machine to modify a physical disk partition that is simultaneously used as a mapped drive on the host.

To unmap a partition that is mapped to a Windows Server 2003 or Windows XP host

- 1 Choose **Start > Settings > Control Panel > Administrative Tools > Computer Management > Storage > Disk Management**.
- 2 Select a partition and choose **Action > All Tasks > Change Drive Letter and Paths**.
- 3 Click **Remove**.

Unmap a Partition That Is Mapped to a Windows Vista Host

Corruption can occur if you allow the virtual machine to modify a physical disk partition that is simultaneously used as a mapped drive on the host.

To unmap a partition that is mapped to a Windows Vista host

- 1 Select **Start > Control Panel (Classic View) > Administrative Tools > Computer Management > Storage > Disk Management**.
- 2 Right-click a partition and choose **Change Drive Letter and Paths**.
- 3 Click **Remove** and **OK**.

Unmap a Partition That Is Mapped to a Windows 7 Host

Corruption can occur if you allow the virtual machine to modify a physical disk partition that is simultaneously used as a mapped drive on the host.

To unmap a partition that is mapped to a Windows 7 host

- 1 Select **Start > Control Panel**.
- 2 In the menu bar, click the arrow next to **Control Panel**.
- 3 From the drop-down menu, select **All Control Panel Items > Administrative Tools > Computer Management > Storage > Disk Management(Local)**.
- 4 Right-click a partition and choose **Change Drive Letter and Paths**.
- 5 Click **Remove** and **OK**.

Set Permissions on Linux Hosts

If permissions are set correctly, the physical disk configuration files in Workstation control access. This reliability provides boot managers access to configuration files and other files they might need to boot operating systems. For example, LILO needs to read `/boot` on a Linux partition to boot a non-Linux operating system that might be on another drive.

To set permissions on Linux hosts

- 1 Make sure the master physical disk device or devices are readable and writable by the user who runs Workstation.
 - Physical devices, such as `/dev/hda` (IDE physical disk) and `/dev/sdb` (SCSI physical disk), belong to group-id `disk` on most distributions. If this is the case, you can add VMware Workstation users to the `disk` group.
 - Another option is to change the owner of the device. Consider all the security issues involved in this option.
- 2 Grant VMware Workstation users access to all `/dev/hd[abcd]` physical devices that contain operating systems or boot managers.

Create a Virtual Machine That Uses a Physical Disk

Use the New Virtual Machine wizard to create a new virtual machine that uses a physical disk rather than adding a physical disk to an existing virtual machine.

Before you begin, complete the tasks described in [“Prerequisites for Using a Physical Disk”](#) on page 245.

To create a virtual machine that uses a physical disk

- 1 Use the Custom setup in the New Virtual Machine wizard to create a virtual machine that uses a physical disk.
- 2 On the Select a Disk page of the wizard, select **Use a physical disk**, and choose to use individual partitions or the entire disk.

If you use individual partitions, only the partitions you select are accessible to the virtual machine. The other partitions might be visible to the guest operating system, but you cannot mount, access, or format them.

- 3 (Optional) To specify a device node for the virtual disk or exclude disks from snapshots, do the following:
 - a Select the virtual machine and choose **VM > Settings**.
 - b On the **Hardware** tab, select the physical disk and click **Advanced**.
 - c To change the device node, select from the **Virtual device node** list.
 - d To exclude disks from snapshots, select **Independent** for the mode and choose one of the following options:
 - **Persistent** – Disks in persistent mode behave like conventional disks on a physical computer. All data written to a disk in persistent mode is written permanently to the disk.
 - **Nonpersistent** – Changes to disks in nonpersistent mode are discarded when you power off or reset the virtual machine. Nonpersistent mode enables you to restart the virtual machine with a virtual disk in the same state every time. Changes to the disk are written to and read from a redo log file that is deleted when you power off or reset the virtual machine.

See [“Information Captured by Snapshots”](#) on page 205.

- 4 Install the guest operating system on the physical disk.

For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link.

Add a Physical Disk to an Existing Virtual Machine

Use the virtual machine settings editor, rather than the New Virtual Machine wizard, to add a physical disk to an existing virtual machine.

Before you begin, complete the tasks described in [“Prerequisites for Using a Physical Disk”](#) on page 245.



CAUTION After you add a virtual machine disk by using one or more partitions on a physical disk, never modify the partition tables by running `fdisk` or a similar utility in the guest operating system. If you do so, you must re-create the virtual machine's physical disk.

To add a physical disk to an existing virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, click **Add**.
- 5 On the Hardware Type page, select **Hard Disk** and click **Next**.
- 6 On the Select a Disk page, select **Use a physical disk** and click **Next**.
- 7 If a warning appears, click **OK**.
- 8 On the Select a Physical Disk page, do the following:
 - a Choose the physical hard disk to use from the drop-down list.
Workstation supports physical disks up to 2TB.
 - b Select whether you want to use the entire disk or only individual partitions on the disk and click **Next**.
- 9 If you selected **Use individual partitions**, select the partitions you want to use in the virtual machine and click **Next**.
The virtual machine can access only the partitions you select. The guest operating system might be able to detect other partitions, but you cannot mount, access, or format them.
- 10 On the Specify Disk File page, accept the default filename and location or browse to a different location.

- 11 (Optional) To specify a device node for the virtual disk or exclude disks from snapshots, do the following:
 - a On the Specify Disk File page, click **Advanced**.
 - b To change the device node, select from the **Virtual device node** list.
 - c To exclude disks from snapshots, select **Independent** for the mode and choose one of the following options:
 - **Persistent** – Disks in persistent mode behave like conventional disks on a physical computer. All data written to a disk in persistent mode is written permanently to the disk.
 - **Nonpersistent** – Changes to disks in nonpersistent mode are discarded when you power off or reset the virtual machine. Nonpersistent mode enables you to restart the virtual machine with a virtual disk in the same state every time. Changes to the disk are written to and read from a redo log file that is deleted when you power off or reset the virtual machine.

See [“Information Captured by Snapshots”](#) on page 205.
- 12 Click **Finish**.
- 13 Use the guest operating system's tools to format any partitions on the physical disk that are not formatted for your guest operating system.

Adding DVD/CD-ROM and Floppy Drives to a Virtual Machine

Workstation 7.0 virtual machines can use up to 4 IDE devices and up to 60 SCSI devices. Any of these devices can be a virtual or physical hard disk or DVD or CD-ROM drive. By default, floppy drive is not connected when the virtual machine powers on.

A virtual machine can read data from a DVD disc. Workstation does not support playing DVD movies in a virtual machine. You might be able to play a movie if you use a DVD player application that does not require video overlay support in the video card.

Add DVD or CD Drives to a Virtual Machine

You can add one or more DVD or CD drives to your virtual machine. You can connect the virtual DVD or CD drive to a physical drive on the host machine or to an ISO image file.

You can configure the virtual DVD or CD drive as either IDE or SCSI regardless of the type of physical drive you connect it to. For example, if your host computer has an IDE CD drive, you can set up the virtual machine drive as either SCSI or IDE and connect it to the host drive. The same is true if the physical drive on the host is a SCSI drive.

To add a DVD or CD drive to a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, click **Add**.
- 4 On the Hardware Type page, select **DVD/CD-ROM Drive** and click **Next**.
- 5 Make a selection on the Select a Drive Connection page and click **Next**.
- 6 (Optional) If you select **Use physical drive**:
 - a Choose a drive from the drop-down list or choose **Auto detect**.
 - b To avoid connecting the CD drive when the virtual machine starts, deselect **Connect at power on**.
 - c To specify which device node the drive uses in the virtual machine, click **Advanced**.

Select **Legacy emulation** only if you experienced problems using normal mode. See [“Legacy Emulation for DVD and CD Drives”](#) on page 252.
 - d Click **Finish**.
- 7 (Optional) If you select **Use ISO image**:
 - a Enter the path and filename for the image file or browse to the file.
 - b To avoid connecting the CD drive when the virtual machine starts, deselect **Connect at power on**.
 - c To specify which device node the drive uses in the virtual machine, click **Advanced**.
 - d Click **Finish**.

The drive is set up initially so that it appears as an IDE drive to the guest operating system.

- 8 (Optional) To make the drive appear to the guest operating system as a SCSI drive, click the entry for that drive in the virtual machine settings editor and edit the settings in the panel on the right.

Legacy Emulation for DVD and CD Drives

In normal mode (that is, not legacy emulation mode), the guest operating system communicates directly with the CD or DVD drive. This direct communication enables you to read multisession CDs, perform digital audio extraction, view videos, and use CD and DVD writers to burn discs.

Legacy emulation mode enables you to read only from data discs in the DVD or CD drive. It does not provide the other capabilities of normal mode. Use legacy emulation mode to work around direct communication problems between a guest operating system and a DVD or CD drive.

Use the virtual machine settings editor (**VM > Settings > Advanced**) to set the **Legacy emulation** option for DVD and CD drives attached to the virtual machine:

- On Windows hosts, this option is deselected by default.
- On Linux hosts with IDE drives, the default setting depends on whether the `ide-scsi` module is loaded in your kernel. The `ide-scsi` module must be loaded, or you must be using a physical SCSI drive to connect directly to the DVD or CD drive.

If you run more than one virtual machine at a time, and if their CD drives are in legacy emulation mode, start the virtual machines with their CD drives disconnected. This ensures that multiple virtual machines are not connected to the CD drive at the same time.

Add a Floppy Drive to a Virtual Machine

You can add up to two floppy drives to a virtual machine. A virtual floppy drive can connect to a physical floppy drive on the host computer, to an existing floppy image file, or to a blank floppy image file. By default, floppy drive is not connected when the virtual machine powers on.

To add a floppy drive to a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, click **Add**.
- 5 On the Hardware Type page, select **Floppy Drive** and click **Next**.
- 6 Follow the instructions to complete the wizard.

- 7 In the **Device Status** section, select the **Connect at power on** option to connect the floppy drive when the virtual machine powers on.
- 8 (Optional) If you are adding a second floppy drive to the virtual machine, enable this second floppy drive in the virtual machine BIOS, as follows:
 - a Select the virtual machine and choose **VM > Power > Power On to BIOS**.
 - b On the main screen, choose **Legacy Diskette B:** and use the plus (+) and minus (-) keys on the numerical keypad to select the type of floppy drive to use.
 - c Press F10 to save the settings.

Connect a CD-ROM, DVD, or Floppy Drive to an Image File

You can connect an existing virtual CD-ROM, DVD to an ISO image file or floppy drive to a floppy image (.flp or .img) file rather than the physical drive on the host. For example, an ISO image file resembles a CD-ROM to your guest operating system and appears as a CD-ROM in Windows Explorer.

In some host configurations, the virtual machine cannot boot from the installation CD-ROM. To avoid that problem, create an ISO image file from the installation CD-ROM.

To connect a CD-ROM, DVD, or floppy drive to an image file

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select a DVD, CD-ROM, or floppy drive.
- 4 Do one of the following:
 - For a DVD or CD-ROM drive, select **Use ISO Image** and specify the path name and filename.
 - For a floppy drive:
 - If the file already exists, select **Use floppy Image** and specify the path name and filename.
 - To create an image file, click **Create**, browse to the directory where you plan to store the floppy image file, supply a filename, and click **Save** (on Windows hosts) or **Open** (on Linux hosts).
- 5 (Optional) To make the file read only, select the **Read Only** check box.
- 6 Click **OK**.

Using VMware Virtual Disk Manager

VMware Virtual Disk Manager is a Workstation utility that allows you to create, manage, and modify virtual disk files from the command line or in scripts.

You can enlarge a virtual disk so that its maximum capacity is larger than it was when you created it. This is useful if you need more disk space in a given virtual machine, but do not want to add another virtual disk or use ghosting software to transfer the data on a virtual disk to a larger virtual disk. You cannot do this with physical hard drives.

You can also change disk types. When you create a virtual machine, you specify how disk space is allocated, as follows:

- All space for the virtual disk is allocated in advance. This corresponds to the preallocated disk type for Virtual Disk Manager.
- Space allocated for the virtual disk begins small and grows as needed. This corresponds to the growable disk type for Virtual Disk Manager.

If you allocate all the disk space for a virtual disk but later need to reclaim some hard disk space on the host, you can convert the preallocated virtual disk into a growable disk. The new virtual disk is still large enough to contain all the data in the original virtual disk.

You can also change whether the virtual disk is stored in a single file or split into 2GB files.

These features and the ability to use scripting to automate management of virtual disks were added to Workstation in version 5.0. See the VMware technical note about using Virtual Disk Manager.

Using Dual-Boot Computers with Virtual Machines

Some users install Workstation on a dual-boot or multiple-boot computer so that they can run one or more of the existing operating systems in a virtual machine. For more information about using dual-boot computers with Workstation, see the VMware *Dual-Boot Computers and Virtual Machines* technical note on the VMware Web site.

Legacy Virtual Disks

You have several options for using Workstation 7.0 in a mixed environment with virtual machines that were created with earlier versions of Workstation or created with other VMware products.

For compatibility information, see the *VMware Virtual Machine Mobility Planning Guide*.

You can use Workstation 7.0 to power on virtual machines created with older versions of Workstation or other VMware products. However, many new features of Workstation are not available in older virtual machines. To upgrade your virtual machines to Workstation 7.0, see [“Change the Version of a Virtual Machine”](#) on page 94.

If you decide not to upgrade a virtual machine, VMware recommends that you upgrade VMware Tools to the latest version. See [“VMware Tools Update Process”](#) on page 115. Do not remove the older version of VMware Tools before installing the new version.

You can also use Workstation to create a version 4, 5.x, or 6.x virtual machine. See [“Use the New Virtual Machine Wizard”](#) on page 89. Use the Custom setup in the wizard.

NOTE If you have Workstation 2 or 3 virtual machines that you want to use with Workstation 7.0, upgrade the virtual machines to at least Workstation version 4 before you attempt to power them on with Workstation 7.0.

Recording and Replaying Virtual Machine Activity

12

The record/replay feature allows you to record all of a Workstation 5.x, 6.x, or 7.0 virtual machine's activity over a period of time. This chapter includes the following topics:

- [“Uses of the Record/Replay Feature”](#) on page 257
- [“Physical and Virtual Hardware Requirements”](#) on page 258
- [“Configure Record/Replay for a Virtual Machine”](#) on page 259
- [“Create a Recording”](#) on page 264
- [“Replay a Recording”](#) on page 265
- [“Using an Execution Trace File of a Recording”](#) on page 266
- [“Maintenance Tasks for Using Recordings”](#) on page 268

Uses of the Record/Replay Feature

Unlike Workstation's movie-capture feature, the record/replay feature records all the processor instructions of the virtual machine throughout the time of the recording. This feature helps software developers and QA engineers to record a bug and attach a debugger while replaying the recording.

After you enable the record/replay feature for a virtual machine, click the **Record** button in the toolbar to start the recording and click **Stop** to end the recording. You can make multiple recordings and use the snapshot manager to name, delete, and play them. While you are making a recording you can insert replay snapshots to return to events and replay them. To mark a point of interest in the recording you can add a marker. You can also make an execution trace file of a recording, to record events that occur during the recording.

Playing a recording is similar to going to a snapshot. When you play a recording, you discard the current state of the virtual machine and go to the recording. At any time when the recording is playing, you can click the **Go Live** button and resume interacting with the guest operating system at the state the virtual machine is in when you click **Go Live**.

NOTE Virtual machine recordings are not interchangeable between different versions of Workstation. Recordings created using earlier Workstation or beta releases cannot be replayed using the current version of Workstation.

Physical and Virtual Hardware Requirements

Following is a list of requirements for and limitations of this feature:

- **Host CPUs** – Record/replay support is limited to certain processors on the host. If you use the record/replay feature on a host computer that does not have the supported processor, when you enable the record/replay feature and try to create a recording, a message appears, informing you that recording is not supported on your processor.

Supported processors include Intel Pentium 4, Intel Core 2 and later versions, Next-Generation Intel Microarchitecture - Nehalem, and Penryn/Harpertown, and AMD Barcelona and later versions. Other processors might operate more slowly during recording and replaying.

NOTE If the record/replay feature is unstable on your P4 system, disable hyperthreading and logical processors in the BIOS.

When these features are enabled in BIOS, other applications using performance counters may interfere with the virtual machine running in the record/replay mode. An example of an application using performance counters is the performance profiling tool.

To ensure that the processor configuration is compatible with record/replay, you must configure your virtual machine. See [“Configure Record/Replay for a Virtual Machine”](#) on page 259.

- **Virtual machine version** – Only Workstation 5.x, 6.x, and 7.0 virtual machines can be recorded.

- **Supported operating systems** – You can use the record/replay feature for the following guest operating systems:
 - Windows 2000, XP, 2003, Vista, 7
 - Red Hat Enterprise Linux 3 and 4
 - SUSE Linux 9.3 and 10.x
 - 64-bit versions of the these guest operating systems might not work with some old host CPUs.
 - **Unsupported virtual hardware** – SMP and paravirtualization on VMI are not supported with record/replay.
 - **Disk space** – How much disk space a recording uses depends on the type of activity that occurs on the virtual machine and the duration of the recording session. By default, a screenshot is created every 15 seconds. Therefore, assume that you will need several megabytes of disk space for one minute of recording.
-
- NOTE** Having a number of virtual machines with high-resolution display settings open on the screen consumes more disk space.
-
- **Disk mode** – You cannot use the record/replay feature if the virtual machine's virtual hard disk is set to independent mode. Recording virtual machine activity requires writing data about the disk to a continual snapshot. Use the virtual machine settings editor to change the disk mode (select **VM > Settings > Hardware > Hard Disk > Advanced**).

Configure Record/Replay for a Virtual Machine

Make sure that the virtual machine meets the requirements listed in [“Physical and Virtual Hardware Requirements”](#) on page 258.

To configure record/replay for a virtual machine

- 1 Make sure the virtual machine is powered off.
- 2 Select the virtual machine and select **VM > Settings**.
- 3 To set processor configuration for record/replay, select **VM > Settings > Hardware > Processors** and select **1** processor with **1** core per processor.

- 4 In the **Preferred mode** drop-down menu, select **Automatic** or **Automatic with Replay** to let Workstation select the execution mode based on the guest operating system and the host CPU.

Automatic with Replay refers to the execution record/replay feature. For many combinations of CPU and guest operating system, you can select **Automatic** and still use the record/replay feature. If not, an error message directs you to select **Automatic with Replay**.

Selecting **Automatic** or **Automatic with Replay** means that Workstation selects one of the following:

- **Binary translation** – Uses a mix of directly executing guest code and binary translation to run the guest. This option uses shadow page tables to map guest memory.
- **Intel VT-x or AMD-V** – Uses hardware extensions to run and isolate guest code. This option also uses shadow page tables to map guest memory.
- **Intel VT-x/EPT or AMD-V/RVI** – Uses hardware extensions to run and isolate guest code. This option uses hardware paging support to map guest memory.

The choice depends on which mode provides the best performance for the selected guest operating system on the host's CPU.

- 5 Click the **Options** tab and select **Replay**.
- 6 (Optional) On the **Replay** settings panel as a safety precaution, use the **When Recording** controls to limit how much disk space the recording can use.
 - Setting the Maximum disk space to **Unlimited** uses much more disk space than setting it to **2GB**.
 - Selecting **Save the last** sets the duration of the time to save the recording.
 - Setting **Snapshot frequency** to **5 min** uses much more disk space than setting it to **Never**.
- 7 (Optional) Select the **Enable VAssert (experimental)** check box to use VMware VAssert to debug applications.

VAssert enables developers and support engineers to take advantage of traditional assert and logging capabilities to debug errors in replay logs. The asserts appear only during replay of a recording.

- 8 (Optional) Select the **Enable Visual Studio debugger (experimental)** check box to use the Integrated Virtual Debugger for Visual Studio on Windows only.

Developers can use record/replay to record an execution of an application and debug the recorded form of the application. Recorded bugs can be replayed repeatedly and exhibit the same behavior.

- 9 Click **OK**.

Record Control Dialog Box Features

On Windows, a record control dialog box appears when you click the **Record** button in the toolbar. On Linux, the record options are located in the toolbar.

NOTE On Linux, you cannot add markers to a recording.

- **Stop** – Stops the recording that is in progress.
- **Add Snapshot** – Takes a replay snapshot at the current location within the recording. You can use this snapshot during replay to skip ahead in a recording.
- **Add Marker** – Adds a marker in the recording without taking a replay snapshot. You can add and label a marker as a reminder of a point of interest in the recording.
- **Minimize** – On Windows and Linux hosts, the (-) button minimizes the record control dialog box to the lower-left side of the status bar. The minimized mode allows you to work on the virtual machine and use the controls in the status bar to either stop a recording or add a marker.

NOTE You cannot close the record control dialog box.

- **Maximum disk space** – Shows the maximum disk space quota allocated for the recording.
- **Saving the last** – Displays the approximate duration of time where the end of a recording is saved. For example, if you are saving the last 30 minutes of the recording, as the recording continues, only the last 30 minutes of the virtual machine activity is saved at any given time.
- **Snapshot Frequency** – Shows the frequency when an automatic replay snapshot is added to the recording.
- **Next auto snapshot** – Displays when the next automatic replay snapshot is going to be added to the recording.
- **Last snapshot** – Indicates when the last replay snapshot was added to the recording.

Replay Control Dialog Box Features

The replay control dialog box appears when you replay a recording.

NOTE On Linux, you cannot add markers to a recording.

Figure 12-1. Windows Replay Control Dialog Box





Figure 12-2. Linux Replay Control Dialog Box



The replay control dialog box contains the following buttons:

- **Play/Pause** – Plays the last recording you made for the selected virtual machine. If the virtual machine is powered off, the recording is resumed as if it had been suspended. If you click the same button once, the replay is paused. To resume replay, click the button again.
- **Go Live** – Stops the replay that is in progress and reverts to the current state of the virtual machine.
- **Add Snapshot** – Takes a replay snapshot at the current location within the recording. You can use this snapshot during replay to skip ahead in a recording.

- **Add Marker** – Adds a marker in the recording without taking a replay snapshot. You can add and label a marker as a reminder of a point of interest in the recording.
- **Go to Beginning** – Returns to the beginning of the recording.
- **Go to Previous Snapshot** – Replays the recording to the point where the previous replay snapshot is located and pauses the playback.
- **Go to Next Snapshot** – Replays the recording to the point where the next replay snapshot is located and pauses the playback.
- **Go to This Snapshot** – Replays the recording from the selected replay snapshot. Right-click the replay snapshot icon to use this option.
- **Rename This Snapshot** – Renames the selected replay snapshot. Right-click the replay snapshot icon to use this option.
- **Delete Up to This Snapshot** – Deletes the portion of the recording up to the selected replay snapshot. All the markers and replay snapshots up to the selected replay snapshot are deleted and cannot be recovered. Right-click the replay snapshot icon to use this option.
- **Delete After This Snapshot** – Deletes the remaining portion of the recording after the selected replay snapshot. All the markers and replay snapshots after the selected replay snapshot are deleted and cannot be recovered. Right-click the replay snapshot icon to use this option.
- **Rename This Marker** – Renames the selected marker. Right-click the marker icon to use this option.
- **Delete This Marker** – Deletes the selected marker. Right-click the marker icon to use this option.
- **Current Replay Position Slider** – Allows you to preview a replay. You can drag the slider to the nearest previous marker or replay snapshot and start replaying. On Linux, the auto-scroll function of the zoomed in portion is enabled. The **Current Replay Position Slider** is a red arrow located in the progress timeline.
- **Zoom control** – Controls the zoom in and out function during replay.
- **Minimize** – The (-) button minimizes the dialog box to the bottom left-hand side of the status bar. The minimized mode allows you to view the recording in the virtual machine and use the controls in the status bar. The progress indicator in the status bar shows the timeline of the recording.

NOTE You cannot close the replay control dialog box.

- **Replay speed control** – Controls the replay speed of a recording. On Windows, click the right button to increase the replay speed to the maximum. Click the left button to decrease the replay speed to normal. On Linux, click button to toggle between speeds.

NOTE The speed of a playback depends on the host activity and workload of the guest.

Create a Recording

While creating a recording you cannot pause or reverse it. For more information about enabling record/replay see [“Configure Record/Replay for a Virtual Machine”](#) on page 259.

Before you begin, verify the screen resolution settings. The existing screen resolution is used in the virtual machine while replaying a recording. The resolution cannot be changed during replay.

NOTE If you hot remove a virtual device from the guest by using the Windows **Safely Remove Hardware** option while creating a recording, the recording terminates unexpectedly.

To create a recording

- 1 Power on the virtual machine.
- 2 To begin recording select **VM > Replay > Record**.

A recording-specific snapshot is taken, and the recording dialog box indicates that recording is in progress.

If the **Record** command is unavailable, the feature might not be enabled or the hard disk might be set to independent mode.
- 3 (Optional) To add a replay snapshot during recording, click **Add Snapshot** and label the replay snapshot in the Add Replay Snapshot dialog box.

Taking a snapshot pauses the execution of the virtual machine for a few seconds. Aside from the replay snapshots you add, replay snapshots are automatically added according to the frequency you set by using the virtual machine settings editor.
- 4 (Optional) To add a marker during recording, click **Add Marker** and label the marker in the Add Marker dialog box.

Adding markers does not pause the execution of the virtual machine.

- 5 To stop recording, click the **Stop** button in the recording dialog box or in the toolbar.

(Optional) On Windows, while making a recording, you can use the minimized record control to stop a recording, add a replay snapshot, or add a marker.
- 6 Complete the dialog box that appears and click **Save**.
- 7 To change the name of the recording, add or change the description, or delete the recording, select **VM > Snapshot > Snapshot Manager**.

Replay a Recording

If you change from windowed mode to full screen mode during replay, the auto-fit feature does not work.

To replay a recording

- 1 Select the virtual machine.
- 2 If it is powered on and you do not want to lose the current state of the virtual machine, take a snapshot of it.

For instructions, see [“Take a Snapshot”](#) on page 209.

- 3 To play the latest recording of the virtual machine select **VM > Replay > Replay <name_of_recording>**.

On Windows, while replaying a recording you can use the controls in the minimized replay control.

- 4 To play an earlier recording, use the snapshot manager, as follows:
 - a Select **VM > Snapshot > Snapshot Manager**.
 - b Select the recording snapshot to play and click **Replay**.

If you stop the recording before it is finished replaying by clicking the **Go Live** button and replay the recording again, the recording starts from the beginning, not from the point where you clicked **Go Live**.

A snapshot of a recording is shown in [Table 9-1, “Snapshot Manager Icons,”](#) on page 208.

- 5 In the dialog box that appears, confirm that you want to start replaying the recording.
- 6 To suspend the replay, click the **Pause** button in the replay control dialog box. The button toggles to a **Play** button so that you can click it again to resume playing the recording.

- 7 (Optional) To make a trace file of events that occurred during recording, see [“Using an Execution Trace File of a Recording”](#) on page 266.
- 8 (Optional) To stop replaying the recording before it finishes playing, click the **Go Live** button to stop the replay and resume interacting with the virtual machine.

Browse a Recording

The length of a recording can vary from a few minutes to several hours. When the recording is several hours long, use the position slider to access the recording at random intervals. On Windows and Linux hosts, zoom in and out of the recording by using the zoom controls. Use the zoomed in auto-scroll function to browse the recording.

To browse a recording

- 1 Open a recording.
- 2 Drag the slider from the current position in the recording to another specific position.

The new slider position must have a 16 second interval from the previous position.
- 3 (Optional) In the confirmation dialog box, select the check box **Never show this again**.

The dialog box stops reappearing every time you browse a recording.
- 4 Click **OK**.

The virtual machine reverts to the nearest previous replay snapshot and starts replaying until it reaches the target location. During the replay, the slider remains at the same point, and the remaining playback time appears in red above the slider. For more information, see [Figure 12-1](#). When the recording reaches the slider's position, the recording is paused.

Using an Execution Trace File of a Recording

Trace files are detailed logs that are helpful for debugging. When you make an execution trace file of a recording, you can view all the events that occurred during the recording.

When a recording is replayed, instruction tracing can be turned on and off by pressing the **t** key with the mouse grabbed by the guest operating system windows.

Enable Execution Tracing for a Recording

Execution tracing is disabled by default. To create execution trace files for a recording, you must enable it.

Before you begin, power off the virtual machine.

To enable execution tracing

- 1 Open the preferences file with a text editor.

This file is located in:

- On Windows Server 2003 and Windows XP hosts, `C:\Documents and Settings\<username>\Application Data\VMware`
- On Windows Vista and Windows 7 hosts, `%USERPROFILE%\AppData\Roaming\VMware\`
- On Linux hosts, `<homedir>/<username>/.vmware/`

Here `<homedir>` is the home directory of the user who is logged in at the time the virtual machine is created.

- 2 To write trace files to the `vmware.log`, add the following line to the preferences file.

```
pref.replay.enableTrace = "TRUE"
```

- 3 Select **VM > Settings**.
- 4 Under the **Options** tab, select **Advanced**.
- 5 Under the **Settings** option, set **Gather debugging information** to **Full** from the drop-down menu.
- 6 Click **OK**.
- 7 (Optional) To write trace files to a separate `.gz` file, add the following line to the `vmx` file.

```
replay.nogzTrace = false
```

Create an Execution Trace File of a Recording

After enabling execution tracing, when you create an execution file of a recording, the **Trace** button appears in the replay dialog box.

To create an execution trace file of a recording

- 1 Replay a recording.
- 2 In the replay dialog box, click **Trace** to start the trace file.

The play back speed of the recording slows considerably while the trace file is created.

- 3 To end the trace file, click **Trace** again.

Otherwise, the trace file ends when the recording finishes replaying.

Maintenance Tasks for Using Recordings

Depending on the length of a recording, the number of its periodic screenshots, and the number of recordings, the disk space used for the record/replay feature can be large. When you create recordings, Workstation goes into full debugging mode.

Delete a Recording

To free disk space, delete recordings that you do not need.

To delete a recording

- 1 Select the virtual machine.
- 2 Select **VM > Snapshot > Snapshot Manager**.
- 3 In the Snapshot Manager window, select the recording to delete.
- 4 Right-click and select **Delete Recording and Children**.

If you select a recording and click the **Delete** button, the selected recording is removed and the corresponding snapshots in the recording remain intact.

Disable Periodic Screenshots

If the recording session lasts for a long time, a significant number of screenshots are automatically created in the virtual machine directory. Even when periodic screenshots are disabled, one screenshot is taken at the end of every recording.

To disable periodic screenshots

- 1 Add the following line to the configuration (.vmx) file for the virtual machine where X denotes the interval of screenshots taken in seconds. The default value for X is 15 seconds.

```
snapshot.periodicScreenshots = "X"
```

- 2 To disable periodic screenshots, change the value of X to 0.
- 3 Save and close the configuration file.

Configuring Teams

This chapter describes what virtual machine teams are used for, how to create them, and how to configure them. This chapter includes the following topics:

- [“Benefits of Using Teams”](#) on page 271
- [“Managing Teams”](#) on page 272
- [“Summary and Console Views for Teams and Their Virtual Machines”](#) on page 276
- [“Managing the Members of a Team”](#) on page 276
- [“Power Operations for Teams and Their Members”](#) on page 279
- [“Working with Team Networks”](#) on page 280
- [“Cloning and Taking Snapshots of Team Virtual Machines”](#) on page 283

Benefits of Using Teams

Workstation teams allow you to set up a virtual computer lab on one host computer. Use a team to power on multiple associated virtual machines with a single click.

You can use teams to do the following:

- **Virtualize-multitier environments** – Start separate client, server, and database virtual machines with one click. Configure startup delay times so clients do not submit queries before the server is ready.

Setting a startup delay between the booting of virtual machines also avoids overloading the CPU of the host.

- **Virtualize multiple-machine testing environments** – Set up a software package for QA on a virtual machine and configure automation on other virtual machines to test the first.

- **Virtualize network performance and security** – Team virtual machines can use networking just as other virtual machines can. In addition, team members can communicate in private networks called LAN segments. Team networking lets you to do the following:
 - Isolate a team completely from the host network. A team LAN segment is undetectable and inaccessible from any other network.
 - Create a virtual DMZ or proxy server to securely bridge the team members to the outside network.
 - Allow specific network bandwidth and packet loss to each virtual machine on the team.
 - Connect all team members fully to host resources.

You control all traffic allowed between the host network and team virtual machines.

- **Monitor multiple virtual machines** – Use thumbnail views of the virtual machine displays to review activity on team virtual machines simultaneously.

Managing Teams

Managing teams requires creating, deleting, opening, closing, and changing the names of teams.

Create a Team

Use the New Team wizard to create a team and add virtual machines.

Before creating a team, if you plan to add virtual machines to the team while completing the New Team wizard, take these actions:

- Power off any virtual machines that you want to add to the team.
- Power off any virtual machines that you want to clone if you intend to create a clone and add it to the team.

You can instead add virtual machines after you create the team, by using the **Team** menu.

NOTE Workstation 4 virtual machines cannot be added to teams.

To create a team

- 1 From the Workstation menu bar, choose **File > New > Team**.
- 2 In the New Team wizard, supply the following information:
 - a Enter a name for the team and specify the location of the virtual team files.
By default, the team files are stored in the same directory as virtual machines. See [“Virtual Machine Location”](#) on page 83.
 - b Specify whether to add virtual machines to the team now or later.
If you want to add virtual machines now, you have the following options:
 - **New Virtual Machine** – Launches the New Virtual Machine wizard. See [“Use the New Virtual Machine Wizard”](#) on page 89.
 - **Existing Virtual Machine** – Opens a file browser from which you can navigate the host file system to locate an existing `.vmx` file.
When you add a virtual machine to a team, it can no longer be accessed outside the team. See [“Add a Virtual Machine to a Team”](#) on page 276.
 - **New Clone of Virtual Machine** – Opens a file browser from which you can navigate the host file system to locate an existing `.vmx` file. After you select a virtual machine, Workstation launches the Clone Virtual Machine wizard. See [“Creating Clones”](#) on page 221.
 - c Specify whether to add one or more LAN segments.
You can add LAN segments after you create the team by using the **Team** menu. If you add LAN segments while creating the team, you can change default names and bandwidth later. See [“Working with Team Networks”](#) on page 280.

After the team is created, you can add it to the **Favorites** list. Use the **Team** menu to configure the team further or to add and remove virtual machines.

Open a Team and Add It to the Favorites List

Opening a team displays its summary tab but does not power on the virtual machines included in the team.

To open a team and add it to the Favorites list

- 1 From the Workstation menu bar, choose **File > Open**.
- 2 Browse to the location of the `.vmtm` file for the team you want.

- 3 Select the file and click **Open**.
- 4 (Optional) To add the team to the **Favorites** list, choose **File > Add to Favorites**.

After a team is added to the **Favorites** list, you can open it by clicking it in the **Favorites** list rather than using the menu bar.

You can now power on one or more of the virtual machines in the team. See [“Power On a Team”](#) on page 279.

Rename a Team

When you create a team, the name of the directory where the team (.vmtm) file is stored is based on the name you originally give the team. Although you can change the name of the team, the name of this file does not change.

To rename a team

Do one of the following:

- If the team is in the **Favorites** list, right-click it and choose **Rename**. Type the new name and press Enter.
- Select the team and choose **Team > Settings > Options**. Type a new name in the **Team name** field and click **OK**.

Power Off or Close a Team

Powering off a team means shutting down all the virtual machines in the team. The virtual machines are powered off in reverse order of that shown in the startup sequence. See [“Specify the Startup Sequence for a Team”](#) on page 278.

Closing a team removes its summary tab from the Workstation window. Depending on how you set Workstation preferences, closing a team might require powering off the team.

To power off or close a team

Depending on which operation you want to perform, do one of the following:

- To power off the team, select it and choose **Team > Power > Power Off**.
Depending on how you configured power operations, the guest operating system might be shut down before the virtual machine is powered off. See [“Configure Power Off and Reset Options for a Virtual Machine”](#) on page 152.

- To close the team, select it and choose **File > Close**.

Depending on how Workstation preferences are set, if any of the team's virtual machines are still powered on, you might see a prompt. For information about the options shown in the prompt, see [“Closing Virtual Machines and Exiting Workstation”](#) on page 71.

Delete a Team

Before you can delete a team, you must power off all virtual machines that are members of the team. See [“Power Off or Close a Team”](#) on page 274.

When you delete a team, you can choose to delete:

- Only the team (retaining the virtual machines in the team)
- The team and the virtual machines in the team

To remove a team from the Workstation window rather than deleting it, see [“Remove a Virtual Machine from a Team”](#) on page 277.



CAUTION Deleting a team permanently removes the team files from the host file system and removes associated LAN segments from all virtual machines. Deleting the team's virtual machines along with the team removes the virtual machine files permanently.

To delete a team

- 1 Select the team and choose **Team > Delete from Disk**.
- 2 Complete the dialog box that appears:
 - To delete the team without deleting the virtual machines in it, choose **Delete**.
 - To delete the team and the virtual machines in it, choose **Delete Team and VMs**.

When you delete a team, you also delete all team LAN segments. The virtual network adapters associated with deleted LAN segments become disconnected. Bridged, host-only, NAT, and custom configurations remain unchanged.

- 3 Click **OK**.

Summary and Console Views for Teams and Their Virtual Machines

Workstation displays teams in a summary view or console view:

- The summary view is available at any time. See [“Summary View”](#) on page 56.
- The console view is available only when a team is powered on. A grab bar allows you to resize the areas. This view displays a large console view of the selected virtual machine and thumbnail console views of the other virtual machines in the team. Thumbnail views show the order of the startup sequence from left to right and top to bottom.

If the team contains many virtual machines, you might need to scroll the thumbnails to view all the virtual machines. The thumbnails are displayed in the same order as the team's startup sequence. The left-most virtual machine is the first one in the sequence.

Workstation updates thumbnails in real time to display the actual content of the virtual machine screens. The active virtual machine is the one you select or switch to by using the **Team > Switch To** menu. It appears in the lower pane of the console. Its thumbnail is represented by the **VMware** icon.

Workstation menus and commands directly affect only the active virtual machine, and you can use the mouse and keyboard to interact directly with the active virtual machine.

In full screen mode, Workstation displays only the active virtual machine. See [“Use Full Screen Mode”](#) on page 162.

Managing the Members of a Team

Managing members of a team requires adding virtual machines to a team, removing them from a team, and setting the order in which members of a team start and stop.

Add a Virtual Machine to a Team

Before you add a virtual machine to a team, consider these issues:

- A virtual machine is not powered on when you add it to a running team. You must power on the added virtual machine manually to use it during the current session. The added virtual machine is thereafter powered on or off with the rest of the team.

- When you add a virtual machine to a team, you can no longer operate the virtual machine outside the team. Adding a virtual machine to a team removes it from the **Favorites** list.

NOTE Workstation 4 virtual machines cannot be added to teams.

To add a virtual machine to a team

Select the team, choose **Team > Add**, and choose one of the following options:

- **New Virtual Machine** – Launches the New Virtual Machine wizard. See [“Use the New Virtual Machine Wizard”](#) on page 89.
- **Existing Virtual Machine** – Opens a file browser from which you can navigate the host file system to locate an existing .vmx file.

When you add a virtual machine to a team it can no longer be accessed outside the team.

- **New Clone of Virtual Machine** – Opens a file browser from which you can navigate the host file system to locate an existing .vmx file. After you select a virtual machine, Workstation launches the Clone Virtual Machine wizard. See [“Creating Clones”](#) on page 221.

Remove a Virtual Machine from a Team

Remove a virtual machine from a team when you want to use the virtual machine independently. That is, it does not need to be started up or shut down before or after any other virtual machine. It also does not need to be in a private team network.

NOTE When you remove a virtual machine from a team, you also remove it from team LAN segments. Virtual network adapters associated with LAN segments become disconnected. Bridged, host-only, NAT, and custom configurations remain unchanged.

To remove a virtual machine from a team

- 1 Power off the virtual machine that you want to remove.
- 2 Select the team and choose **Team > Remove > <virtual machine name>**.

The selected virtual machine is removed from the team.

You can perform these tasks after removing the virtual machine:

- Add the virtual machine to the **Favorites** list. See [“To add virtual machines and teams to the Favorites list”](#) on page 64.
- Delete the virtual machine and erase its files from the host file system. See [“Delete a Virtual Machine”](#) on page 158.

Specify the Startup Sequence for a Team

Use a startup sequence to specify the order in which virtual machines start and stop and the delay, in seconds, between starting and stopping the next virtual machine in the sequence.

Power on and resume operations occur in the order of the sequence shown in the team settings list. Power off operations occur in reverse order. The default sequence, is the order in which you added the virtual machines to the team. The default delay is 10 seconds.

Setting a startup sequence is useful, for example, if you have a virtual machine that runs an application to be tested and you want it to start before the virtual machines running an automated testing script.

Setting a delay avoids overloading the CPU when multiple virtual machines start and allows applications on a virtual machine to launch before another team virtual machine attempts to connect.

To specify a startup sequence for a team

- 1 Select the team.
- 2 Choose **Team > Settings** and click the **Virtual Machines** tab.
- 3 Use the up and down arrow buttons to arrange the virtual machines in the list.

The virtual machine at the top of the list is the first in the startup sequence.

- 4 Select each virtual machine and specify how many seconds you want it to wait before starting the next virtual machine.

If the virtual machine team depends on precise startup timing, experiment to determine how much time the host and guest operating environments and applications need to launch.

- 5 Click **OK** to save your changes.

Power Operations for Teams and Their Members

Power operations for teams are much the same as those for an individual virtual machine. However, for a team, you can also change the sequence in which the members of a team power on and off. See [“Specify the Startup Sequence for a Team”](#) on page 278.

You can also use Workstation’s command-line application for team power operations. See [Appendix A, “Appendix: Workstation Command-Line Reference,”](#) on page 485.

Power On a Team

When you power on a team, the virtual machines in the team power on in the startup sequence specified in the team settings editor. See [“Specify the Startup Sequence for a Team”](#) on page 278.

To power on a team

Do one of the following:

- To use the Workstation GUI, select the team and choose **Team > Power > Power On**.
- To use the command line, see [“Startup Options for Workstation and Virtual Machines”](#) on page 485.

Suspend or Resume a Team

When you suspend a team, all team virtual machines are suspended simultaneously. The startup sequence determines the order in which virtual machines are resumed and how much time elapses before resuming the next team member. See [“Specify the Startup Sequence for a Team”](#) on page 278.

If you attempt to close Workstation while a team suspend or resume operation is still in progress, a warning dialog box appears.

To suspend or resume a team

- 1 To suspend or resume a team, select the team and choose one of the **Team > Power** options.
All team virtual machines are suspended simultaneously.
- 2 To see the progress of a particular team member, choose **Team > Switch To > <virtual_machine_name>**.

The time to complete the operation varies with the size of the virtual machines.

Perform Power Operations on One Team Member

Performing a power operation for one member of a team is similar to performing the operation for a virtual machine that is not part of the team, except that instead of selecting the machine from the **Favorites** list, you select it from the team's console tab.

To perform power operations on one team member

- 1 Select the virtual machine from the team's console tab.
- 2 Choose the appropriate command from the **VM > Power** menu.

Working with Team Networks

One of the advantages of teams is the ability to isolate virtual machines in private virtual networks, called LAN segments. This can be useful with multitier testing, network performance analysis, and situations where isolation and packet loss are important.

For information about other aspects of networking than LAN segments, see [Chapter 14, "Configuring a Virtual Network,"](#) on page 285.

LAN Segment Requirements Regarding IP Addresses

When you add an existing virtual machine to a team, the virtual machine might be configured to expect an IP address from a DHCP server. Unlike host-only and NAT networking, LAN segments have no DHCP server provided automatically by Workstation.

Each network client must have an IP address for TCP/IP networking. Therefore you must manually configure IP addressing for team virtual machines on a LAN segment. Two choices are available:

- **DHCP** – Configure a DHCP server on your LAN segment to allocate IP addresses to your virtual machines.
- **Static IP** – Configure a fixed IP address for each virtual machine on the LAN segment.

Create a Team LAN Segment

The first step to creating a virtual network for a team is to add and name a LAN segment. You can then configure connections to this segment.

To create a team LAN segment

- 1 Select the team and choose **Team > Add > LAN Segment**.
- 2 Enter a name for the private network and click **OK**.

You can configure the other settings in this dialog box later.

You can perform these tasks after creating a LAN segment:

- Configure network transmission properties for the segment. See [“Configure LAN Segments”](#) on page 281.
- Create a network adapter and connect it to the segment. See [“Add or Remove Network Adapters”](#) on page 282.

Configure LAN Segments

You can configure network transmission properties for a team LAN segment, including bandwidth settings such as connection type and speed, as well as percentage of packet loss allowed.

To configure LAN segments

- 1 Select the team and choose **Team > Settings**.
- 2 Click the **LAN Segments** tab, and complete the fields.

From this tab you can add, remove, and rename the LAN segments configured for the team.

The list in the left pane displays LAN segments associated with the team.

- 3 Click a name to select the LAN segment you want to configure.

The right pane displays parameters for the physical properties of the emulated LAN segment link:

- **Name** – Name of the LAN segment. To change the name, type a new name in the **Name** field.
- **Bandwidth** – Drop-down menu of bandwidths for typical network links. To change the bandwidth, choose another connection type from the drop-down menu.

- **Kbps** – Field to set a custom bandwidth, in kilobits per second. Changes here are overwritten when you make a selection from the **Bandwidth** menu. To change the bandwidth, type a number into the field.
 - **Packet Loss** – Specification of the efficiency or faultiness of the link, measured in the percentage of packets lost from the total number of packets transmitted. To change the packet loss setting, type a number into the field.
- 4 Click **OK** to save your changes.
 - 5 (Optional) If virtual machines are currently running and you want them to adopt these configuration changes, power on, reset, or resume the virtual machines, as appropriate.

Add or Remove Network Adapters

A physical PC must have a network adapter or NIC (network interface controller), for each physical network connection. Similarly, a virtual machine must be configured with a virtual network adapter for each LAN segment it interacts with.

To connect a virtual machine to multiple LAN segments simultaneously, you must configure that virtual machine with multiple network adapters.

To add or remove network adapters

- 1 Power off the virtual machine that you want to add a network adapter to or remove an adapter from.
- 2 Select the team and choose **Team > Settings**.
- 3 On the **Connections** tab, select the virtual machine and do one of the following:
 - To add a network adapter, click **Add Adapter**.

The added adapter is displayed in the **Adapters** column. By default, the adapter connects to the bridged LAN segment, but you can change the setting by clicking a check box for another segment. If the segment you want to use is not listed, create it. See [“Create a Team LAN Segment”](#) on page 281.

NICs configured with connections through a DHCP server cannot connect to a team LAN segment.
 - To remove an adapter, select the adapter you want to remove and click **Remove Adapter**.
- 4 Click **OK**.

Delete a LAN Segment

Deleting a LAN segment disconnects all virtual network adapters that are configured for that LAN segment. When you remove a virtual machine from a team, you must manually configure its disconnected virtual network adapter if you want to reconnect the virtual machine to a network.

To delete a LAN segment

- 1 Select the team and choose **Team > Settings**.
- 2 Click the **LAN Segments** tab and select the LAN segment you want to delete.
- 3 Click **Remove** and click **OK**.

Cloning and Taking Snapshots of Team Virtual Machines

You can clone a virtual machine in a team in the same way you clone any other virtual machine. See [“Creating Clones”](#) on page 221.

When you clone a virtual machine in a team:

- The resulting clone is not part of the team.
- The clone appears on the **Favorites** list as well as in a summary window.
- If the parent virtual machine is configured for a LAN segment, the virtual network adapter for that LAN segment on the clone is disconnected. To connect to a network, you must reconfigure the virtual Ethernet adapter manually.

Snapshots operate only on virtual machines and not on the whole team. When a team is active, you can use the **Snapshot** button on the toolbar to take a snapshot of only the active virtual machine.

To preserve the state of all virtual machines on a team, power off the team, and take a snapshot of each virtual machine before you power on the team again.

Configuring a Virtual Network

14

This chapter previews the virtual networking components that VMware Workstation provides and shows how to use them with your virtual machine. This chapter includes the following topics:

- [“Components of the Virtual Network”](#) on page 285
- [“Common Networking Configurations”](#) on page 286
- [“Example of a Custom Networking Configuration”](#) on page 291
- [“Changing a Networking Configuration”](#) on page 295
- [“Configuring Bridged Networking”](#) on page 297
- [“Changing the Subnet or DHCP Settings for a Virtual Network”](#) on page 299
- [“Configuring Host Virtual Network Adapters”](#) on page 301

Components of the Virtual Network

Workstation provides the bridged, network address translation (NAT), host-only networking, and custom networking options to configure a virtual machine for virtual networking.

Virtual Switch

Like a physical switch, a virtual switch lets you connect other networking components together. Virtual switches are created as needed by Workstation, up to a total of 10 virtual switches on Windows and 255 on Linux. You can connect one or more virtual machines to a switch. By default, a few of the virtual switches are mapped to specific networks.

Table 14-1. Default Virtual Network Switches

Network Type	Switch Name	Reference
Bridged	VMnet0	“Bridged Networking” on page 287
NAT	VMnet8	“Network Address Translation (NAT)” on page 289
Host-only	VMnet1	“Host-Only Networking” on page 290

The other available networks are named VMnet2, VMnet3, VMnet4, and so on.

DHCP Server

The dynamic host configuration protocol (DHCP) server provides IP network addresses to virtual machines in configurations that are not bridged to an external network. For example, host-only and NAT configurations use the DHCP server.

Network Adapter

A virtual network adapter is set up for your virtual machine when you use any type of networking to create it with the New Virtual Machine wizard. It appears in the guest operating system as an AMD PCNET PCI adapter or as an Intel Pro/1000 MT Server Adapter. On Windows Vista and Windows 7 guests, it is an Intel Pro/1000 MT Server Adapter.

Use the virtual machine settings editor to create and configure up to 10 network adapters in each Workstation 6.0 and higher virtual machine. The limit is three adapters for Workstation 4 or 5.x virtual machines. For more information, see [“Changing a Networking Configuration”](#) on page 295.

Common Networking Configurations

When you choose the standard networking options in the New Virtual Machine wizard or the virtual machine settings editor, the networking configurations are set up for you automatically.

If you select the Typical setup path in the New Virtual Machine wizard, the wizard sets up network address translation (NAT) for the virtual machine. Select the Custom setup path to choose any of the common configurations: bridged networking, NAT, or host-only networking. The wizard connects the virtual machine to the appropriate virtual network.

You can set up more specialized configurations by choosing the appropriate settings in the virtual machine settings editor, in the virtual network editor (on Windows and Linux hosts), and on your host computer. On all hosts, the software needed for all networking configurations is installed when you install Workstation.

You can connect multiple virtual machines to the same virtual Ethernet switch. On a Windows host, you can connect an unlimited number of virtual network devices to a virtual switch. On a Linux host, you can connect up to 32 devices.


If you have set your virtual network settings on a previous version of Workstation and upgrade to a new version, your previous network settings might be fully or partially preserved. For more information, see [“Preparing for an Upgrade”](#) on page 47.

Bridged Networking

Bridged networking connects a virtual machine to a network by using the host computer’s network adapter. If your host computer is on a network, this is often the easiest way to give your virtual machine access to that network. The virtual network adapter in the virtual machine connects to the physical network adapter in your host computer, allowing it to connect to the LAN the host computer uses.

Bridged networking configures your virtual machine as a unique identity on the network, separate from and unrelated to its host. It makes the virtual machine visible to other computers on the network, and they can communicate directly with the virtual machine. Bridged networking works with both wired and wireless physical host network cards.

Figure 14-1. Bridged Networking Setup



Set Up Bridged Networking

Windows and Linux hosts can use bridged networking to connect to wired and wireless networks.

To set up bridged networking

Do one of the following:

- For a new virtual machine, choose **File > New > Virtual Machine > Custom (advanced)** and select **Use bridged networking** in the New Virtual Machine wizard.
- For an existing virtual machine, choose **VM > Settings**.
 - a On the **Hardware** tab select **Network Adapter**.
 - b In the **Network connection** section select **Bridged: Connected directly to the physical network**.
 - c (Optional) Select **Replicate physical network connection state** if you use the virtual machine on a laptop or other mobile device.

As you move from one wired or wireless network to another, the IP address is automatically renewed.

Setup Requirements for IP Addresses

If you use bridged networking, your virtual machine must have its own identity on the network. For example, on a TCP/IP network, the virtual machine needs its own IP address. Your network administrator can tell you whether IP addresses are available for your virtual machine and which networking settings you should use in the guest operating system. Generally, your guest operating system can acquire an IP address and other network details automatically from a DHCP server, or you might need to set the IP address and other details manually in the guest operating system.

If you use bridged networking, the virtual machine is a full participant in the network. It has access to other machines on the network and other machines on the network can contact it as if it were a physical computer on the network.


Users who boot multiple operating systems often assign the same address to all systems, because they assume that only one operating system will be running at a time.

NOTE If the host computer is set up to boot multiple operating systems and you run one or more of them in virtual machines, configure each operating system with a unique network address.

Network Address Translation (NAT)

NAT configures a virtual machine to share the IP and MAC addresses of the host. The virtual machine and the host share a single network identity that is not visible outside the network. NAT can be useful when your network administrator lets you use a single IP address or MAC address. If cannot give your virtual machine an IP address on the external network, you can use NAT to give your virtual machine access to the Internet or another TCP/IP network. NAT uses the host computer's network connection. NAT works with Ethernet, DSL, and phone modems.

Figure 14-2. NAT Setup



If you select NAT, the virtual machine can use many standard TCP/IP protocols to connect to other machines on the external network. For example, you can use HTTP to browse Web sites, FTP to transfer files, and Telnet to log on to other computers. NAT also lets you to connect to a TCP/IP network by using a Token Ring adapter on the host computer.

In the default configuration, computers on the external network cannot initiate connections to the virtual machine. That means, for example, that the default configuration does not let you use the virtual machine as a Web server to send Web pages to computers on the external network. This configuration protects the guest operating system from being compromised before you have a chance to install security software. For more information on NAT, see [“Using NAT”](#) on page 316.

Setting Up NAT

By default, NAT is used when you use the Typical setup to create a virtual machine in the New Virtual Machine wizard.


Setup Requirements for IP Addresses

If you use NAT, your virtual machine does not have its own IP address on the external network. Instead, a separate private network is set up on the host computer. Your virtual machine gets an address on that network from the VMware virtual DHCP server. The VMware NAT device passes network data between one or more virtual machines and the external network. It identifies incoming data packets intended for each virtual machine and sends them to the correct destination.

Host-Only Networking

Host-only networking creates a network that is completely contained within the host computer. Host-only networking provides a network connection between the virtual machine and the host computer, using a virtual network adapter that is visible to the host operating system. This approach can be useful if you need to set up an isolated virtual network. In this configuration, the virtual machine cannot connect to the Internet. For more information on host-only networking, see [“Selecting IP Addresses on a Host-Only Network or NAT Configuration”](#) on page 304.

Figure 14-3. Host-Only Networking Setup



Set Up Host-Only Networking

You can set up host-only networking while creating a virtual machine or after a virtual machine is created.

To set up host-only networking

Do one of the following:

- For a new virtual machine, choose **File > New > Virtual Machine > Custom (advanced)** and select **Use host-only networking** in the New Virtual Machine wizard.
- For an existing virtual machine, choose **VM > Settings**.
 - a On the **Hardware** tab select **Network Adapter**.
 - b In the **Network connection** section click **Host-only: A private network shared with the host**.

Setup Requirements for IP Addresses

If you use host-only networking, your virtual machine and the host virtual adapter are connected to a private Ethernet network. The VMware DHCP server provides addresses on this network.

Routing and Connection Sharing

If you install the proper routing or proxy software on your host computer, you can establish a connection between the host virtual network adapter and a physical network adapter on the host computer. This lets you connect the virtual machine to a Token Ring or other non-Ethernet network.

On a Windows XP or Windows Server 2003 host computer, you can use host-only networking in combination with the Internet connection sharing feature in Windows to allow a virtual machine to use the host's dial-up networking adapter or other connection to the Internet. For details on how to configure Internet connection sharing, see your Windows documentation.


Example of a Custom Networking Configuration

With the Workstation virtual networking components, you can create sophisticated virtual networks. The virtual networks can be connected to one or more external networks, or they can run entirely on the host computer. On Windows hosts, you can use the virtual network editor to access multiple network cards in your host and create multiple virtual networks.

Before you attempt to set up complex virtual networks, you need a good understanding of how to configure network devices in your host and guest operating systems.

[Figure 14-4](#) shows most of the ways you can combine devices on a virtual network. In this example, a Web server connects through a firewall to an external network. An administrator's computer connects to the Web server through a second firewall.

Figure 14-4. Custom Configuration with Two Firewalls



Other custom configurations are described in [“Advanced Virtual Networking”](#) on page 303 and [“Using NAT”](#) on page 316.

Set Up a Custom Networking Configuration

To set up the custom networking configuration, create four virtual machines and use the virtual machine settings editor to adjust the settings for their virtual network adapters. Install the appropriate guest operating systems and application software in each virtual machine and make the appropriate networking settings in each virtual machine.

To set up a custom networking configuration

- 1 Set up four virtual machines using the New Virtual Machine wizard:
 - a Choose **File > New > Virtual Machine**.
 - b Create the first virtual machine with bridged networking so that it can connect to an external network by using the host computer's network adapter.
 - c Create the other three virtual machines without networking.
 Setting up virtual network adapters and installation of the operating systems are performed in [Step 7](#).
- 2 Configure network settings for the first virtual machine:
 - a Open the first virtual machine, but do not power it on.
 - b Use the virtual machine settings editor to add a second virtual network adapter.
 See ["Changing a Networking Configuration"](#) on page 295.
 - c Connect the second adapter to Custom (VMnet2).
- 3 Configure network settings for the second virtual machine.
 - a Open a virtual machine, but do not power it on.
 - b Use the virtual machine settings editor to add a virtual network adapter.
 - c Connect the adapter to Custom (VMnet2).
- 4 Configure network settings for the third virtual machine:
 - a Open virtual machine 3, but do not power it on.
 - b Use the virtual machine settings editor to add a virtual network adapter.
 - c Connect the adapter to Custom (VMnet2).
 - d Use the virtual machine settings editor to add a second virtual network adapter.
 - e Connect the second adapter to Custom (VMnet3).
- 5 Configure network settings for the fourth virtual machine:
 - a Open virtual machine 4, but do not power it on.
 - b Use the virtual machine settings editor to add a virtual network adapter.
 - c Connect the adapter to Custom (VMnet3).

- 6 Determine the network addresses used for VMnet2 and VMnet3:
 - On Windows hosts, open a command prompt and run the following command:


```
ipconfig /all
```

Note the network addresses that each virtual adapter uses.
 - On Linux hosts, open a terminal and run the following command:


```
ifconfig
```

Note the network addresses that each virtual switch uses.
- 7 Power on each virtual machine in turn and install the appropriate guest operating system.
- 8 On Windows and Linux hosts, to configure network addresses using the DHCP server, do the following:
 - a Choose **Edit > Virtual Network Editor**.

On Linux, choose **Applications > System Tools > Virtual Network Editor**, or the equivalent menu path for your version of Linux.
 - b Select VMnet2 and check the **Use local DHCP service to distribute IP address to VMs** option.

For more information on changing subnets, see [“Change Subnet or DHCP Settings on a Windows Host”](#) on page 300 and [“Change Subnet or DHCP Settings on a Linux Host”](#) on page 300.
- 9 Configure the networking in each guest operating system:
 - **Machine 1** – For the bridged network adapter in virtual machine 1, use the networking settings needed for a connection to the external network. If the virtual machine receives its IP address from a DHCP server on the external network, the default settings should work.

For the second network adapter in virtual machine 1, manually assign an IP address in the range you are using with VMnet2.
 - **Machine 2** – Assign an IP address in the range you are using with VMnet2.
 - **Machine 3** – Network adapters are connected to VMnet2 and VMnet3. Assign an IP address in the virtual network's range it is connected to.
 - **Machine 4** – Assign an IP address in the range you are using with VMnet3.
- 10 Install the necessary application software in each virtual machine.

Changing a Networking Configuration

You can use the virtual machine settings editor to add virtual network adapters to your virtual machine and change the networking configuration of existing adapters.

Find the Network Type of a Virtual Machine

Unless you set up a custom network connection, a virtual machine uses a bridged, NAT, or host-only network connection. If you use the Typical setup path in the New Virtual Machine wizard to create a virtual machine, the new virtual machine uses the NAT network type.

For more information, see [“Common Networking Configurations”](#) on page 286.

To find the network type of a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings > Hardware**.
- 3 Select the network adapter.

The **Network Connection** section displays the details that lets you to change the settings.

To change the network type, see [“Modify Existing Virtual Network Adapters”](#) on page 296.

Add Virtual Network Adapters

You can add up to 10 virtual network adapters to a virtual machine.

To add virtual network adapters

- 1 Select the virtual machine to which you want to add the adapter.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, click **Add**.
- 4 Select **Network Adapter** and click **Next**.
- 5 Select the network type to use.

- 6 (Optional) If you select **Custom**, choose the VMnet network to use from the drop-down menu.

Although VMnet0, VMnet1, and VMnet8 are technically available in this list, they are usually used for bridged, host-only, and NAT configurations, respectively. You must perform another procedure to make them available for use in custom configurations. Choose one of the other VMnet switches.

- 7 Click **Finish**.

The new adapter is added.

- 8 Click **OK** to save your configuration.

Modify Existing Virtual Network Adapters

Before you begin modifying the virtual network adapters, determine the network type you want to assign. See [“Common Networking Configurations”](#) on page 286.

To modify existing virtual network adapters

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select the adapter to modify.
- 4 Select the network type to use.
- 5 (Optional) If you select **Custom**, choose the VMnet virtual network to use for the network from the drop-down menu.

Although VMnet0, VMnet1, and VMnet8 are technically available in this menu, they are usually used for bridged, host-only, and NAT configurations, respectively. You must perform another procedure to make them available for use in custom configurations. Choose one of the other VMnet switches.

- 6 Click **OK**.
- 7 Be sure the guest operating system is configured to use an appropriate IP address on the new network.

If the guest is using DHCP, release and renew the lease. If the IP address is set statically, be sure the guest has an address on the correct virtual network.

Configuring Bridged Networking

Windows and Linux hosts allow you to configure bridged networking. You can view and change the settings for bridged networking on your host, determine which network adapters on your host to use for bridged networking, and map specific network adapters to specific virtual networks, called VMnets.

Configure VMnet0 Automatic Bridged Networking on a Windows Host

When you configure VMnet0 bridged networking the change you make affects all the virtual machines that use bridged networking on the host.

To configure VMnet0 bridged networking on a Windows host

- 1 Choose **Edit > Virtual Network Editor**.

By default, VMnet0 is set to use automatic bridging mode and bridges to all of the active network adapters on the host computer.

- 2 Click the **Automatic Settings**, and select the check box for the available physical network adapter(s) to automatically bridge to VMnet0.

To place restrictions on a network adapter, see [“Add or Remove a Host Network Adapter from the List of Included Adapters.”](#)

- 3 Click **OK**.

Add or Remove a Host Network Adapter from the List of Included Adapters

On host systems with multiple physical network adapters, the choice of which adapter Workstation uses is arbitrary. Therefore, you can place or remove restrictions on a network adapter of your choice.

To add or remove a host network adapter from the list of included adapters

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Click **Automatic Settings**.
- 3 In the **Include adapters** section, do one of the following:
 - To remove an adapter, deselect the adapter.
 - To add an adapter, select the adapter.
- 4 Click **OK**.

Designate a Physical Network Adapter to Bridge to Custom Virtual Switches

Before you change the bridged adapter mappings, check which virtual network the physical network adapter is going to be assigned to.



CAUTION If you reassign a physical network adapter to a different virtual network, any virtual machine that is using the original network loses its network connectivity through that network. You must then change the setting for each affected virtual machine's network adapter individually.

This can be especially troublesome if your host has only one physical network adapter and you reassign it to a VMnet other than VMnet0. In this case, even though the VMnet still appears to be bridged to an automatically chosen adapter, the only adapter it can use was assigned to another VMnet.

To designate a physical network adapter to bridge to custom virtual switches

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Choose an adapter from the **Bridged to** drop-down menu.

You can create a custom bridged network on virtual switches VMnet2 to VMnet7. On Windows, you can also use VMnet9. On Linux, you can also use vmnet10 through vmnet255.

- 3 Click **OK**.

Configure vmnet0 Automatic Bridged Networking on a Linux Host

By default, vmnet0 is set to use automatic bridging mode and bridges to one of the active network adapters on the host computer.

To configure vmnet0 automatic bridged networking on a Linux host

- 1 On the Linux host, do one of the following:
 - From the desktop,
 - Open a terminal window and enter the following command:
`/usr/bin/vmware-netcfg`
- 2 When prompted, enter the administrator password.
- 3 If the table in the network editor does not display a row for vmnet0, click **Add Network** and complete the Add Virtual Network dialog box.

- 4 Select the `vmnet0` row in the table and select **Bridged**.
- 5 Do one of the following:
 - To use automatic bridging, click **Automatic Settings** and complete the dialog box.

If you select multiple check boxes, the virtual machine bridges to the first available host network adapter. If an item in the list is disabled, the adapter is not available because it is already being used to bridge to another `vmnet`.
 - To specify one host network adapter, use the **Bridge to** list box.
- 6 Click **Save**.

Setting Up a Second Automatic Bridged Network Interface

If you have two network adapters installed on your host computer that are connected to two different networks, you might want your virtual machines on that host computer to bridge to both network adapters so that the virtual machines can access either or both physical networks.

When you install Workstation on a host computer with multiple network adapters, you can configure multiple bridged networks. On a Windows host, to set up multiple bridged networks see [“Configure VMnet0 Automatic Bridged Networking on a Windows Host”](#) on page 297. On a Linux host, to set up multiple bridged networks see [“Configure vmnet0 Automatic Bridged Networking on a Linux Host”](#) on page 298.

Changing the Subnet or DHCP Settings for a Virtual Network

On Windows and Linux hosts, you can use the virtual network editor to make changes to subnet and DHCP settings.

IP networks are divided using subnet masks. When you modify the subnet mask, Workstation automatically updates the IP address settings for other components such as DHCP, NAT, and host virtual adapter if the default settings were never changed. The specific settings that are automatically updated include DHCP lease range, DHCP server address, NAT gateway address, and host virtual adapter IP address.

However, if you changed any of these settings from their default value, Workstation does not update that setting automatically if the value is in the valid range. If the value exceeds the valid range, Workstation resets the settings based on the subnet range. Workstation presumes that custom settings are not to be modified. This is the case even if you later changed the setting back to the default.

Change Subnet or DHCP Settings on a Windows Host

To change the subnet settings, configure the subnet mask. The default subnet mask is 255.255.255.0 (a Class C address). Typically, this means you should modify only the third number in the IP address, for example, x in 192.168.x.0 or 198.16.x.0. In general, do not change the subnet mask. Certain virtual network services might not work as well with a customized subnet mask.

To change subnet or DHCP settings on a Windows host

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Change the subnet IP address in the **Subnet IP** field and modify the subnet mask in the **Subnet mask** field.

The address should specify a valid network address that is suitable for use with the subnet mask.

- 3 Click **OK**.
- 4 In the DHCP settings dialog box, you can change the range of IP addresses provided by the Workstation DHCP server on a particular virtual network.

You can also set the duration of DHCP leases provided to clients on the virtual network.
- 5 Click **OK**.

Change Subnet or DHCP Settings on a Linux Host

NAT and host-only network types can have settings for subnet IP. You can use the virtual network editor to change subnet settings for a virtual network on a Linux host.

You can also use the virtual network editor to specify that a local DHCP service distributes IP addresses to virtual machines. To change DHCP settings further, edit the `dhcp.conf` file. See [“Configure the DHCP Server on a Linux Host”](#) on page 306.

To change subnet or DHCP settings on a Linux host

- 1 On the Linux host, do one of the following:
 - From the desktop, choose **Applications > System Tools > Virtual Network Configuration**, or the equivalent menu path for your version of Linux.
 - Open a terminal window and enter the following command:

`/usr/bin/vmware-netcfg`
- 2 When prompted, enter the administrator password.

- 3 If the table in the network editor does not display a row for the network type you want, click **Add Network** and complete the Add Virtual Network dialog box.
Use `vmnet1` for a host-only network type, and use `vmnet8` for a NAT network type.
- 4 Select the row in the table that corresponds to the network to edit and select **NAT** or **Host-only**, as appropriate.
- 5 Use the appropriate check boxes to specify whether to use a DHCP service, a host virtual adapter, or both.
- 6 To specify subnet IP, do one of the following:
 - To automatically select an unused subnet IP, leave the **Subnet IP** text box empty.
The next time you start the virtual network editor, the subnet IP appears in the text box.
 - Type the subnet IP you want to use in the **Subnet IP** text box.
- 7 Click **Save**.

Configuring Host Virtual Network Adapters

When you install Workstation, two network adapters are added to the configuration of your host operating system. One lets the host to connect to the host-only network, and the other lets the host to connect to the NAT network.

The presence of virtual network adapters has a slight performance cost, because broadcast packets must go to the extra adapters. On Windows networks, browsing your network might be slower than usual. In some cases, these adapters interact with the host computer's networking configuration in undesirable ways.

Connect or Disconnect a Host Virtual Network Adapter

Before you disconnect a host virtual network adapter determine whether you are going to use the virtual network adapter.

To connect or disconnect a host virtual network adapter

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Click the **Connect a host virtual adapter to this network** option to connect.
- 3 Deselect the **Connect a host virtual adapter to this network** option to disconnect.

Setting Up Two Separate Host-Only Networks

Set up multiple host-only networks on the same host computer in situations such as the following:

- To have two virtual machines connected to one host-only network, and other virtual machines connected to another host-only network to isolate the network traffic on each network.
- To test routing between two virtual networks.
- To test a virtual machine with multiple network interface cards, without using any physical network adapters.

On Windows and Linux hosts, the first host-only network is set up automatically when you install Workstation. To set up multiple host-only networks on Windows and Linux hosts see [“Connect or Disconnect a Host Virtual Network Adapter”](#) on page 301.

On a Linux host, after the host-only networks are set up, at least four network interfaces appear: `eth0`, `lo`, `vmnet1`, and `vmnet2`. These four interfaces should have different IP addresses on separate subnets.

Advanced Virtual Networking

15

This chapter provides detailed information about networking capabilities and specialized configurations for expert users. This chapter includes the following advanced virtual networking topics:

- [“Selecting IP Addresses on a Host-Only Network or NAT Configuration”](#) on page 304
- [“Avoiding IP Packet Leakage in a Host-Only Network”](#) on page 306
- [“Maintaining and Changing the MAC Address of a Virtual Machine”](#) on page 308
- [“Controlling Routing Information for a Host-Only Network on Linux”](#) on page 310
- [“Potential Issues with Host-Only Networking on Linux”](#) on page 311
- [“Configuring Host-Only Virtual Machines”](#) on page 312
- [“Set Up Routing Between Two Host-Only Networks”](#) on page 314
- [“Using Virtual Network Adapters in Promiscuous Mode on a Linux Host”](#) on page 316
- [“Using NAT”](#) on page 316
- [“Advanced NAT Configuration”](#) on page 319
- [“Using Samba with Workstation”](#) on page 328

Selecting IP Addresses on a Host-Only Network or NAT Configuration

The host and all virtual machines configured for host-only networking are connected to the network through a virtual switch. Typically, all the parties on this network use the TCP/IP protocol suite, although other communication protocols can be used.

A network address translation (NAT) configuration also sets up a private network, which must be a TCP/IP network. The virtual machines configured for NAT are connected to that network through a virtual switch. A host virtual adapter connects the host computer to the private network used for NAT.

Each virtual machine and the host must be assigned addresses on the private network. This is typically done by using the DHCP server included with Workstation. This server does not service virtual or physical machines residing on bridged networks.

Addresses can also be assigned statically from a pool of addresses that the DHCP server does not assign.

How the Subnet Number Is Assigned

When host-only networking is enabled at the time Workstation is installed, the subnet IP address for the virtual network is automatically selected as an unused private subnet IP address. A NAT configuration also uses an unused private network automatically selected when you install Workstation.

Find the Network Type Used on a Virtual Machine

Before you assign a subnet number, determine the network type used on the virtual machine.

To find the network type used on a virtual machine

Choose **Edit > Virtual Network Editor**.

The subnet number associated with the virtual network is listed in the **Subnet Address** column.

Determining Whether to Use DHCP or Statically Assign Addresses

Using DHCP to assign IP addresses is simpler and more automatic than statically assigning them. Most Windows operating systems, for example, are preconfigured to use DHCP at boot time, so Windows virtual machines can connect to the network the first time they are booted, without additional configuration. If you want your virtual machines to communicate with each other using names instead of IP addresses, however, you must set up a naming convention, a name server on the private network, or both. In that case it might be simpler to use static IP addresses.

In general, if you have virtual machines you intend to use frequently or for extended periods of time, it is most convenient to assign them static IP addresses or configure the VMware DHCP server to always assign the same IP address to each of these virtual machines.

DHCP Conventions for Assigning IP Addresses

For temporary virtual machines, use DHCP and let it allocate an IP address.

For each host-only or NAT network, the available IP addresses are allocated using the conventions shown in [Table 15-1](#) and [Table 15-2](#), where <net> is the network number assigned to your host-only or NAT network. Workstation always uses a Class C address for host-only and NAT networks.

Table 15-1. IP Address Use on a Host-Only Network

Range	Address Use	Example
<net>.1	Host machine	192.168.0.1
<net>.2–<net>.127	Static addresses	192.168.0.2–192.168.0.127
<net>.128–<net>.253	DHCP-assigned	192.168.0.128–192.168.0.253
<net>.254	DHCP server	192.168.0.254
<net>.255	Broadcasting	192.168.0.255

Table 15-2. IP Address Use on a NAT Network

Range	Address Use	Example
<net>.1	Host machine	192.168.0.1
<net>.2	NAT device	192.168.0.2
<net>.3–<net>.127	Static addresses	192.168.0.3–192.168.0.127
<net>.128–<net>.253	DHCP-assigned	192.168.0.128–192.168.0.253

Table 15-2. IP Address Use on a NAT Network (Continued)

Range	Address Use	Example
<net>.254	DHCP server	192.168.0.254
<net>.255	Broadcasting	192.168.0.255

Configure the DHCP Server on a Windows Host

On a Windows host, use the virtual network editor to configure the DHCP server.

To configure the DHCP server on a Windows host

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Click **DHCP Settings** to change settings for the selected virtual network.
- 3 In the DHCP Settings dialog box that appears, make changes and click **OK**.

Configure the DHCP Server on a Linux Host

Editing the DHCP server configuration file requires information that is best obtained directly from the DHCP server documentation. Consult the `dhcpcd(8)` and `dhcpcd.conf(8)` manual pages.

NOTE The edits made inside the read-only section of the DHCP configuration file are lost the next time you run the network editor.

To configure the DHCP server on a Linux host

- To configure the host-only DHCP server, edit the DHCP configuration file for `vmnet1 (/etc/vmware/vmnet1/dhcp/dhcp.conf)`.
- To configure the DHCP server for the NAT network, edit the configuration file for `vmnet8 (/etc/vmware/vmnet8/dhcp/dhcp.conf)`.

Avoiding IP Packet Leakage in a Host-Only Network

Each host-only network should be confined to the host machine on which it is set up. Packets that virtual machines send on this network should not leak out to a physical network attached to the host. Packet leakage can occur only if a machine actively forwards packets.

If you use dial-up networking support in a virtual machine and packet forwarding is enabled, host-only network traffic might leak out through the dial-up connection. To prevent the leakage, disable packet forwarding in your guest operating system.

If the host computer has multiple network adapters, it might be intentionally configured to use IP forwarding. If that is the case, you do not want to disable forwarding. To avoid packet leakage, you must enable a packet filtering facility and specify that packets from the host-only network should not be sent outside the host computer. Consult your operating system documentation for details on how to configure packet filtering.

Disable Packet Forwarding on Windows Hosts

Systems using server versions of Windows operating systems can forward IP packets that are not addressed to them. By default, these systems and Windows Vista and Windows 7 systems have IP packet forwarding disabled. IP forwarding is not a problem on Windows XP Professional or Windows XP Home Edition hosts.

If you find packets leaking from a host-only network on a Windows host computer, check whether forwarding was enabled on the host machine. If it is enabled, disable it.

To disable packet forwarding on Windows hosts

Do one of the following:

- Stop the Routing and Remote Access service:
 - a Choose **Start > Run** and enter **services.msc** in the Run dialog box.
 - b In the Services window that appears, disable the Routing and Remote Access service.
- Use Windows Administrative Tools to disable routing and remote access:
 - a On a Windows 2003 Server host, choose **Start > Programs > Administrative Tools > Routing and Remote Access**.
 An icon on the left is labeled with the host name. If a green dot appears over the icon, IP forwarding is turned on.
 - b To turn off IP forwarding, right-click the icon and disable **Routing and Remote Access**.
 A red dot appears, indicating that IP forwarding is disabled.

Disable Packet Forwarding on Linux Hosts

If you find packets leaking from a host-only network on a Linux host computer, check whether forwarding was mistakenly enabled on the host machine. If it is enabled, disable it.

To disable packet forwarding on Linux hosts

Depending on which type of Linux system you have, use one of the following methods:

- Disable forwarding by writing a 0 (zero) to the special file `/proc/sys/net/ipv4/ip_forward`. As root (`su-`), enter the following command:


```
echo "0" > /proc/sys/net/ipv4/ip_forward
```
- Use a configuration option that is appropriate for your Linux distribution. For example, you might use a control panel, specify a setting at the time you compile your kernel, or enter a specification when you boot your system.

For details about the method to use with your distribution, consult your operating system documentation.

Maintaining and Changing the MAC Address of a Virtual Machine

When a virtual machine is powered on, Workstation assigns each of its virtual network adapters an Ethernet media access control (MAC) address. A MAC address is the unique address assigned to each Ethernet network device.

The software guarantees that virtual machines are assigned unique MAC addresses within a given host system. The virtual machine is assigned the same MAC address every time it is powered on if both of the following conditions are true:

- The virtual machine is not moved. That is, the path name and filename for the virtual machine's configuration file remain the same.
- No changes are made to certain settings in the configuration file.

However, Workstation cannot guarantee to automatically assign unique MAC addresses for virtual machines that run on multiple host systems.

Avoiding MAC Address Changes

To avoid changes in the MAC address automatically assigned to a virtual machine, do not move the virtual machine's configuration file. Moving it to a different host computer or even moving it to a different location on the same host computer changes the MAC address.

Do not change certain settings in the virtual machine's configuration (.vmx) file. If you never edit the configuration file by hand and do not remove the virtual network adapter, these settings remain unchanged. If you do edit the configuration file by hand, do not remove or change the following options:

```
ethernet[n].generatedAddress
ethernet[n].addressType
ethernet[n].generatedAddressOffset
uuid.location
uuid.bios
ethernet[n].present
```

In these options, [n] is the number of the virtual network adapter, for example 0.

NOTE To preserve a virtual network adapter's MAC address, you must be careful not to remove the adapter. If you remove the adapter but later re-create it, the adapter might receive a different MAC address.

Assign the Same MAC Address to Any Virtual Machine Manually

Assign the MAC address manually instead of allowing Workstation to assign it to guarantee the following:

- The same MAC address is assigned to a given virtual machine every time you power it on, even if the virtual machine is moved.
- A unique MAC address is provided for each virtual machine within a networked environment.

To assign the same MAC address to any virtual machine manually

- 1 Use a text editor to remove from the configuration (.vmx) file the three lines that begin with the following:

```
ethernet[n].generatedAddress
ethernet[n].addressType
ethernet[n].generatedAddressOffset
```

In these options, [n] is the number of the virtual network adapter, for example, 0.

On a Linux host, a virtual machine created with an earlier VMware product might have a configuration file with a .cfg extension.

- 2 Add the following line to the configuration file above the UUID lines in the file:

```
ethernet[n].address = 00:50:56:XX:YY:ZZ
```

In this line, the fourth pair of numbers, **XX**, must be a valid hexadecimal number between 00h and 3Fh, and **YY** and **ZZ** must be valid hexadecimal numbers between 00h and FFh. You must use the above format because Workstation virtual machines do not support arbitrary MAC addresses.

A value for **XX:YY:ZZ** that is unique among your hard-coded addresses avoids conflicts between the automatically assigned MAC addresses and the manually assigned addresses.

Controlling Routing Information for a Host-Only Network on Linux

A host-only network is a full-fledged network. It has a network interface associated with it (vmnet1) that is marked **up** at the time the host operating system is booted. Routing server processes that operate on the host operating system, such as **routed** and **gated**, automatically discover the host-only network and propagate information on how to reach the network unless you explicitly configure them not to do so.

If either of these processes is being run only to receive routing information, the easiest solution is to run the routing configuration with a **-q** option so that the host-only network does not supply but only receives routing information.

If, however, routing services are running because they are to supply routing information, configure them so that they do not advertise routes to the host-only network.

The version of **routed** included with many distributions of Linux has no support for specifying that an interface should not be advertised. Consult the **routed(8)** manual page for your system.

For **gated**, configuration you must explicitly exclude the vmnet1 interface from any protocol activity. If you need to run virtual machines on a host-only network on a multihomed system where **gated** is used and have problems doing so, contact VMware technical support by submitting a support request on the VMware Web site.

Potential Issues with Host-Only Networking on Linux

The following are common issues you might encounter when you are configuring a host-only network on Linux.

DHCPD on the Linux Host Does Not Work After Installing Workstation

If you were running the DHCP server `dhcpd` utility on your machine before you installed Workstation, it probably was configured to respond to DHCP requests from clients on any network interface present on the machine. When host-only networking is configured, an additional network interface, `vmnet1`, is marked **up** and available for use, and `dhcpd` might notice this.

In such cases, some `dhcpd` implementations abort if their configuration files do not include a subnet specification for the interface. This can happen even if `dhcpd` is not supposed to respond to messages that arrive through the interface.

The best solution is to add a line to the `dhcpd` configuration file in the following format:

```
subnet <net>.0 netmask 255.255.255.0 {}
```

Here `<net>` is the network number assigned to your host-only network, for example, 192.168.0. This line in the configuration file informs `dhcpd` about the host-only network and tells it explicitly not to respond to any DHCP requests arriving from it.

An alternative solution is to explicitly state the set of network interfaces for `dhcpd` to monitor each time you start the program. For example, if your machine has one Ethernet interface, `eth0`, each time you start `dhcpd`, list the interface on the command line:

```
dhcpd eth0
```

This prevents `dhcpd` from searching for all available network interfaces.

If these solutions do not work for your DHCP server program, it might be an old DHCP server. You can try upgrading to a more current version of DHCP available from the Internet Systems Consortium (ISC) Web site.

DHCP and DDNS

Use DHCP to supply IP addresses as well as other information, such as the identity of a host running a name server and the nearest router or gateway. The DHCP server in Workstation does not provide a means to dynamically establish a relationship between the IP address it assigns and a client's name (that is, to update a DNS server using dynamic domain name service (DDNS)).

To use names to communicate with other virtual machines, you must either edit the DHCP configuration file for vmnet1 (/etc/vmware/vmnet1/dhcpd/dhcpd.conf), or use IP addresses that are statically bound to a host name. Editing the DHCP server configuration file requires information that is best obtained directly from the DHCP server documentation. Consult the dhcpd(8) and dhcpd.conf(8) manual pages.

NOTE The edits made inside the read-only section of the DHCP configuration file are lost the next time you run the network editor.

Configuring Host-Only Virtual Machines

If you have already created two host-only interfaces (VMnet1 and VMnet2), you can set up your virtual machines for one of the following configurations:

- **Configuration 1** – The virtual machine is configured with one virtual network adapter, and that virtual adapter is connected to the default host-only interface (VMnet1). To use this configuration, see [“Set Up Using Configuration 1 or 2”](#) on page 312.
- **Configuration 2** – The virtual machine is configured with one virtual network adapter, and that virtual adapter is connected to the newly created host-only interface (VMnet2). To use this configuration, see [“Set Up Using Configuration 1 or 2”](#) on page 312.
- **Configuration 3** – The virtual machine is configured with two virtual network adapters. One virtual adapter is connected to the default host-only interface (VMnet1) and the other virtual adapter is connected to the newly created host-only interface (VMnet2). To use this configuration, see [“Set Up Using Configuration 3”](#) on page 313.

Set Up Using Configuration 1 or 2

Use the virtual machine settings editor to connect the virtual machine to the default host-only adapter or a custom host-only adapter.

To set up using configuration 1 or 2

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select **Network Adapter**.

- 4 In the **Network Connection** section, do one of the following:
 - To connect to the default host-only interface (VMnet1), select **Host-only**.
 - To connect to the newly created host-only interface, select **Custom**, and choose **VMnet2** from the drop-down menu on the right.
- 5 (Optional) If no network adapter is shown in the list of devices, add one, as described in [“Add Virtual Network Adapters”](#) on page 295.

Set Up Using Configuration 3

Make sure that there are two network devices for this virtual machine. For more information on adding virtual network adapters, see [“Add Virtual Network Adapters”](#) on page 295.

To set up using configuration 3

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, select the first **Network Adapter**.
- 5 In the **Network Connection** section, select **Host-only**.
This adapter is connected to the default host-only interface (VMnet1).
- 6 Select the second network adapter in the list, and in the **Network Connection** section, select **Custom** and choose **VMnet2** from the drop-down menu.

Complete Configuring the Virtual Network Adapters

To complete the configuration you must assign an IP address on the appropriate VMnet subnet to each virtual network adapter as you would for physical adapters on a physical computer.

To complete configuring the virtual network adapters

- 1 Power on the virtual machine and install your guest operating system.
In configurations 1 and 2, you see one network adapter. In configuration 3, you see two network adapters within the guest.
- 2 Assign IP addresses to the virtual network adapters.

- 3 (Optional) To see the IP address that a host-only network is using:
 - On Windows hosts, open a command prompt and run the following command:


```
ipconfig /all
```
 - On Linux hosts, open a terminal and run the following command:


```
ifconfig
```

Set Up Routing Between Two Host-Only Networks

If you are setting up a complex test network that uses virtual machines, you might want to have two independent host-only networks with a router between them.

Use one of the following methods. In both cases, you need two host-only interfaces.:

- The router software runs on the host computer.
- The router software runs on its own virtual machine.

The examples described here outline the simplest case, with one virtual machine on each of the host-only networks. For more complex configurations, you can add more virtual machines and host-only networks, as appropriate.

To set up routing between two host-only networks

- 1 Set up the connection to the first (default) host-only interface, as described in [“Set Up Using Configuration 1 or 2”](#) on page 312.
- 2 Set up the connection to the second (VMnet2) host-only interface, as described in [“Set Up Using Configuration 1 or 2”](#) on page 312.
- 3 (Optional) To run the router software on a virtual machine, set up a third virtual machine with connections to the two host only interfaces, as described in [“Set Up Using Configuration 3”](#) on page 313.

To run the router software on your host computer, skip this step.

- 4 Stop the VMnet DHCP server service:
 - On a Windows host, choose **Edit > Virtual Network Editor > DHCP**, select the service and click **Stop**.
 - On a Linux host, open a terminal and use the following command to stop the `vmnet-dhcpd` service:

```
killall -TERM vmnet-dhcpd
```

- 5 Install guest operating systems in each of the virtual machines.

- 6 Install the router software, either on the host computer or in the third virtual machine, depending on the approach you are using.
- 7 Configure networking in the first two virtual machines to use addresses on the appropriate host-only network:
 - On Windows hosts, open a command prompt and run the `ipconfig /all` command to determine which IP addresses each host-only network is using.
 - On Linux hosts, open a terminal and run the `ifconfig` command to determine which IP addresses each host-only network is using.
- 8 Assign IP addresses by doing one of the following:

- If you are running the router on the host computer, assign default router addresses based on the addresses of the host-only adapters on the host computer.

In the first virtual machine's networking configuration, the default router address should be the IP address for the host-only adapter connected to VMnet1. In the second virtual machine's networking configuration, the default router address should be the IP address for the host-only adapter connected to VMnet2.

- If you are running the router software in a third virtual machine, set the default router addresses in the first two virtual machines based on the addresses that the third virtual machine uses.

In the first virtual machine's networking configuration, the default router address should be the IP address for the third virtual machine's network adapter connected to VMnet1. In the second virtual machine's networking configuration, the default router address should be the IP address for the third virtual machine's network adapter connected to VMnet2.

You can now ping the router machine from virtual machines 1 and 2. If the router software is set up correctly, you can communicate between the first and second virtual machines.

Using Virtual Network Adapters in Promiscuous Mode on a Linux Host

Workstation does not allow the virtual network adapter to go into promiscuous mode unless the user running Workstation has permission to make that setting. This restriction follows the standard Linux practice that only the root user can put a network interface into promiscuous mode.

When you install and configure Workstation, you must run the installation as the root user. Workstation creates the vmnet devices with root ownership and root group ownership, which means that only the root user has read and write permissions to the devices.

To set the virtual machine's network adapter to promiscuous mode, you must launch Workstation as the root user because you must have read and write access to the vmnet device. For example, if you are using bridged networking, you must have access to `/dev/vmnet0`.

To grant selected other users read and write access to the vmnet device, you can create a new group, add the appropriate users to the group, and grant that group read and write access to the appropriate device. You must make these changes on the host operating system as the root user (`su -`). For example, you can enter the following commands:

```
chgrp <newgroup> /dev/vmnet0
chmod g+rw /dev/vmnet0
```

Here `<newgroup>` is the group that should be able to set `vmnet0` to promiscuous mode.

For all users to be able to set the virtual network adapter (`/dev/vmnet0` in the example) to promiscuous mode, run the following command on the host operating system as the root user:

```
chmod a+rw /dev/vmnet0
```

Using NAT

NAT provides a way for virtual machines to use most client applications over almost any type of network connection available to the host. The only requirement is that the network connection must support TCP/IP.

NAT is useful when you have a limited supply of IP addresses or are connected to the network through a non-Ethernet network adapter. NAT works by translating addresses of virtual machines in a private VMnet network to the address of the host machine. When a virtual machine sends a request to access a network resource, it appears to the network resource as if the request is coming from the host machine.

The host computer has a host virtual adapter on the NAT network identical to the host virtual adapter on the host-only network. This adapter allows the host and the virtual machines to communicate with each other for such purposes as file sharing. The NAT device never forwards traffic from the host virtual adapter.

How the NAT Device Uses the VMnet8 Virtual Switch

The NAT device is connected to the VMnet8 virtual switch. Virtual machines connected to the NAT network also use the VMnet8 virtual switch.

The NAT device waits for packets coming from virtual machines on the VMnet8 virtual network. When a packet arrives, the NAT device translates the address of the virtual machine to the address of the host before forwarding the packet to the external network. When data arrives from the external network for the virtual machine on the private network, the NAT device receives the data, replaces the network address with the address of the virtual machine and forwards the data to the virtual machine on the virtual network. This translation occurs automatically and requires minimal configuration on the guest and the host.

DHCP on the NAT Network

To make networking configuration easy, a DHCP server is installed when you install Workstation. Virtual machines running on the network with the NAT device can send out DHCP requests to dynamically obtain their IP addresses.

The DHCP server on the NAT network, which is also used in host-only networking configurations, dynamically allocates IP addresses in the range of <net>.128 through <net>.254, where <net> is the network number assigned to your NAT network. Workstation always uses a Class C address for NAT networks. IP addresses <net>.3 through <net>.127 can be used for static IP addresses. IP address <net>.1 is reserved for the host adapter and <net>.2 is reserved for the NAT device. For more information, see [“DHCP Conventions for Assigning IP Addresses”](#) on page 305.

In addition to the IP address, the DHCP server on the NAT network sends out configuration information that enables the virtual machine to operate. This information includes the default gateway and the DNS server. In the DHCP response, the NAT device instructs the virtual machine to use the IP address <net>.2 as the default gateway and DNS server. This routing causes all IP packets destined for the external network and DNS requests to be forwarded to the NAT device.

DNS on the NAT Network

The NAT device acts as a DNS server for the virtual machines on the NAT network. The NAT device is a DNS proxy and forwards DNS requests from the virtual machines to a DNS server that the host knows. Responses return to the NAT device, which then forwards them to the virtual machines.

If they get their configuration information from DHCP, the virtual machines on the NAT network automatically use the NAT device as the DNS server. However, the virtual machines can be statically configured to use another DNS server.

The virtual machines in the private NAT network are not accessible through DNS. To have the virtual machines running on the NAT network access each other by DNS names, you must set up a private DNS server connected to the NAT network.

External Access from the NAT Network

A virtual machine on the NAT network can use any protocol using TCP or UDP as long as the virtual machine initiates the network connection. This is true for most client applications such as Web browsing, Telnet, passive-mode FTP, and downloading streaming video. Additional protocol support is built into the NAT device to allow FTP and ICMP echo (ping) to work transparently through the NAT.

On the external network to which the host is connected, any virtual machine on the NAT network appears to be the host itself, because its network traffic uses the host's IP address. The virtual machine can send and receive data using TCP/IP to any machine that is accessible from the host.

Before any communication can occur, the NAT device must set up a map between the virtual machine's address on the private NAT network and the host's network address on the external network.

When a virtual machine initiates a network connection with another network resource, this map is created automatically. The operation is transparent to the user of the virtual machine on the NAT network. No additional work needs to be done.

Network connections that are initiated from outside the NAT network to a virtual machine on the NAT network are not transparent. When a machine on the external network attempts to initiate a connection with a virtual machine on the NAT network, it cannot reach the virtual machine because the NAT device does not forward the request.

However, you can configure port forwarding manually on the NAT device so that network traffic destined for a certain port can still be forwarded automatically to a virtual machine on the NAT network. See [“Advanced NAT Configuration”](#) on page 319.

File sharing of the type used by Windows operating systems and Samba is possible among computers on the NAT network, including virtual machines and the host computer. If you are using WINS servers on your network, a virtual machine using NAT networking can access shared files and folders on the host that the WINS server knows if those shared files and folders are in the same workgroup or domain.

Advanced NAT Configuration

You can configure NAT to make custom configuration settings for Windows and Linux.

Configure NAT on a Windows Host

Use the virtual network settings to configure NAT on a Windows host. To edit the NAT configuration file, see [“Custom NAT and DHCP Configuration on a Windows Host”](#) on page 319.

To configure NAT on a Windows host

- 1 Choose **Edit > Virtual Network Editor**.
- 2 Use the controls in the **NAT Settings** menu to configure NAT:
 - To stop and start the virtual NAT device, click the appropriate buttons.
 - To edit NAT settings for a virtual network, choose the VMnet network from the drop-down menu and click **Edit**.
- 3 Click DNS Settings to set up or change port forwarding or to specify DNS servers that the virtual NAT device should use.
- 4 Click **OK**.

Custom NAT and DHCP Configuration on a Windows Host

If you are an advanced user on a Windows host computer, you can edit the NAT and DHCP configuration files to make custom configuration settings. If your host operating system is installed on the C drive, the configuration files for NAT and DHCP are in the following locations:

Table 15-3. NAT and DHCP File Locations

File Type	Location
NAT	On Windows XP: C:\Documents and Settings\All Users\Application Data\VMware\vmnetnat.conf On Windows Vista and Windows 7: C:\ProgramData\VMware\vmnetnat.conf For more information about this file, see “Contents of the NAT Configuration File” on page 321.
DHCP	On Windows XP: C:\Documents and Settings\All Users\Application Data\VMware\vmnetdhcp.conf On Windows Vista and Windows 7: C:\ProgramData\VMware\vmnetdhcp.conf

Use the virtual network editor (**Edit > Virtual Network Editor**) to change many key NAT and DHCP settings.

If you make manual changes to the configuration files, those changes might be lost when you use the virtual network editor. Make backup copies of the files before you change any settings in the virtual network editor. You can then copy your manual changes back into the appropriate configuration files.

Specifying Connections from Ports Below 1024

When a client machine makes a TCP or UDP connection to a server, the connection comes from a particular port on the client (the source port) and connects to a particular port on the server (the destination port). For security reasons, some servers accept connections only from source ports below 1024. You might see this configuration on machines used as NFS file servers, for example.

If a virtual machine using NAT attempts to connect to a server that requires the client to use a source port below 1024, the NAT device must forward the request from a port below 1024. You can specify this behavior in the `vmnetnat.conf` file.

This behavior is controlled by entries in sections headed `[privilegedUDP]` and `[privilegedTCP]`. You might need to add settings to or modify settings in either or both of these sections, depending on the kind of connection you need to make.

You can set two parameters, each of which appears on a separate line.

Table 15-4. Parameters to Map Virtual Machine Source and Destination Ports

Parameter	Description
autodetect = <n>	The autodetect setting determines whether the VMware NAT device automatically attempts to map virtual machine source ports below 1024 to NAT source ports below 1024. A setting of 1 means true. A setting of 0 means false. On a Windows host, the default is 1 (true). On a Linux host, the default is 0 (false).
port = <n>	The port setting specifies a destination port (where <n> is the port on the server that accepts the connection from the client). Whenever a virtual machine connects to the specified port on any server, the NAT device attempts to make the connection from a source port below 1024. You can include one or more port settings in the [privilegedUDP] or [privilegedTCP] section or in both sections, as required for the connections you need to make. Enter each port setting on a separate line.

Configuring NAT on a Linux Host

Use the default NAT configuration file on the host to configure the NAT device. This file is located in `/etc/vmware/vmnet8/nat/nat.conf`.

For an example of a NAT configuration file, see [“Sample Linux nat.conf File”](#) on page 327.

Contents of the NAT Configuration File

The NAT configuration file is in the following locations:

- On a Windows host:
C:\Documents and Settings\All Users\Application Data\VMware\vmnetnat.conf
If you edit this file and then use the virtual network editor (**Edit > Virtual Network Editor**) your edits might be lost.
- On a Linux host:
`/etc/vmware/vmnet8/nat/nat.conf`

The NAT configuration file is divided into sections. Each section configures a part of the NAT device. Text surrounded by square brackets, such as [dns], marks the beginning of a section. In each section is a configuration parameter that can be set.

The configuration parameters take the form `ip = 192.168.27.1/24`. The NAT configuration file contains the following sections.

The [host] Section

The [host] section includes parameters to configure the NAT connection.

- **ip** – The IP address that the NAT device should use. It can be followed by a slash and the number of bits in the subnet.
- **netmask** – The subnet mask to use for the NAT network. DHCP addresses are allocated from this range of addresses.
- **configport** – A port that can be used to access status information about the NAT device.
- **device** – The VMnet device to use. Windows devices are of the form `vmnet<x>` where `<x>` is the number of the VMnet. Linux devices are of the form `/dev/vmnet<x>`.
- **activeFTP** – Flag to indicate if active FTP is to be allowed. Active FTP allows incoming connections to be opened by the remote FTP server. Turning this off means that only passive mode FTP works. Set this flag to 0 to turn it off.

The [udp] Section

timeout – Number of seconds to keep the UDP mapping for the NAT network.

The [dns] Section

The [dns] section is for Windows hosts only. Linux does not use this section.

- **policy** – Policy to use for DNS forwarding. Accepted values include:
 - **order** – Send one DNS request at a time in the order of the name servers.
 - **rotate** – Send one DNS request at a time and rotate through the DNS servers.
 - **burst** – Send to three servers and wait for the first one to respond.
- **timeout** – Time in seconds before retrying a DNS request.
- **retries** – Number of retries before the NAT device stops trying to respond to a DNS request.
- **autodetect** – Flag to indicate whether the NAT device should detect the DNS servers available to the host.
- **nameserver1** – IP address of a DNS server to use.

- `nameserver2` – IP address of a DNS server to use.
- `nameserver3` – IP address of a DNS server to use.

If `autodetect` is on and some name servers are specified, the DNS servers specified in `nameserver1`, `nameserver2`, and `nameserver3` are added before the list of detected DNS servers.

The `[netbios]` Section

The `[netbios]` section applies to Windows hosts only. Linux does not use this section.

- `nbnsTimeout` = 2 – Timeout, in seconds, for NBNS queries.
- `nbnsRetries` = 3 – Number of retries for each NBNS query.
- `nbdsTimeout` = 3 – Timeout, in seconds, for NBDS queries.

The `[incomingtcp]` Section

Use the `[incomingtcp]` section to configure TCP port forwarding for NAT. In this section, you can assign a port number to an IP address and port number on a virtual machine.

The following line shows the format used in this section:

```
8887 = 192.168.27.128:21
```

This example creates a map from port 8887 on the host to the IP address 192.168.27.128 and port 21. When this map is set and an external machine connects to the host at port 8887, the network packets are forwarded to port 21 (the standard port for FTP) on the virtual machine with IP address 192.168.27.128.

The `[incomingudp]` Section

Use the `[incomingudp]` section to configure UDP port forwarding for NAT. In this section, you can assign a port number to an IP address and port number on a virtual machine.

The following line shows the format used in this section. It illustrates a way to forward X server traffic from the host port 6000 to the virtual machine's port 6001:

```
6000 = 192.168.27.128:6001
```

This example creates a map from port 6000 on the host to the IP address 192.168.27.128 and port 6001. When this map is set and an external machine connects to the host at port 6000, the network packets are forwarded to port 6001 on the virtual machine with IP address 192.168.27.128.

Considerations for Using NAT

Consider the following items when you use NAT:

- NAT causes some performance loss.

Because NAT requires that every packet sent to and received from a virtual machine must be in the NAT network, an unavoidable performance penalty occurs.

- NAT is not perfectly transparent.

NAT does not usually allow connections to be initiated from outside the network, although you can manually configure the NAT device to set up server connections. The practical result is that some TCP and UDP protocols that require a connection be initiated from the server machine, some peer to peer applications, for example, do not work automatically, and some might not work at all.

- NAT provides some firewall protection.

A standard NAT configuration provides basic-level firewall protection because the NAT device can initiate connections from the private NAT network, but devices on the external network usually cannot initiate connections to the private NAT network.

Using NAT with NetLogon

When you use NAT networking in a virtual machine with a Windows guest operating system running on a Windows host, you can use NetLogon to log in to a Windows domain from the virtual machine. You can then access file shares that the WINS server knows.

To use NetLogon, you need to know how WINS servers and Windows domain controllers work. This section explains how to set up the virtual machine to use NetLogon. The setup process is similar to the way you set up a physical computer on one LAN that is using a domain controller on another LAN.

To log in to a Windows domain outside the virtual NAT network, the virtual machine needs access to a WINS server for that domain. You can connect the virtual machine to a WINS server in the following ways:

- Connect to the WINS server that the DHCP server used on the NAT network provides, if the WINS server is already set up on the host.
- Manually enter the IP address of the WINS server to connect from the virtual machine to a WINS server not set up on the host.

Use NAT to Connect to an Existing WINS Server Set Up on the Host

To use NAT to connect, a WINS server in the same workgroup or domain must be set up on the host. This procedure applies to the Windows 2000, XP, 2003 Server, NT, Me, and 9x guest versions.

Differences for Windows Vista and Windows 7, are noted in the specific steps.

To use NAT to connect to an existing WINS server set up on the host

- 1 In the virtual machine, right-click **My Network Places** and choose **Properties**.
 - For Windows Vista, open the Network and Sharing Center and click the **View Status** link for the connection that uses the needed virtual network adapter.
 - For Windows 7, open the Network and Sharing Center and click one of the **Local Area Connection** links for the connection that uses the needed virtual network adapter.
- 2 In the Network Connections window, right-click the virtual network adapter and choose **Properties**.
 - For Windows Vista, in the Local Area Connection Status window, click **Properties** and click **Continue** when prompted for permission.
 - For Windows 7, in the Local Area Connection Status window, click **Properties**.
- 3 In the Properties dialog box, select **Internet Protocol (TCP/IPv4)** and click **Properties**.
- 4 In the TCP/IP Properties dialog box, click **Advanced**.
- 5 On the **WINS** tab, under **NetBIOS** setting, select **Default: Use NetBIOS setting from DHCP Server**.
- 6 Click **OK** twice and click **Close**.

Enter the IP Address of a WINS Server Manually

Use the IP address to connect to a WINS server in the same workgroup or domain that is not already set up on the host.

To enter the IP address of a WINS server manually

- 1 In the virtual machine, right-click **My Network Places** and choose **Properties**.
 - For Windows Vista, open the Network and Sharing Center and click the **View Status** link for the connection that uses the needed virtual network adapter.
 - For Windows 7, open the Network and Sharing Center and click one of the **Local Area Connection** link for the connection that uses the needed virtual network adapter.
- 2 In the Network Connections window, right-click the virtual network adapter and choose **Properties**.
 - For Windows Vista, in the Local Area Connection Status window, click **Properties** and click **Continue** when prompted for permission.
 - For Windows 7, in the Local Area Connection Status window, click **Properties**.
- 3 In the Properties dialog box, select **Internet Protocol (TCP/IPv4)** and click **Properties**.
- 4 In the TCP/IP Properties dialog box, click **Advanced**.
- 5 On the **WINS** tab, click **Add**.
- 6 In the TCP/IP WINS Server dialog box, enter the IP address for the WINS server in the WINS server field and click **Add**.

The IP address of the WINS server appears in the WINS addresses list on the **WINS** tab.
- 7 Repeat [Step 5](#) and [Step 6](#) for each WINS server to which you want to connect from this virtual machine.
- 8 Click **OK** twice and click **Close**.

Now that the virtual machine has an IP address for a WINS server, you can use NetLogon in the virtual machine to log in to a domain and access shares in that domain. However, your access is limited to shares of virtual machines that are on the same NAT network or are bridged on the same domain.

For example, if the WINS server covers a domain with a domain controller, you can access that domain controller from the virtual machine and add the virtual machine to the domain. You need to know the Administrator user ID and password for the domain controller.

Sample Linux nat.conf File

```
# Linux NAT configuration file

[host]

# NAT gateway address
ip = 192.168.237.2/24
hostMAC = 00:50:56:C0:00:08

# enable configuration; disabled by default for security reasons
#configport = 33445

# vmnet device if not specified on command line
device = vmnet8

# Allow PORT/EPRT FTP commands (they need incoming TCP stream...)
activeFTP = 1

# Allows the source to have any OUI. Turn this one if you change the OUI
# in the MAC address of your virtual machines.
#allowAnyOUI = 1

[udp]
# Timeout in seconds, 0 = no timeout, default = 60; real value might
# be up to 100% longer
timeout = 30

[dns]
# This section applies only to Windows.
#
# Policy to use for DNS forwarding. Accepted values include order,
# rotate, burst.
#
# order: send one DNS request at a time in order of the name servers
# rotate: send one DNS request at a time, rotate through the DNS servers
# burst: send to three servers and wait for the first one to respond
policy = order;

# Timeout in seconds before retrying DNS request.
timeout = 2

# Retries before giving up on DNS request
retries = 3

# Automatically detect the DNS servers (not supported in Windows NT)
autodetect = 1

# List of DNS servers to use. Up to three may be specified
#nameserver1 = 208.23.14.2
```

```

#nameserver2 = 63.93.12.3
#nameserver3 = 208.23.14.4

[netbios]
# This section applies only to Windows.

# Timeout for NBNS queries.
nbnsTimeout = 2

# Number of retries for each NBNS query.
nbnsRetries = 3

# Timeout for NBDS queries.
nbdsTimeout = 3

[incomingtcp]
# Use these with care – anyone can enter into your virtual machine through
# these...

# FTP (both active and passive FTP is always enabled)
#   ftp localhost 8887
#8887 = 192.168.27.128:21

# WEB (make sure that if you are using named webhosting, names point to
#   your host, not to guest... And if you are forwarding port other
#   than 80 make sure that your server copes with mismatched port
#   number in Host: header)
#   lynx http://localhost:8888
#8888 = 192.168.27.128:80

# SSH
#   ssh -p 8889 root@localhost
#8889 = 192.168.27.128:22

[incomingudp]
# UDP port forwarding example
#6000 = 192.168.27.128:6001

```

Using Samba with Workstation

If you have Samba on your Linux host, you can configure Samba so that it works with Workstation.

Modify your Samba configuration so that it includes the IP subnet that the vmnet1 Workstation virtual network adapter uses. To determine which subnet vmnet1 is using, run the following command:

```
/sbin/ifconfig vmnet1
```

Make sure the Samba password file includes entries for all users of the virtual machine who will access the host's file system. The user names and passwords in the Samba password file must match those used for logging on to the guest operating system.

Add Users to the Samba Password File

You can add user names and passwords to the Samba password file at any time from a terminal window on your Linux host computer.

To add users to the Samba password file

- 1 Log in to the root account:

`su`
- 2 Run the Samba password command:

`smbpasswd -a <username>`

Here <username> is the user name to add.
- 3 Follow the instructions on the screen.
- 4 Log out of the root account:

`exit`

Using a Samba Server for Bridged and Host-Only Networks

To use your Samba server for host-only and bridged networking, you must modify one parameter in the `smb.conf` file. You can define the `interface` parameter so that your Samba server serves multiple interfaces. An example of this is the following:

```
interface = eth0 vmnet1
```

This example tells the Samba server to monitor and use both the `eth0` and `vmnet1` interfaces, which are the interfaces that bridged and host-only networking use, respectively.

Use Samba Without Network Access

To make Samba inaccessible from your physical network interface, you must configure the configuration file.

To use Samba without network access

- 1 Open the configuration file:
`/etc/samba/smb.conf`
- 2 Add the following line to the configuration file and save the changes.
`interfaces = vmnet*`
- 3 Restart Samba.

Connecting Devices

This chapter describes how to use various devices with a virtual machine.

This chapter includes the following topics:

- [“Using Parallel Ports”](#) on page 331
- [“Using Serial Ports”](#) on page 335
- [“Configuring Keyboard Features”](#) on page 339
- [“Using USB Devices in a Virtual Machine”](#) on page 351
- [“Use Smart Cards with Virtual Machines”](#) on page 358
- [“Support for Generic SCSI Devices”](#) on page 361
- [“Use Four-Way Virtual Symmetric Multiprocessing”](#) on page 366

Using Parallel Ports

Parallel ports are used by a variety of devices, including printers, scanners, dongles, and disk drives. Although these devices can connect to the host without problems, only printers can reliably connect to virtual machines by using parallel ports.

Currently, Workstation provides only partial emulation of PS/2 hardware. Interrupts that a device connected to the physical port requests are not passed to the virtual machine. The guest operating system cannot use DMA (direct memory access) to move data to or from the port. For this reason, not all devices that attach to the parallel port are guaranteed to work correctly. Do not use parallel port storage devices in a virtual machine.

Add a Virtual Parallel Port to a Virtual Machine

If the virtual machine is configured with a parallel port, most guest operating systems detect the port at installation time and install the required drivers. Some operating systems, including Linux, Windows NT, and Windows 2000, automatically detect the ports at boot time. Others, like Windows 95 and Windows 98, do not.

To add a virtual parallel port to a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, click **Add**.
- 5 In the New Hardware wizard, select **Parallel Port** and click **Next**.
- 6 Specify which option to use for the parallel port:
 - If you select **Use physical parallel port**, click **Next** and choose the port from the drop-down menu.
 - If you select **Output file**, click **Next** and enter the path and filename or browse to the location of the file.
- 7 Under **Device status**, if you do not want the parallel port to connect at power on, deselect the check box.
- 8 Click **Finish**.
- 9 If the guest operating system is Windows 95 or Windows 98, run the guest operating system's Add New Hardware wizard to let Windows detect the new device.

To display this wizard, choose **Start > Settings > Control Panel > Add New Hardware**.

Troubleshoot ECR Errors for Parallel Ports

When you power on the virtual machine after adding a parallel port, you might see an error message stating that the parallel port on the host does not have an Extended Control Register (ECR). If so, it is possible the hardware supports ECR but it has been disabled in the BIOS.

To troubleshoot ECR errors for parallel ports

- 1 Reboot the host.
- 2 Early in the boot process, press and hold down the Delete key to enter the host computer's BIOS configuration editor.
- 3 Find the parallel port field and enable Extended Capability Port (ECP) mode or a combination of modes that includes ECP.

Most modern computers support ECP mode.

Configuring a Parallel Port on a Linux Host

For a parallel port to work properly in a guest, it must first be configured properly on the host. Most problems with parallel ports are caused by mistakes in the host configuration.

Linux kernels in the 2.6.x series use a special arbitrator for access to the parallel port hardware. If the host is using the parallel port, the virtual machine cannot use it. If a virtual machine is using the parallel port, the host and any users accessing the host are denied access to the device. You must use the **VM > Removable Devices** menu to disconnect the parallel port from the virtual machine to access the device from the host.

Configure Parallel Ports for Linux 2.6.x Kernels

The 2.6.x kernels that support parallel ports use the `modprobe <modulename>` and `modprobe parport_pc` modules. Workstation requires that the parallel port PC-style hardware option (`CONFIG_PARPORT_PC`) be built and loaded as a kernel module. That is, it must be set to `m`.

To configure parallel ports for Linux 2.6.x kernels

- 1 To determine whether the `modprobe <modulename>` and `modprobe parport_pc` modules are installed and loaded on your system, run the `lsmod` command as the root user.

You can also look at the `/proc/modules` file for the list.

With 2.6.x, loading `parport_pc` does not load all modules.

- 2 If none of the listed parallel port modules is loaded, use the following command:

```
modprobe parport_pc && modprobe ppdev
```

This command inserts the modules needed for a parallel port.

If problems persist, the `lp` module might be loaded. If it is, the virtual machine cannot use the parallel port correctly.

- 3 If the `lp` module is loaded, run the following command as root to remove it:

```
rmmod lp
```

- 4 To verify that the line referring to the `lp` module in the `/etc/modules.conf` or `/etc/conf.modules` file is removed or commented out, insert a pound sign (`#`) at the beginning of the line.

The name of the configuration file depends on the Linux distribution you are using. When you reboot the host after removing this line, the configuration file no longer starts the `lp` module.

- 5 To ensure that the proper modules for the parallel port are loaded at boot time, add the following line to the `/etc/modules.conf` or `/etc/conf.modules` file:

```
alias parport_lowlevel parport_pc
```

Configure Device Permissions for Parallel Ports

Some Linux distributions by default do not grant the virtual machine access to the `lp` and `parport` devices. You must add the VMware user to the group that has permission to access these devices.

To configure device permissions for parallel ports

- 1 Run the following command to determine the owner and group for the device:

```
ls -la /dev/parport0
```

The third and fourth columns of the output show the owner and group, respectively. In most cases, the owner of the device is `root` and the associated group is `lp`.

- 2 To add the user to the device group, become the root user and open the `/etc/group` file with a text editor.
- 3 On the line starting with `lp`, which defines the `lp` group, add the Workstation user's user name.

The following line provides an example for a user whose user name is `userj`.

```
lp::7:daemon,lp,userj
```

The next time the user logs on to the host, the changes take effect.

Using Serial Ports

A Workstation virtual machine can use up to four virtual serial ports. The virtual serial ports can be configured in several ways:

- Connect a virtual serial port to a physical serial port on the host computer.
- Connect a virtual serial port to a file on the host computer.
- Make a direct connection between two virtual machines or between a virtual machine and an application running on the host computer.

For each of these choices, you can also select whether to connect the virtual serial port when you power on the virtual machine.

NOTE The virtual printer feature automatically configures a serial port to make host printers available to the guest without installing additional drivers in the virtual machine. See [“Use Host Printers in a Virtual Machine”](#) on page 180.

Add a Virtual Serial Port to a Virtual Machine

Use virtual serial ports to make devices such as modems and printers available to virtual machines or to send debugging data from a virtual machine to the host or to another virtual machine.

You can use virtual serial ports to send data to the following:

- **Physical serial port** – Enables you to use a device such as an external modem or hand-held device in a virtual machine. Workstation creates a virtual serial port automatically when you enable the virtual printer feature.
- **Output file on the host** – Captures the data that a program running in the virtual machine sends to the virtual serial port.
- **An application on the host** – Enables you to use an application on the host to capture debugging information sent from the virtual machine’s serial port.
- **Another virtual machine** – Enables you to use an application in one virtual machine (the client) to capture debugging information sent from the other (the server) virtual machine’s serial port.

To add a virtual serial port to a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.

- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, click **Add**.
- 5 In the Add Hardware wizard, select **Serial Port** and click **Next**.
- 6 On the Serial Port Type page, do one of the following:
 - For physical devices such as modems, select **Use physical serial port on the host**, click **Next**, and choose the port on the host computer that you want to use for this serial connection.
 - To capture data from an application in an output file, select **Output file**, click **Next**, and enter the path and filename or browse to the location of the file on the host.
 - To connect to a debugging application on the host or in another virtual machine, select **Output to Named Pipe** and click **Next**.
- 7 If you selected **Output to Named Pipe**, do one of the following:
 - For a Windows host, on the Specify Named Pipe page, specify the pipe name.
The pipe name must follow the form `\\.pipe<namedpipe>`. That is, it must begin with `\\.pipe\`.
 - For a Linux host, in the **Path** field, enter `/tmp/<socket>` or another UNIX socket name.
- 8 Also if you selected **Output to Named Pipe**, do one of the following:
 - To send debugging information to an application on the host:
 - i In the first drop-down menu, select **This end is the server** or **This end is the client**.
Select **This end is the server** to start this end of the connection first.
 - ii In the second drop-down menu, select **The other end is an application**.
 - To send debugging information to another virtual machine:
 - i In the first drop-down menu, select **This end is the server**.
 - ii In the second drop-down menu, select **The other end is a virtual machine**.
- 9 Make sure the **Connect at power on** check box is selected if desired.
- 10 Click **Finish**.

- 11 (Optional) On the **Hardware** tab of the virtual machine settings editor, to configure this serial port to use polled mode, select **Yield CPU on poll**.

This option is of interest to developers who are using debugging tools that communicate over a serial connection. If the serial port in the guest is being used in polled mode rather than interrupt mode, you might notice performance issues. This option forces the virtual machine to yield processor time if the only task it is trying to do is poll the virtual serial port.

If you are setting up a connection between two virtual machines, you now have the first virtual machine set up as the server. Repeat this procedure for the second virtual machine, but set it up as the client by selecting **This end is the client** when configuring the named pipe.

Change the Input Speed of the Serial Connection

You can increase the speed of a serial connection over a pipe to a virtual machine.

Before you begin, use the guest operating system to configure the serial port for the highest setting supported by the application you are running in the virtual machine.

In principle, the output speed, which is the speed at which the virtual machine sends data through the virtual serial port, is unlimited. In practice, the output speed depends on how fast the application at the other end of the pipe reads inbound data.

To change the input speed of the serial connection

- 1 Power off the virtual machine and close the Workstation window.
- 2 Use a text editor to add the following line to your virtual machine's configuration (.vmx) file:

```
serial<n>.pipe.charTimePercent = "<x>"
```

<n> is the number of the serial port, starting from 0. The first serial port is serial0.

The <x> value is a positive integer that specifies the time taken to transmit a character, expressed as a percentage of the default speed set for the serial port in the guest. For example, a setting of 200 forces the port to take twice as long for each character, or send data at half the default speed. A setting of 50 forces the port to take only half as long for each character, or send data at twice the default speed.

Assuming that the serial port speed is set appropriately in the guest operating system, experiment with this setting. Start with a value of 100 and gradually decrease it until you find the highest speed at which your connection works reliably.

Debugging over a Virtual Serial Port

Using virtual machines, you can debug kernel code on one system without the need for two physical computers, a modem, or a serial cable. You can use Debugging Tools for Windows (WinDbg) or Kernel Debugger (KD) to debug kernel code in a virtual machine over a virtual serial port.

You can Download Debugging Tools for Windows from the Windows Hardware Developer Central (WHDC) Web site.

Debug an Application in a Virtual Machine from a Windows Host

In this configuration, you have kernel code to debug in a virtual machine (called the target virtual machine) and are running Debugging Tools for Windows (WinDbg) or Kernel Debugger (KD) on a Windows host.

Before you begin, on the host, make sure you have a recent version of Debugging Tools for Windows, which supports debugging over a pipe. You need version 5.0.18.0 or higher.

To debug an application in a virtual machine from a Windows host

- 1 Prepare the target virtual machine as described in [“Add a Virtual Serial Port to a Virtual Machine”](#) on page 335.
Make sure you select **This end is the server** when configuring the named pipe.
- 2 Power on the virtual machine.
- 3 Choose **VM > Removable Devices** menu to make sure the serial port is connected.
If **Serial<n>** is not reported as `\\.\pipe\<namedpipe>`, choose the virtual serial port and click **Connect**.
- 4 On the host, open a command prompt window and enter the following command:

```
<debugger> -k com:port=\\.\pipe\<namedpipe>,pipe  
<debugger> is WinDbg or KD.
```
- 5 Press Enter to start debugging.

Debug an Application in a Virtual Machine from Another Virtual Machine

This configuration is useful if you use Workstation on a Linux host. In this situation, you have kernel code to debug in the target virtual machine and are running Debugging Tools for Windows (WinDbg) or Kernel Debugger (KD) in the debugger virtual machine on the same host.

Before you begin, download and install WinDbg or KD in the Windows guest that you plan to use as the debugger virtual machine.

To debug an application from another virtual machine

- 1 Prepare the virtual machines as described in [“Add a Virtual Serial Port to a Virtual Machine”](#) on page 335.
- 2 Power on both virtual machines.
- 3 Use the **VM > Removable Devices** menu to make sure the serial port is connected.
If the serial port is not connected, choose the virtual serial port and click **Connect**.
- 4 In the debugger virtual machine, start debugging with WinDbg or KD.

Configuring Keyboard Features

You can change which key combinations you use for hot-key sequences in Workstation and which language to use for the keyboard that virtual network computing (VNC) clients use. In addition, you can configure platform-specific keyboard features for Windows and Linux hosts.

Use the Enhanced Virtual Keyboard for Windows Hosts

The enhanced virtual keyboard feature provides better handling of international keyboards and keyboards with extra keys. It also offers security improvements because it processes raw keyboard input as soon as possible, bypassing Windows keystroke processing and any malware that is not already at a lower layer.

If you use the enhanced virtual keyboard, when you press Ctrl+Alt+Delete, the guest system only, rather than both guest and host, acts on the command.

Before you begin, if you just installed or upgraded to Workstation 7.0 and have not yet restarted your computer, do so.

To use the enhanced virtual keyboard for Windows hosts

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 Click the **Options** tab, and select **General**.
- 5 To enable or disable the setting, select or deselect the **Use enhanced virtual keyboard** check box and click **OK**.

Hot Keys for Virtual Machines

Hot keys let you specify the key combination that is used with hot-key sequences for virtual machines. For example, you can require that all hot-key sequences use Ctrl+Shift+Alt.

Configuring hot keys is useful to prevent certain key combinations (such as Ctrl+Alt+Del) from being intercepted by Workstation instead of being sent to the guest operating system. Use hot-key sequences to:

- Switch between virtual machines
- Enter and leave full screen mode
- Release (ungrab) input
- Send Ctrl+Alt+Del to the virtual machine only (not to the host machine)
- Send commands to the virtual machine only (not to the host machine)

The default settings for hot keys are listed in the preferences editor (choose **Edit > Preferences > Hot Keys**). Use the preferences editor to change them.

Use Ctrl+Alt in a Key Combination

Because Ctrl+Alt tells Workstation to release (ungrab) mouse and keyboard input, combinations that include Ctrl+Alt are not passed to the guest operating system. You must use the Space key if the key combination includes Ctrl+Alt.

To use Ctrl+Alt in a key combination

- 1 Press Ctrl+Alt+spacebar.
- 2 Release the spacebar without releasing Ctrl and Alt.
- 3 Press the third key of the key combination you want to send to the guest.

Specify a Language Keyboard Map for VNC Clients

If you set a virtual machine to act as a VNC server, you can specify which language to use for the keyboard that VNC clients use. By default, the US101 keyboard map (U.S. English) is used.

Before you begin, set the virtual machine to act as a VNC server. See [“Configure a Virtual Machine as a VNC Server”](#) on page 228.

Also, determine the location of the keymap file to use. Default keymap files are included in the Workstation installation directory:

- On Windows XP hosts, this directory is in `C:\Documents and Settings\All Users\Application Data\VMware\vnckeymap`.
- On Windows Vista and Windows 7 hosts, this directory is in `C:\ProgramData\VMware\vnckeymap`.
- On Linux hosts, this directory is in `/usr/lib/vmware/vnckeymap`.

If the keymap file you want to use is in another location, determine the path to the file.

Also determine the language code. Use the following list:

- `de`: German
- `de-ch`: German (Switzerland)
- `es`: Spanish
- `fi`: Finnish
- `fr`: French
- `fr-be`: French (Belgium)
- `fr-ch`: French (Switzerland)
- `is`: Icelandic
- `it`: Italian
- `jp`: Japanese
- `nl-be`: Dutch (Belgium)
- `no`: Norwegian
- `pt`: Polish
- `uk`: UK English
- `us`: US English

To specify a language keyboard map for VNC clients

- 1 Use a text editor to open the configuration file (.vmx file) for the virtual machine and add the following lines, where <port number> is the port number to use:

- **RemoteDisplay.vnc.enabled = "TRUE"**
- **RemoteDisplay.vnc.port = "<port number>"**

- 2 Add one of the following properties to the configuration file, where <xx> is the code for the language to use, such as jp for Japanese:

- To use the default keymap file included in the Workstation installation directory, set the following property:
RemoteDisplay.vnc.keyMap = "<xx>"
- To use a keyboard map file in another location, set the following property to an absolute file path:

RemoteDisplay.vnc.keyMapFile

You can now start the virtual machine and connect to it from a VNC client. See [“Use a VNC Client to Connect to a Virtual Machine”](#) on page 229.

Keyboard Mapping on a Linux Host

Several situations might require you to set properties in a virtual machine's configuration file (.vmx file) to change the way a key is mapped.

Configure Keyboard Mapping for a Remote X Server

Sometimes the keyboard works correctly with a local X server but not when you run the same virtual machine with a remote X server. You need to set additional properties in the configuration (.vmx) file.

Before you begin, verify that the remote X server is an XFree86 server running on a PC.

If the keyboard does not work correctly on an XFree86 server running locally, report the problem to VMware technical support.

For local X servers, Workstation maps X key codes to PC scan codes to correctly identify a key. Workstation uses this key code map only for local X servers because it cannot tell whether a remote X server is running on a PC or on some other kind of computer. In this case, you can set a property to tell Workstation to use key code mapping. For a description of key code mapping, see [“X Key Codes Compared to Keysyms”](#) on page 344.

To configure keyboard mapping for a remote X server

- 1 Power off the virtual machine and close the Workstation window.
- 2 On the machine that hosts the virtual machine, add one of the following lines to the virtual machine configuration (.vmx) file or to ~/.vmware/config:
 - If you use an XFree86-based server that Workstation does not recognize as an XFree86 server, use the following property:


```
xkeymap.usekeycodeMap = "TRUE"
```

This property tells Workstation to always use key code mapping regardless of server type.
 - If Workstation does recognize the remote server as an XFree86 server, use the following property:


```
xkeymap.usekeycodeMapIfXFree86 = "TRUE"
```

This property tells Workstation to use key code mapping if you are using an XFree86 server, even if it is remote.
- 3 Save and close the file.

Change How a Specific Key Is Mapped

If some keys on the keyboard do not work correctly in a virtual machine, you can set a property that makes a modification to the map.

Before you begin, perform the following tasks:

- Verify that the X server is an XFree86 server running on a PC. If the X server is remote, configure it to use key code mapping. See [“Configure Keyboard Mapping for a Remote X Server”](#) on page 342. For a description of key code mapping, see [“X Key Codes Compared to Keysyms”](#) on page 344.
- Determine the X key code and the corresponding v-scan code for the key. To find the X key code for a key, run `xev` or `xmodmap -pk`. Most v-scan codes are listed in [“V-Scan Code Table”](#) on page 347.

To change how a specific key is mapped

- 1 Power off the virtual machine and close the Workstation window.
- 2 On the machine that hosts the virtual machine, add the following line to the virtual machine configuration (.vmx) file or to ~/.vmware/config:

```
xkeymap.keycode.<code> = "<v-scan_code>"
```

The <code> value must be a decimal number and <v-scan_code> must be a C-syntax hexadecimal number (for example, 0x001).

For example, to swap left Ctrl and Caps Lock, use the following lines:

```
xkeymap.keycode.64 = "0x01d # X Caps_Lock -> VM left ctrl"
xkeymap.keycode.37 = "0x03a # X Control_L -> VM caps lock"
```

- 3 Save and close the file.

X Key Codes Compared to Keysyms

Pressing a key on the PC keyboard generates a PC scan code based roughly on the position of the key. For example, the Z key on a German keyboard generates the same code as the Y key on an English keyboard because they are in the same position on the keyboard. Most keys have one-byte scan codes, but some keys have two-byte scan codes with prefix 0xe0.

Internally, Workstation uses a simplified version of the PC scan code that is a single nine-bit numeric value, called a v-scan code. A v-scan code is written as a three-digit hexadecimal number. The first digit is 0 or 1. For example, the Ctrl key on the left side of the keyboard has a one-byte scan code (0x1d). Its v-scan code is 0x01d. The Ctrl key scan code on the right side of the keyboard is two bytes (0xe0, 0x1d). Its v-scan code is 0x11d.

An XFree86 server on a PC has a one-to-one mapping from X key codes to PC scan codes, or v-scan codes, which is what Workstation uses. When Workstation is hosted on an XFree86 server and runs a local virtual machine, it uses the built-in mapping from X key codes to v-scan codes. This mapping is keyboard independent and should be correct for most languages. In other cases (not an XFree86 server or not a local server), Workstation must map keysyms to v-scan codes by using a set of keyboard-specific tables.

An X server uses a two-level encoding of keys, which includes the X key code and the keysym. An X key code is a one-byte value. The assignment of key codes to keys depends on the X server implementation and the physical keyboard. As a result, an X application normally cannot use key codes directly. Instead, the key codes are mapped

into keysyms that have names like space, escape, x and 2. You can use an X application to control the mapping by using the function `XChangeKeyboardMapping()` or by the program `xmodmap`. To explore keyboard mappings, you can use the `xev` command, which shows the key codes and keysyms for keys typed into its window.

A key code corresponds roughly to a physical key, while a keysym corresponds to the symbol on the key top. For example, with an XFree86 server running on a PC, the Z key on the German keyboard has the same key code as the Y key on an English keyboard. The German Z keysym, however, is the same as the English Z keysym, and different from the English Y keysym.

Configure How Keysyms Are Mapped

When key code mapping cannot be used or is disabled, Workstation maps keysyms to v-scan codes. If a language-specific keyboard does not appear to be supported by Workstation, you might need to set a property that tells Workstation which keysym table to use.

Before you begin, perform the following tasks:

- To change the mapping of a few keys, determine the keysym name for each key that is not mapped correctly.

The easiest way to find the keysym name for a key is to run the `xev` or `xmodmap -pk` commands. The X header file `/usr/include/X11/keysymdef.h` has a complete list of keysyms. The name of a keysym is the same as its C constant without the `XK_` prefix.

- To use a different keysym table, determine which mapping table to use.

The tables are located in the `xkeymap` directory in the Workstation installation directory (usually `/usr/lib/vmware`). The table you must use depends on the keyboard layout. The normal distribution includes tables for PC keyboards for the United States and a number of European countries and languages. For most of these, both the 101-key (or 102-key) and the 104-key (or 105-key) variants are available.

- If none of the mapping tables is completely correct, find one that works best, copy it to a new location, and change the individual keysym mappings.

Workstation determines which table to use by examining the current X keymap. However, its decision-making process can sometimes fail. In addition, each mapping is fixed and might not be completely correct for any given keyboard and X key code-to-keysym mapping. For example, a user might have swapped Ctrl and Caps Lock using `xmodmap`. This means the keys are swapped in the virtual machine when using a remote server (keysym mapping) but are unswapped when using a local server (key code mapping). To correct this situation, use configuration settings.

To configure how keysyms are mapped

- 1 Power off the virtual machine and close the Workstation window.
- 2 On the machine that hosts the virtual machine, add one or more of the following lines to the virtual machine configuration (`.vmx`) file or to `~/ .vmware/config`:

- To disable X key code mapping to map keysyms rather than key codes to v-scan codes, set the following property:

```
xkeymap.nokeycodeMap = "TRUE"
```

For more information, see [“X Key Codes Compared to Keysyms”](#) on page 344.

- If Workstation has a table in the `xkeymap` directory for your keyboard but cannot detect it, set the following property:

```
xkeymap.language = "<keyboard_type>"
```

The value `<keyboard_type>` must specify one of the tables in the `xkeymap` directory. However, the failure to detect the keyboard probably means the table is not completely correct for you. You might need to create a modified table and use the `xkeymap.fileName` property, described next.

- To use a different keysym mapping table that is not in the `xkeymap` directory, set the following property, where `<file_path>` is the path to the table:

```
xkeymap.fileName = "<file_path>"
```

The table must list a keysym for each key by using the following form:

```
<sym> = "<v-scan_code>"
```

The `<sym>` value is an X keysym name, and `<v-scan_code>` is a C-syntax hexadecimal number (for example, `0x001`). Use a new line for each keysym.

Compiling a complete keysym mapping is difficult. VMware recommends editing an existing table and making small changes.

- To change the keysym mapping of a few keys, set the following property for each key, on separate lines:

```
xkeymap. keysym. <sym> = "<v-scan_code>"
```

The value <sym> must be an X keysym name and <v-scan_code> is a C-syntax hexadecimal number (for example, 0x001).

Most v-scan codes are listed in “V-Scan Code Table” on page 347. The xkeymap tables themselves are also helpful.

3 Save and close the file.

V-Scan Code Table

Table 16-1 shows the v-scan codes for the 104-key U.S. keyboard.

Table 16-1. V-Scan Codes for the 104-Key U.S. Keyboard

Symbol	Shifted Symbol	Location	V-Scan Code
Esc			0x001
1	!		0x002
2	@		0x003
3	#		0x004
4	\$		0x005
5	%		0x006
6	^		0x007
7	&		0x008
8	*		0x009
9	(0x00a
0)		0x00b
-	_		0x00c
=	+		0x00d
Backspace			0x00e
Tab			0x00f
Q			0x010
W			0x011
E			0x012
R			0x013

Table 16-1. V-Scan Codes for the 104-Key U.S. Keyboard (Continued)

Symbol	Shifted Symbol	Location	V-Scan Code
T			0x014
Y			0x015
U			0x016
I			0x017
O			0x018
P			0x019
[{		0x01a
]	}		0x01b
Enter			0x01c
Ctrl		left	0x01d
A			0x01e
S			0x01f
D			0x020
F			0x021
G			0x022
H			0x023
J			0x024
K			0x025
L			0x026
;			0x027
'			0x028
`			0x029
Shift		left	0x02a
\			0x02b
Z			0x02c
X			0x02d
C			0x02e
V			0x02f
B			0x030

Table 16-1. V-Scan Codes for the 104-Key U.S. Keyboard (Continued)

Symbol	Shifted Symbol	Location	V-Scan Code
N			0x031
M			0x032
,	<		0x033
.	>		0x034
/	?		0x035
Shift		right	0x036
*		numeric pad	0x037
Alt		left	0x038
Space bar			0x039
Caps Lock			0x03a
F1			0x03b
F2			0x03c
F3			0x03d
F4			0x03e
F5			0x03f
F6			0x040
F7			0x041
F8			0x042
F9			0x043
F10			0x044
Num Lock		numeric pad	0x045
Scroll Lock			0x046
Home	7	numeric pad	0x047
Up arrow	8	numeric pad	0x048
PgUp	9	numeric pad	0x049
-		numeric pad	0x04a
Left arrow	4	numeric pad	0x04b
5		numeric pad	0x04c
Right arrow	6	numeric pad	0x04d

Table 16-1. V-Scan Codes for the 104-Key U.S. Keyboard (Continued)

Symbol	Shifted Symbol	Location	V-Scan Code
+		numeric pad	0x04e
End	1	numeric pad	0x04f
Down arrow	2	numeric pad	0x050
PgDn	3	numeric pad	0x051
Ins	0	numeric pad	0x052
Del		numeric pad	0x053
F11			0x057
F12			0x058
Break	Pause		0x100
Enter		numeric pad	0x11c
Ctrl		right	0x11d
/		numeric pad	0x135
SysRq	Print Scrn		0x137
Alt		right	0x138
Home		function pad	0x147
Up arrow		function pad	0x148
Page Up		function pad	0x149
Left arrow		function pad	0x14b
Right arrow		function pad	0x14d
End		function pad	0x14f
Down arrow		function pad	0x150
Page Down		function pad	0x151
Insert		function pad	0x152
Delete		function pad	0x153
Windows		left	0x15b
Windows		right	0x15c
Menu			0x15d

The 84-key keyboard has a Sys Req key on the numeric pad. Its v-scan code is 0x054.

Keyboards outside the U.S. usually have an extra key (often <> or <> |) next to the left Shift key. The v-scan code for this key is 0x056.

Using USB Devices in a Virtual Machine

You can connect up to 20 USB devices to one virtual machine simultaneously. Workstation provides two USB controllers per virtual machine, a UHCI controller for USB 1.1 devices and an EHCI controller for USB 2.0 devices.

For USB 2.0 support, your host must support USB 2.0, and you must enable USB 2.0 support in Workstation. USB 2.0 support is available only for Workstation 6.x and higher virtual machines. USB 2.0 devices are high-speed devices which include the latest models of USB flash drives, USB hard drives, iPods, and iPhone.

On the host, when a USB 2.0 device connects to a USB port, the device is automatically connected to EHCI controller and operates in USB 2.0 mode. A USB 1.1 device is connected to UHCI controller and operates in USB 1.1 mode. A virtual machine with USB 2.0 support enabled, simulates this behavior. See [“Enable the USB 2.0 Controller for a Virtual Machine”](#) on page 352.

Although your host operating system must support USB, you do not need to install device-specific drivers for USB devices in the host operating system to use those devices only in the virtual machine. Windows NT and Linux kernels earlier than 2.2.17 do not support USB.

VMware has tested a variety of USB devices with Workstation 7.0. If the guest operating system has appropriate drivers, you can use a wide variety of USB devices, for example, PDAs, Smart phones, printers, storage (disk) devices, scanners, MP3 players, digital cameras, memory card readers, and isochronous transfer devices, such as webcams, speakers, and microphones.

USB human interface devices, such as the keyboard and mouse, can be connected to the virtual machine by enabling the Show all USB input devices option. If you do not select the option to Show all USB input devices as removable devices, these devices do not appear as Removable Devices available to connect to the virtual machine, even though they are plugged into USB ports on the host. This option enables users to use special USB human interface devices (HIDs) inside a virtual machine.

Enable the USB 2.0 Controller for a Virtual Machine

The virtual machine's USB controller and high-speed USB 2.0 devices are enabled by default. Modems and certain streaming data devices, such as speakers and webcams, do not work properly unless you enable USB 2.0 support.

If your virtual machine was created using an older version of Workstation the USB 2.0 device support is not enabled. You can enable the USB controller in the virtual machine settings editor of Workstation 7.0.

Before you begin, perform one of the following tasks that apply to your configuration:

- Verify that the virtual machine is a Workstation 6.x or higher virtual machine.
- Verify that the guest supports USB 2.0 devices.
- On Windows XP guests, verify that the latest service pack is installed to use USB 2.0.

If you use Windows XP with no service packs, the driver for the EHCI controller cannot be loaded.

If you do not plan to use USB devices in a virtual machine, you can use the virtual machine settings editor to disable USB 2.0 support.

To enable the USB 2.0 Controller for a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, select **USB Controller**.
- 4 Select the **Enable high-speed support for USB 2.0 devices** check box and click **OK**.

Add a USB Controller to a Virtual Machine

By default, a USB controller is included when you create a virtual machine. If you remove the USB controller, you can add it back.

This controller is required to use a smart card in a virtual machine regardless of whether the smart card reader is a USB device.

To add a USB controller to a virtual machine

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.

- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, click **Add** to start the Add Hardware wizard.
- 5 On the Hardware Type page, select **USB Controller** and click **Next**.
- 6 On the USB page, click **Finish**.
- 7 In the virtual machine settings editor, click **OK**.

You can now start the virtual machine and automatically or manually connect USB devices and smart card readers.

Connecting USB Devices

When a virtual machine is running, its window is the active window. If you plug a USB device into the host, by default, the device connects to the virtual machine instead of the host.

If you manually connect a USB device to a virtual machine (choose **VM > Removable Devices**), Workstation retains the virtual machine's connection to the affected port on the host. You can suspend or power off the virtual machine, or unplug the device. When you plug the device back in or resume the virtual machine, Workstation reconnects the device. Workstation retains the connection by writing an autoconnect entry to the virtual machine's configuration (`.vmx`) file.

If Workstation cannot reconnect to the device (for example, because you disconnect the device), the device is removed and a message is displayed, indicating that Workstation cannot connect to the device. You can connect manually to the device if it is still available.

Enable or Disable Automatic Connection of USB Devices

You can disable the autoconnect feature if you do not want USB devices to automatically connect to the virtual machine when you power it on.

To enable or disable automatic connection of USB devices

- 1 Select the virtual machine.

The virtual machine can be powered on or off unless you plan to change the setting for connecting to USB mouse and keyboard devices. In this case, the virtual machine must be powered off.
- 2 Choose **VM > Settings**.

- 3 On the **Hardware** tab, select **USB Controller**.
- 4 Select or deselect the **Automatically connect new USB devices** check box to enable or disable the setting and click **OK**.

Enable or Disable Show All USB Input Devices

The Show all USB input devices option is disabled by default. This option enables users to use special USB HID devices inside a virtual machine exclusively.

NOTE An HID that is connected to the guest is not available to the host.

VMware recommends disabling automatic connection of USB device when using a KVM switch for a mouse or keyboard.

Before you begin, make sure that the virtual machine is powered off.

To enable or disable Show all USB input devices

- 1 Select **VM > Settings**.
- 2 On the **Hardware** tab, select **USB Controller**.
- 3 Select the **Show all USB input devices** check box to enable or disable the setting and click **OK**.

If the Show all USB input devices check box is enabled, all the HID devices, such as USB 1.1 and 2.0 mouse and keyboard devices, appear as Removable Devices when the virtual machine is powered on.

Connect a USB Device Manually

If a device that is connected to the host does not automatically connect to a virtual machine at power on, you can connect the device manually.

Before you begin, for USB mouse, keyboard, and other input devices, you must enable showing these devices. See [“Enable or Disable Show All USB Input Devices”](#) on page 354.

Also, when you are using a virtual machine, if you plug a device in to the host, the autoconnect feature usually connects the device to the virtual machine. If this action does not occur, you can connect the device manually.

To connect a USB device manually

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered on.
- 3 Choose **VM > Removable Devices > <device_name>**.

Here **<device_name>** specifies the USB device that is plugged in to the host. A check mark appears next to the device's name, indicating that it is connected.

If the physical USB devices are connected to the host through a hub, the virtual machine sees only the USB devices, not the hub.

USB Driver Installation on a Windows Host

When a particular USB device is connected to a virtual machine for the first time, the host detects it as a new device named VMware USB Device and installs the appropriate VMware driver.

On Windows XP and Windows Server 2003 hosts, the Microsoft Windows Found New Hardware wizard prompts you to run it. Select the default action, **Install the software automatically**. After the software is installed, the guest operating system detects the USB device and searches for a suitable driver.

Synchronize a PDA to Install a PDA Driver

When you synchronize a PDA to a virtual machine for the first time, the total time required to load the VMware USB device driver in the host and the PDA driver in the guest might exceed the device's connection timeout value. This causes the device to disconnect itself from the computer before the guest can synchronize with it.

To synchronize a PDA to install a PDA driver

- 1 Connect the USB device to the computer that hosts the virtual machine.
- 2 Synchronize the PDA with the host.
- 3 Let the guest finish installing the PDA driver.
- 4 Dismiss any connection error warnings.
- 5 Synchronize the PDA again.

This second attempt usually succeeds.

Access and Use a USB Device on a Linux Host

On Linux hosts, Workstation uses the USB device file system to connect to USB devices. If the USB device file system is not located in `/proc/bus/usb`, you must mount the USB file system to that location.

Before you begin, add a USB controller to the virtual machine if the virtual machine does not have one. See [“Add a USB Controller to a Virtual Machine”](#) on page 352.

Do not attempt to add a USB drive's device node directory (for example, `/dev/sda`) to the virtual machine as a hard disk.

To access and use a USB device on a Linux host

- 1 Run the following command as root:

```
mount -t usbfs none /proc/bus/usb
```
- 2 Connect the USB device to the host and begin using it.

How Device Control Is Shared Between Host and Guest

Only the host or the guest can have control of a USB device at any one time. Device control operates differently, depending on whether the host is a Linux or a Windows computer.

Device Control on a Windows Host

When you connect a device to a virtual machine, it is disconnected from the host or from the virtual machine that previously had control of the device. When you disconnect a device from a virtual machine, it is returned to the host.

Under some circumstances, if a USB storage device is in use on the host (for example, one or more files stored on the device are open on the host), an error appears in the virtual machine when you try to connect to the device. You must let the host complete its operation or close any application connected to the device on the host, and connect to the device in the virtual machine again.

On Windows XP and Windows Server 2003 hosts, when you connect a USB network or storage device to a virtual machine, a message might appear on the host that says the device can be removed safely. This is normal behavior, and you can dismiss the dialog box. However, do not remove the device from your physical computer.

If the network or storage device does not disconnect from the host, use the appropriate system tray icon to disconnect it. On Windows XP and Windows Server 2003, it is called **Safely Remove Hardware**.

Troubleshoot Device Control Issues on a Linux Host

On Linux hosts, guest operating systems can use devices that are not already in use by the host, that is, devices that are not claimed by a host operating system driver.

If the device is in use by the host and you try to choose **VM > Removable Devices** to connect it to the guest, a dialog box appears, asking whether you want to disconnect the driver on the host. Occasionally, disconnecting the device fails.

A related issue sometimes affects devices that rely on automatic connection (as PDAs often do). Occasionally, even if you successfully used autoconnection to connect the device to the virtual machine, you might experience problems with the connection to the device.

To troubleshoot device control issues on a Linux host

- 1 If you have problems with automatic connections, choose **VM > Removable Devices** to disconnect the device and reconnect it.
- 2 If the problem persists, unplug the device physically and plug it in again.
- 3 If a warning appears that the device is in use, disable the device in the `hotplug` configuration files in the `/etc/hotplug` directory.

For details on editing these configuration files, see your Linux distribution's documentation.

- 4 If a disconnection fails, do one of the following:
 - If the driver was automatically loaded by `hotplug`, disable it in the `hotplug` configuration files in the `/etc/hotplug` directory.
For details on editing these configuration files, see your Linux distribution's documentation.
 - To unload the device driver manually, become root (`su -`) and use the `rmmod` command.

Disconnecting USB Devices from a Virtual Machine

Before you unplug a USB device or choose **VM > Removable Devices** to disconnect it from a virtual machine, be sure it is in a safe state.

Follow the procedures the device manufacturer specifies for unplugging the device from a physical computer. This is true whether you are physically unplugging it, moving it from host to virtual machine, moving it between virtual machines, or moving it from virtual machine to host.

This is important with data storage devices (a Zip drive, for example). If you move a data storage device too soon after saving a file and the operating system did not actually write the data to the disk, you can lose data.

Use Smart Cards with Virtual Machines

A smart card is a plastic card about the size of a credit card but embedded with a computer chip. Many government agencies and large enterprises use smart cards to send secure communication, digitally sign documents, and authenticate users who access their computer networks. Users plug a smart card reader into their computer and insert their smart card in the reader. They are then prompted for their PIN to log on.

The virtual machine considers smart card readers to be a type of USB device. You can choose **VM > Removable Devices** to access them. Virtual machines can connect to smart card readers that interface to serial ports, parallel ports, USB ports, PCMCIA slots, and PCI slots.

A smart card can be shared between virtual machines or between the host and one or more virtual machines. Sharing is enabled by default. To disable sharing, see [“Disable Smart Card Sharing”](#) on page 360.

When you plug a smart card reader into the computer the reader appears as two separate USB devices in the Workstation interface. This is because you can use smart cards in one of two mutually exclusive modes: virtual mode or USB passthrough mode. You must select one or the other.

- Virtual mode (Recommended) – The smart card reader device is available as **Virtual <smart_card_reader_model>** under **Removable Devices**. After the virtual reader is connected to the virtual machine, it is visible as **USB Smart Card Reader** on Windows XP guests. On Windows Vista and Windows 7 guests the generic smart card reader device name appears under the Windows Device Manager list. In virtual mode, the smart card reader can be shared among applications on the host and among applications within different guests on the host.
- USB passthrough mode – The smart card reader device is available as **<smart_card_reader_model>** under **Removable Devices**. In USB passthrough mode, a single virtual machine directly controls the physical smart card reader. A USB passthrough smart card reader cannot be used by applications on the host or by applications within other virtual machines. You should use USB passthrough mode only if connection in virtual mode does not work well for your scenario. If you are using the USB passthrough mode you may need to install the driver provided by the manufacturer.

Smart cards can be used with many Linux distributions. VMware provides full smart card support for Windows guests running on Linux hosts. However, using smart cards within Linux, typically requires third party software to effectively authenticate to a domain or enable secure communications. Smart cards should work with common Linux browsers, email applications, and directory services however, these products have not been tested or certified by VMware.

To use a host's smart card reader in a virtual machine, make sure the following prerequisites are satisfied:

- On Windows hosts, start the service called `SCardSvr.exe` if it is not already running.
- On Linux hosts, make sure the `libpcsc-lite` library is installed. Most recent Linux distributions include this library. Also make sure the `pcscd` daemon is running.
- Make sure the virtual machine has a USB controller.

A USB controller is required regardless of whether the smart card reader itself is a USB device. By default, USB controllers are included when you create a virtual machine. If you removed the USB controller, you must add it back. See [“Add a USB Controller to a Virtual Machine”](#) on page 352.

To use smart cards with virtual machines

- 1 Connect the smart card reader to the host machine.
- 2 Start the virtual machine.
- 3 To connect the smart card reader to a virtual machine, choose **VM > Removable Devices > Virtual <smart_card_reader_model> > Connect**.

If the smart card reader is a USB smart card reader, two items appear for it in the **Removable Devices** menu. Both items use the model name of the reader, but one item name begins with **Virtual**.

On Linux hosts, if you select the wrong item and then want to select the **Virtual** smart card item, see [“Switch to Using the Virtual Smart Card Reader on Linux Hosts”](#) on page 360.

- 4 To disconnect the smart card reader from the virtual machine, choose **VM > Removable Devices > Virtual <smart_card_reader_model> > Disconnect**.

- 5 To remove the smart card from the virtual machine, choose **VM > Removable Devices > Virtual <smart_card_reader_model> > Remove Smart Card**.

The smart card is removed from the virtual machine but stays connected on the host. If the smart card is physically removed from the smart card reader then this option is disabled.

- 6 To insert the smart card to the virtual machine, choose **VM > Removable Devices > Virtual <smart_card_reader_model> > Insert Smart Card**.

If the smart card is physically inserted in the smart card reader then the smart card is also inserted in the virtual machine.

Switch to Using the Virtual Smart Card Reader on Linux Hosts

Because of the way smart card reader functionality is implemented on Linux hosts, you must exit Workstation and restart the `pcscd` daemon on the host before switching from the non-virtual smart card reader to the virtual smart card reader.

To switch to using the virtual smart card reader on Linux hosts

- 1 To disconnect from the non-virtual smart card reader, use the **Removable Devices** menu and select **Disconnect**.
- 2 Power off the virtual machine and exit Workstation.
- 3 Physically disconnect the smart card reader from the host.
- 4 Restart the `pcscd` daemon on the host.
- 5 Physically connect the smart card reader to the host.
- 6 Start Workstation, power on the virtual machine, and connect to the virtual smart card reader.

See [“Use Smart Cards with Virtual Machines”](#) on page 358.

Disable Smart Card Sharing

By default, you can share a smart card between virtual machines or between the host and one or more virtual machines. You might want to disable smart card sharing if you are using a PCMCIA smart card reader, deploying virtual machines for enterprise use and do not want to support drivers for various smart card readers, and your host has drivers but not the guest.

The setting that controls smart card sharing is located in the global configuration file. The global configuration file is created when you change any of the default settings in the Workstation preferences editor (**Edit > Preferences**). The file location depends on the host operating system:

- On most Windows hosts:

`C:\Documents and Settings\All Users\Application Data\VMware\VMware Workstation\config.ini`

- On Windows Vista and Windows 7 hosts:

`C:\ProgramData\VMware\VMware Workstation\config.ini`

- On Linux hosts:

`/etc/vmware/config`

To disable smart card sharing

- 1 If the `config.ini` file does not yet exist on your host computer, choose **Edit > Preferences** and change at least one of the settings in the preference editor.
- 2 Open the `config.ini` file with a text editor and add the following line:
`usb.ccid.useSharedMode = "FALSE"`
- 3 Save and close the file.
- 4 Set permissions on this file so that other users cannot change it.

Support for Generic SCSI Devices

Generic SCSI gives the guest operating system direct access to SCSI devices connected to the host, such as scanners, tape drives, and other data storage devices. Using the SCSI generic driver, Workstation allows a virtual machine to run any SCSI device that is supported by the guest operating system.

In theory, generic SCSI is completely device independent, but VMware has discovered it is sensitive to the guest operating system, device class, and specific SCSI hardware. Try any SCSI hardware and report problems to VMware technical support.

On Windows hosts, to access host SCSI devices from within a virtual machine, you must run Workstation as a user with administrator access.

On Linux hosts, you must have read and write permissions on a given generic SCSI device to use the device within a virtual machine, even if the device is a read-only device such as a CD-ROM drive. These devices typically default to root-only permissions. Your administrator can create a group with access to read and write to these devices and add the appropriate users to that group.

Installing Required Adapters or Drivers for Some Windows Guests

On older Windows guest operating systems, you might need to install special host bus adapters. To use a SCSI device with 32-bit Windows XP guests, you must install a special driver that VMware provides.

Installing a SCSI Adapter on Windows 9.x and Me Guests

If you use generic SCSI devices in a Windows 95, Windows 98, or Windows Me guest operating system and are experiencing problems with the devices, download the latest Mylex (BusLogic) BT/KT-958 compatible host bus adapter from LSI Web site. To install the driver, follow the instructions on the Web site.

This driver overrides what Windows chooses as the best driver, but it corrects known problems.

Installing a SCSI Driver for 32-Bit Windows XP Guests

To use SCSI devices in a 32-bit Windows XP virtual machine, you need a special SCSI driver available from the Downloads page of the VMware Web site.

Install the BusLogic Driver in a Windows NT 4.0 Guest

Generic SCSI devices use the virtual Mylex (BusLogic) BT/KT-958 compatible host bus adapter provided by the virtual machine. On Windows NT 4.0, you might need to install the driver manually if it is not already installed for a virtual SCSI disk. Do so before you add a generic SCSI device.

Before you begin, have your Windows NT installation CD available.

To install the BusLogic driver in a Windows NT 4.0 guest

- 1 To open the SCSI Adapters control panel, choose **Start > Settings > Control Panel > SCSI Adapters**.
- 2 On the **Drivers** tab, click **Add**.
- 3 In the list of vendors on the left, select **BusLogic**.
- 4 In the list of drivers on the right, select **BusLogic MultiMaster PCI SCSI Host Adapters** and click **OK**.
- 5 Insert the Windows NT CD when you are prompted and click **OK**.
- 6 Reboot when you are prompted.

Avoiding Concurrent Access on Linux Hosts

The SCSI generic driver sets up a mapping for each SCSI device in `/dev`. Each entry starts with `sg` (for the SCSI generic driver) followed by a number. For example, `/dev/sg0` is the first generic SCSI device. Each entry corresponds to a SCSI device in the order specified in `/proc/scsi/scsi`, from the lowest device ID on the lowest adapter to the highest device ID on the lowest adapter, and so on to the highest device ID on the highest adapter.

Some Linux devices such as tape drives, disk drives, and CD-ROM drives already have a designated `/dev` entry (`st`, `sd`, and `sr`, respectively). When the SCSI generic driver is installed, Linux identifies these devices with corresponding `sg` entries in `/dev` in addition to their traditional entries. Workstation ensures that multiple programs are not using the same `/dev/sg` entry at the same time but cannot always ensure that multiple programs are not using the `/dev/sg` entry and the traditional `/dev` entry at the same time. When you specify which SCSI device to use in a virtual machine, do not specify `/dev/st0` or `/dev/sr0`.



CAUTION Do not attempt to use the same generic SCSI device in both host and guest. This can cause unexpected behavior and might cause loss or corruption of data.

Add a Generic SCSI Device to a Virtual Machine

To map virtual SCSI devices on a virtual machine to physical generic SCSI devices on the host, you must add a generic SCSI device to the virtual machine.

Before you begin, make sure you have the following required permissions:

- On Windows hosts, to access host SCSI devices as generic SCSI devices, you must run Workstation as a user with administrator access.
- On Linux hosts, generic SCSI requires version 2.1.36 or higher of the SCSI Generic (`sg.o`) driver, which comes with kernel 2.2.14 and higher. Also, you must be logged on as a user who has permissions to use the device (that is, read and write permissions).

To add a generic SCSI device to a virtual machine

- 1 Select the virtual machine.
- 2 Choose **VM > Settings**.
- 3 On the **Hardware** tab, click **Add** to start the Add Hardware wizard.
- 4 On the Hardware Type page, select **Generic SCSI Device** and click **Next**.

- 5 On the Choose SCSI Device page, from the drop-down menu of SCSI devices, select the physical device to map.

If you do not see the device you want in the list, see [“Troubleshoot Problems Detecting Generic SCSI Devices”](#) on page 364.

On Linux hosts, if you type in the path to the SCSI device, do not enter `/dev/st0` or `/dev/sr0`.

- 6 Select the **Connect at power on** check box to configure automatic connection behavior and click **Finish**.
- 7 On the **Hardware** tab, in the **Virtual device node** section, select the SCSI device identifier to use for the drive and click **OK**.

For example, if you select SCSI 0:2, the guest operating system sees the drive as ID 2 on controller 0.

Troubleshoot Problems Detecting Generic SCSI Devices

When you use the virtual machine settings editor to add a generic SCSI device to a virtual machine, occasionally the device does not appear in the list of available SCSI devices.

Before you begin troubleshooting this problem, you might need to know the following:

- The SCSI bus number that the device uses on the host system. The SCSI bus is assigned a number by the host operating system after all IDE buses are assigned numbers. For example, if you have two IDE buses, they are numbered 0 and 1. The first SCSI bus is assigned bus number 2.

If you cannot determine the SCSI bus number, try using a third-party tool such as `winobj` to determine this information. You can download `winobj` for free from the Windows Sysinternals Web site.

- The target ID the device uses in the virtual machine and on the host. This ID is usually set by some jumpers or switches on the device. To determine the target ID, see the owner's manual for the device.

The main reasons Workstation cannot detect a device include the following:

- A driver for that device is not installed on the host.
- A driver on the host prevents the device from being detected.
- The virtual machine uses a device for which there are no drivers available to the host operating system. In this case, add the device manually to the virtual machine's configuration (.vmx) file. Adding a device in this manner is recommended for advanced users only.

To troubleshoot problems detecting generic SCSI devices

- 1 Find out whether the device driver for this device is installed on the host.
- 2 If the device driver is not installed and you want to install it, do so and see if the device appears correctly in the virtual machine settings editor.

You might not want to install the driver on the host if you want to avoid a device-in-use conflict between the host and guest.

If a driver is installed but does not appear correctly, if you cannot install the driver on the host, or if you do not want to install the driver on the host, continue with the rest of this procedure.

- 3 If an original SCSI device driver is already installed on the host, disable it.
Some Windows operating systems do not process the send command from the adapter if the device driver owns the device.
- 4 Power off the virtual machine and open the virtual machine's configuration (.vmx) file in a text editor.
- 5 Add or change the following line in the .vmx file, where *X* is the SCSI bus number the device uses on the host system, and *Y* is the target ID the device uses both in the virtual machine and on the host:

```
scsiZ:Y.fileName = "<deviceName>"
```

For "<deviceName>" use:

```
"scsiX:Y"
```

The following is an example of how to set the option. The problematic device is a CD-ROM drive, and the existing entry in the configuration file is:

```
scsi0:4.fileName = "CdRom0"
```

If the device on the host is located on bus 2 with target ID 4, change this line to:

```
scsi0:4.fileName = "scsi2:4"
```

If your problem was that the virtual machine has a SCSI adapter and generic SCSI device, but Workstation did not recognize the device when the virtual machine was powered on, you can stop at this point.

- 6 If the virtual machine does not contain any SCSI devices, to add a generic SCSI device to a new virtual SCSI adapter, or to use an existing SCSI device as a generic SCSI device, add the following line in the `.vmx` file:

```
scsiZ:Y.deviceType = "scsi-passthru"
```

If you wanted to use an existing SCSI device as a generic SCSI device, you can stop at this point.

- 7 If the virtual machine does not contain any SCSI devices, or to add a generic SCSI device to a new virtual SCSI adapter, add the following lines in the `.vmx` file, where Z is the SCSI bus number the device uses in the virtual machine:

```
scsiZ:Y.present = "true"
```

```
scsiZ.present = "true"
```

If the virtual machine settings editor still does not include this device in the list of available SCSI devices for this virtual machine, contact VMware technical support.

Use Four-Way Virtual Symmetric Multiprocessing

With Virtual SMP, you can assign processors and cores per processor to a virtual machine on any host machine that has at least two logical processors.

The following are all considered to have two or more logical processors:

- A multiprocessor host with two or more physical CPUs
- A single-processor host with a multicore CPU
- A single-processor host with hyperthreading enabled

NOTE On hyperthreaded uniprocessor hosts, performance of virtual machines with Virtual SMP might be below normal. Even on multiprocessor hosts, performance is affected if you overcommit by running multiple workloads that require more total CPU resources than are physically available.

You can power on and run multiple dual-processor virtual machines concurrently.

The number of processors for a given virtual machine appears in the summary view of the virtual machine.

To use four-way virtual symmetric multiprocessing

Do one of the following:

- For a new virtual machine, choose the custom configuration in the New Virtual Machine wizard. On the Processor Configuration page, specify the number.
- For an existing virtual machine, choose **VM > Settings** and on the **Hardware** tab, select **Processors** and specify the number.

Use a Virtual Machine That Originally Had More Than Four Virtual Processors

You can use Workstation 7.0, running on a multiprocessor host machine, to open a virtual machine created in ESX Server that has one or more virtual processors. You cannot use Workstation, however, to power on a virtual machine that has more than four virtual processors assigned, even if more processors were assigned when the virtual machine was created in ESX Server.

You can see the number of processors in the virtual machine's summary view or by using the virtual machine settings editor. To use a virtual machine that has more than four virtual processors assigned, you must change the number of processors before powering it on.

To use a virtual machine that originally had more than four virtual processors

- 1 Select the virtual machine.
- 2 Make sure the virtual machine is powered off.
- 3 Choose **VM > Settings**.
- 4 On the **Hardware** tab, select **Processors**, and note that **Number of Processors** is set to **Other (x)**, where **x** is the number of processors originally assigned in ESX Server.

Workstation preserves this original configuration setting for the number of processors, even though two is the maximum number of processors supported.

After you commit a change to this setting, the original setting for the number of processors is discarded and no longer appears as an option in the virtual machine settings editor.

- 5 Change the **Number of processors** setting to **One**, **Two**, or **Four** and click **OK**.

Special-Purpose Configuration Options for Windows Hosts

17

You can use configuration options for tasks, such as restricting the operations a user can perform with a virtual machine or simplifying the user interface for inexperienced users. In a classroom, for example, you can ensure that virtual machine configurations remain consistent from one class session to the next.

This chapter includes the following topics:

- [“Restricting the User Interface”](#) on page 369
- [“Making a Virtual Machine Always Use Full Screen Switch Mode”](#) on page 372
- [“Guest ACPI S1 Sleep”](#) on page 380

Restricting the User Interface

To enable the restricted user interface, a user must have sufficient privileges to edit the virtual machine’s configuration file and to set file permissions. The restricted user interface affects only the specific virtual machines for which the setting is created.

The following changes occur when you enable the restricted user interface:

- The toolbar is always hidden.
- All functions on the **VM > Power** menu, **Snapshot** menu, **Replay** menu, and **Removable Devices** menu are disabled.
- No access is provided to the virtual machine settings editor (**VM > Settings**).

- The user cannot change virtual networking settings (**Edit > Virtual Network Editor**).
- The user starts the virtual machine by double-clicking the configuration (.vmx) file or a desktop shortcut. The user shuts down by closing the virtual machine (**File > Exit**). It is also possible to launch Workstation and open a restricted-interface virtual machine from the **Favorites** list or **File** menu.

Enable the Restricted User Interface

Although the restricted user interface provides no access to menu and toolbar controls for a snapshot, you can give users limited snapshot control. If you set up a snapshot for the restricted virtual machine and set the power-off option to **Ask Me**, the standard dialog box appears when a virtual machine shuts down and the user can choose **Just Power Off**, **Take Snapshot**, or **Revert to Snapshot**.

To enable the restricted user interface

- 1 Power off the virtual machine and close the VMware Workstation window.
- 2 Open the virtual machine's configuration file (.vmx file) in a text editor.
- 3 Add the following line anywhere in the file:
`gui.restricted = "TRUE"`
- 4 (Optional) Set file permissions on the configuration file to give normal users of the system only read access to the file.
- 5 Create a shortcut to the configuration file on the desktop and give it an appropriate name.

Restrict the User Interface and Return to a Snapshot

You can combine a restricted user interface with a snapshot to ensure that users' virtual machines always start in the same state. Typically, users running a virtual machine with a restricted user interface can only power it on and off, and the virtual machine boots when powered on. When the virtual machine has a snapshot set and is configured to return to that snapshot when powered off, the user can only start and power off the virtual machine. The virtual machine always starts from the snapshot.

To restrict the user interface and return to a snapshot

- 1 Power on the virtual machine and be sure it is in the appropriate state.
- 2 Create a snapshot.

See [“Take a Snapshot”](#) on page 209.

- 3 Configure the virtual machine to return to the snapshot any time it is powered off: Choose **VM > Settings > Options > Snapshot/Replay** and select **After Powering Off** and **Revert to Snapshot**.
- 4 With the virtual machine powered off, restrict the user interface, as follows:
 - a Close the VMware Workstation window.
 - b Open the virtual machine's configuration file (.vmx file) in a text editor.
 - c Add the following line anywhere in the file.


```
gui.restricted = "TRUE"
```
- 5 (Optional) Set file permissions on the configuration file to give normal users of the system read-only access to the file.
- 6 Create a shortcut to the configuration file on the desktop and name it.
- 7 Run this virtual machine by double-clicking the shortcut to the configuration file.

The virtual machine starts at the snapshot, with the user interface restricted. Users do not have a toolbar or access to the **VM > Power** menu or the virtual machine settings editor.
- 8 Choose **File > Close**.

The virtual machine powers off, and the next time a user powers it on, it returns to the snapshot.

Disable the Restricted User Interface

Disable the restricted user interface to make items in the **VM** menu available to users again.

To disable the restricted user interface

- 1 Power off the virtual machine and close the VMware Workstation window.
- 2 Open the configuration file (.vmx) file and do one of the following:
 - Set `gui.restricted = "FALSE"`.
 - Remove or comment out the `gui.restricted = "TRUE"` line.
- 3 Save the changes to the configuration file and close it.
- 4 Start the virtual machine by double-clicking the shortcut.

The virtual machine starts at the snapshot, and the interface is not restricted.

Making a Virtual Machine Always Use Full Screen Switch Mode

Full screen switch mode is a runtime option for Workstation on Windows hosts. When Workstation is running in full screen switch mode, the user has no access to the Workstation user interface. The user cannot create, reconfigure, or launch virtual machines. A system administrator performs these functions.

When Workstation is running in full screen switch mode, one or more virtual machines can be running, and you can use hot keys to switch from one to another. You can also provide hot-key access to the host operating system.

Specify Global Configuration Settings for Full Screen Switch Mode

To run Workstation in full screen switch mode, you must, set one or more properties in the Workstation global configuration file.

The global configuration file is created when you change any of the default settings in the Workstation preferences editor (**Edit > Preferences**). The file location depends on the host operating system:

- On most Windows hosts:
C:\Documents and Settings\All Users\Application Data\VMware\VMware Workstation\config.ini
- On most Windows Vista and Windows 7 hosts:
c:\ProgramData\VMware\VMware Workstation\config.ini

To specify global configuration settings for full screen switch mode

- 1 If the config.ini file does not yet exist on your host computer, choose **Edit > Preferences** and change at least one of the settings in the preference editor.
- 2 Open the config.ini file with a text editor and add at least one of the following lines:

- **fullScreenSwitch.cycleHost = "TRUE"**

This setting causes the host operating system to be included when you use a hot key for cycling through powered on virtual machines. See [“Hot Key for Cycling Through Virtual Machines and the Host Computer”](#) on page 375.

- **FullScreenSwitch.hostDirectKey = "<value>"**

Use this setting to define a hot key for switching directly to the host operating system. See [“Host Operating System Hot Key”](#) on page 376.

- 3 (Optional) Specify other full screen switch mode settings you want to use.

To specify hot keys for switching to other virtual machines or the host computer, first, see the following sections, in the order listed:

- [“Virtual Key Codes”](#) on page 373
- [“Other Entries in the Global Configuration File”](#) on page 376

- 4 Save and close the file.

- 5 Set permissions on this file so that other users cannot change it.

- 6 Open the `preferences.ini` file with a text editor and add the following lines:

```
pref.fullScreen.v5 = "TRUE"
pref.autoFitFullScreen = "fitGuestToHost"
```

On most Windows hosts, this file is located in:

```
%USERPROFILE%\Application Data\VMware\preferences.ini
```

On Windows Vista and Windows 7 hosts, this file is located in:

```
%USERPROFILE%\AppData\Roaming\VMware\preferences.ini
```

To specify a hot key for switching to a specific virtual machine, see [“Virtual Machine Hot Key”](#) on page 376.

Virtual Key Codes

To configure hot keys for use when running Workstation in full screen switch mode, you must specify the virtual key code for each hot key. Virtual key codes use hexadecimal format, which is a hexadecimal number preceded by 0x. For example, to use the virtual key code of 5A as a value, type **0x5A**.

Microsoft provides a reference list of virtual key codes. To access this reference list, enter the keyword virtual key codes on the MSDN Web site.

The hot-key entries also include modifier keys. The modifier keys are Ctrl, Alt, Shift, and Windows keys. The Windows key is the key between the Ctrl and Alt keys. You can also use a combination of those keys. [Table 17-1](#) lists the key codes for modifier keys.

Table 17-1. Modifier Keys for Hot-Key Entries

Modifier Key	Hexadecimal Value
No modifier	0x0
Alt	0x1
Ctrl	0x2
Shift	0x4
Win (Windows)	0x8
Ctrl+Alt	0x3
Alt+Shift	0x5
Ctrl+Shift	0x6
Ctrl+Alt+Shift	0x7
Win+Alt	0x9
Win+Ctrl	0xa
Win+Ctrl+Alt	0xb
Win+Shift	0xc
Win+Shift+Alt	0xd
Win+Shift+Ctrl	0xe
Win+Shift+Ctrl+Alt	0xf

Keep the following limitations in mind when defining cycle keys and switch keys:

- Do not use the Pause key with the Ctrl key. You can use the Pause key with other modifier keys.
- If you use the F12 key, you must use one or more modifier keys. You cannot use the F12 key alone.
- You cannot use combinations that include only the Shift, Ctrl, and Alt keys. These keys can be used only as modifiers in combination with some other key.

When listing a key plus a modifier, type the virtual key code for the key followed by a comma and type the value for the modifier key or keys. For example, the value entry for Ctrl+Shift+F1 is 0x70,0x6.

Hot Key for Cycling Through Virtual Machines and the Host Computer

You can specify a hot key or hot-key combination for cycling through the available virtual machines on a host computer when running Workstation in full screen switch mode. Hot keys behave in the following manner:

- Each time you press the specified hot key, the next virtual machine appears in order. You can also include the host operating system in the cycle.
- If any particular virtual machine is not running, it is skipped.
- If only one virtual machine is running and the host operating system is not included in the cycle, pressing the hot key has no effect.

The hot key for cycling through virtual machines is defined in the global configuration file (`config.ini`). Two options control cycling:

- `FullScreenSwitch.cycleKey`

The value of this option defines the hot key. It is specified as `<key>, <modifier>`. It has no default. For example, to use the Pause key with no modifier to cycle through virtual machines, add the following line to the `config.ini` file, or modify its value if the option is already listed:

```
FullScreenSwitch.cycleKey = "0x13,0x0"
```

- `FullScreenSwitch.cycleHost`

Set this option to `TRUE` to include the host operating system in the cycle. The default is `FALSE`. For example, to include the host operating system in the cycle, add the following line to the `config.ini` file, or modify its value if the option is already listed:

```
FullScreenSwitch.cycleHost = "TRUE"
```

Hot Keys for Switching Directly to Virtual Machines and the Host Computer

You can specify a hot key or combination of hot keys for switching directly to any available virtual machine on a host computer when running Workstation in full screen switch mode. Each time you press the specified hot key, the screen display switches to that of the specified virtual machine. You can also specify a hot key for switching directly to the host operating system.

Virtual Machine Hot Key

You define the hot key used to switch to a virtual machine by adding a local configuration setting in the virtual machine's `.vmx` file.

Use the following format:

```
<option> = "<value>"
```

Entries in the configuration files can appear in any order. The value of this option defines the hot key. It is specified as `<key>`, `<modifier>`. It has no default.

For example, to use Ctrl+Shift+F1 to switch to a particular virtual machine, add the following line to that virtual machine's `.vmx` file or modify its value if the option is already listed:

```
FullScreenSwitch.directKey = "0x70,0x6"
```

If any particular virtual machine is not running, pressing the hot key for that virtual machine has no effect.

Host Operating System Hot Key

You define the hot key used to switch to the host operating system by adding a line to the global configuration file (`config.ini`). The value of this option defines the hot key. It is specified as `<key>`, `<modifier>`. It has no default.

For example, to use Ctrl+Shift+F9 to switch to the host operating system, add the following line to the `config.ini` file, or modify its value if the option is already listed:

```
FullScreenSwitch.hostDirectKey = "0x78,0x6"
```

Other Entries in the Global Configuration File

The global configuration file (`config.ini`) entries in [Table 17-2](#) are optional. They enable you to control certain functions of the virtual machine that are important in work environments where virtual machines need to be isolated from each other and from the host computer.

Table 17-2. Optional Global Configuration File Entries

Option	Description	Default Setting
<code>Isolation.tools.copy.disable</code>	This option determines whether data in one virtual machine or the host operating system can be copied to another virtual machine or to the host operating system.	TRUE
<code>Isolation.tools.paste.disable</code>	This option determines whether data copied in one virtual machine or the host operating system can be pasted into another virtual machine or the host operating system.	TRUE
<code>Isolation.tools.HGFS.disable</code>	When set to TRUE, this option specifies that folder sharing is disabled by default. Folder sharing is one method of sharing files among virtual machines and with the host computer.	TRUE
<code>mks.CtlAltDel.ignore</code>	Set this property to TRUE so that dialog boxes usually generated by Microsoft Windows Secure Attention Sequence (SAS) are not displayed but are passed on to the guest if the guest has keyboard focus.	
<code>mks.fullscreen.allScreenSaver</code>	Set this property to TRUE to allow the host operating system to run its screen saver when it determines that the machine is idle.	
<code>msg.autoAnswer</code>	Set this property to TRUE to suppress any Workstation dialog boxes that otherwise appear. The default answer is selected in these dialog boxes.	

Using `vmware-fullscreen` to Run a Virtual Machine

Use the `vmware-fullscreen` command to run Workstation in full screen switch mode and to start and stop virtual machines on a user's computer. The command can pass certain information to the virtual machine when it starts.

As administrator, you must decide how to issue the command. For example, you can use a custom application or script running on the host operating system to issue one or more `vmware-fullscreen` commands. Or you can include the command to start a virtual machine in a shortcut in the host operating system's startup group, so the virtual machine starts when the user logs in to the host computer.

Issue the `vmware-fullscreen` command once for each virtual machine you want to start or stop. The syntax for this command is:

```
C:\Program Files\VMware\VMware Workstation\vmware-fullscreen.exe [-poweron
    <parameters> | -poweroff <parameters> | -exit | -switchto
    <parameters> | -query | -listvms]
```

You can type these commands at the Windows command prompt or create scripts to run multiple commands.

Table 17-3 describes the available options and parameters.

Table 17-3. Command-Line Options for the `vmware-fullscreen` Program

Option	Parameters	Description
<code>-poweron</code> or <code>-fullscreen</code>	"<config-file>"	Powers on the virtual machine, where "<config-file>" is required and specifies the full path to the virtual machine's configuration (.vmx) file. With <code>-poweron</code> , the user sees no immediate indication when the virtual machine starts, but the user can switch to the virtual machine with its direct-switch key or with the cycle key. With <code>-fullscreen</code> , the virtual machine goes to full screen mode immediately instead of running invisibly until the user switches to it later.
	<code>-s <variable>=<value></code>	(Optional) Sets the specified variable to the specified value. Any variable names and values that are valid in the configuration file can be specified on the command line with the <code>-s</code> switch.
	<code>-name=<alias></code>	(Optional) Gives an alias to the virtual machine. You can use that alias in <code>-switchto</code> and <code>-poweroff</code> commands.
	<code>-directkey=<keyspec></code>	(Optional) Specifies the virtual machine's direct-switch key. If a direct-switch key is specified in the virtual machine's configuration file, the command line overrides the configuration file. The following is an example of this switch: <code>-directkey=0x70,0x6</code>
<code>-poweroff</code> or <code><alias></code>	"<config-file>" or <code><alias></code>	Powers off the specified virtual machine. To specify the virtual machine, use either the full path to the virtual machine's configuration (.vmx) file or the alias if you defined one by using the <code>-name</code> switch.
<code>-exit</code>		Powers off all virtual machines and exits Workstation.

Table 17-3. Command-Line Options for the `vmware-fullscreen` Program (Continued)

Option	Parameters	Description
<code>-switchto</code>		Depending on the parameter you use, switches to the specified virtual machine, host operating system, or next machine (virtual machine or host) in the cycling order. A virtual machine must be powered on before you can switch to it.
	<code>"<config-file>"</code>	Switches to the virtual machine, where <code>"<config-file>"</code> specifies the full path to the virtual machine's configuration (<code>.vmx</code>) file.
	<code><alias></code>	Switches to the virtual machine, where <code><alias></code> specifies the alias you defined by using the <code>-name</code> switch.
	<code>host</code>	Switches to the host operating system.
	<code>next -qu</code>	Switches to the next machine in the cycling order.
<code>-query</code>		Determines whether Workstation is running in full screen switch mode. If so, also displays the process ID and window handle.
<code>-listvms</code>		Lists all virtual machines that are currently powered on. The list is added to the <code>vmware-fullscreen</code> log file.

vmware-fullscreen Log File

The `vmware-fullscreen` program writes to a log file. This log file records errors reported by `vmware-fullscreen` as it starts, stops, and passes other commands to Workstation. It is separate from the `vmware.log` file, which stores information on the running virtual machines.

The name of the `vmware-fullscreen` log file is `vmware-<username>-<pid>.log`. By default, the `vmware-fullscreen` log file is in the `temp` directory for the user logged in to the host computer. This location might be specified in the `TEMP` environment variable. The default location is:

- On Windows XP hosts:
C:\Documents and Settings\<username>\Local Settings\Temp
- On Windows Vista and Windows 7 hosts:
C:\Users\<username>\AppData\Local\Temp\

The administrator can specify a different location for this log file by adding the following line to the Workstation global configuration file (`config.ini`):

```
fullScreenSwitch.log.filename="<path>"
```

VMware recommends using a full path. If you use a relative path, the location is relative to the directory that is active when the `vmware-fullscreen` command is issued for the first time after the host computer reboots.

Guest ACPI S1 Sleep

Workstation provides experimental support for guest operating system ACPI S1 sleep. Not all guest operating systems support this feature. Common guest operating system interfaces for entering standby are supported.

By default, ACPI S1 sleep is implemented in Workstation as suspend. You can use the Workstation **Resume** button to wake the guest.

With the following entry in the configuration (.vmx) file for a virtual machine, ACPI S1 sleep is instead implemented as power-on suspend:

```
chipset.onlineStandby = TRUE
```

The guest operating system is not fully powered down. You can awaken the virtual machine in the following ways:

- Keyboard input
- Mouse input
- Programming the CMOS external timer

This feature can be useful for test and development scenarios.

Learning the Basics of VMware ACE

18

This chapter provides an overview of how to use Workstation to create and deploy virtual machines for end users. ACE (Assured Computing Environment) features are available only in the version of Workstation that runs on Windows hosts. This chapter includes the following topics:

- [“Benefits of Using VMware ACE”](#) on page 381
- [“Network and Disk Space Requirements for the Administrative Workstation”](#) on page 384
- [“Overview of Creating and Deploying ACE Packages”](#) on page 385
- [“Overview of the ACE User Interface”](#) on page 386
- [“Troubleshooting Users’ Problems”](#) on page 387

Benefits of Using VMware ACE

VMware ACE is a software solution that enables organizations to deploy and manage secure, platform-independent virtual machines that end users can use on their work PC, personal computer, or even a portable USB media device. End users can be either connected to or disconnected from the enterprise network.

VMware ACE enables safe access to enterprise resources from assured computing environments. These isolated PC environments run on top of existing PCs. The assured computing environment (ACE) contains an operating system, enterprise applications, and preconfigured security settings.

With virtual rights management, built-in copy protection controls, and automatic encryption, VMware ACE helps prevent theft, tampering, and unauthorized copying of applications, data, system settings, and files. Administrators can protect data and ensure compliance with IT policies, including software life-cycle management and access to data and applications.

Key Features of VMware ACE

The key features of VMware ACE include manageability, security, and usability.

Manageability

- Create standardized hardware-independent PC environments and deploy them to any PC throughout the extended enterprise.
- Control the virtual machine's life-cycle, security settings, network settings, system configuration, and user interface capabilities.
- Track instances through the user interface. View and manage the activation, expiration, and other policies of instances managed with ACE Management Server.

Security

- Rules-based network access lets you identify and quarantine unauthorized or out-of-date ACE instances. Enable access to the network once the ACE instance complies with IT policies.
- Tamper-resistant computing environment protects the entire ACE instance and package, including data and system configuration, with seamless encryption.
- Copy-protected computing environment prevents users from copying enterprise information.
- Roles-based SSL communication provides a secure protocol between the ACE Management Server and client.
- Resource signing lets you specify that ACE Resource files be protected from all tampering.

Usability

- The customizable interface lets you customize the behavior and look and feel for users.
- Pocket ACE lets you store a computing environment on portable devices such as USB keys (flash memory drives), Apple iPod mobile digital devices, and portable hard drives. You can plug the portable device into any x86 PC.
- The flexible computing environment lets users revert to a previous state within seconds and can work when connected or disconnected from the enterprise network.

VMware ACE Terminology

The following terms are used frequently in the chapters describing VMware ACE features:

- **ACE-enabled virtual machine** – A virtual machine template that the ACE administrator creates. The ACE-enabled virtual machine can be configured with various policies, devices, and deployment settings and then used as the basis for creating any number of packages to be sent to ACE users.
- **ACE instance** – The virtual machine that ACE administrators create, associate with policies, and activate on end users' computers. An ACE instance that is managed by ACE Management Server is a managed ACE instance. An ACE instance that is not managed by ACE Management Server is a standalone ACE instance.
- (Optional) **ACE Management Server** – The ACE Management Server enables you to manage ACE instances, to publish policy changes to dynamically update those instances, and to test and deploy packages more easily. ACE Management Server adds new integration with Active Directory setups and provides secure Active Directory and LDAP integration, with role-based secure SSL communication.

For more information, see the *VMware ACE Management Server Administrator's Guide*.

- **Pocket ACE** – Enables an administrator to bundle and deploy an ACE instance onto a USB portable media device, including USB flash drives, Apple iPod mobile digital devices, and portable hard drives.

Network and Disk Space Requirements for the Administrative Workstation

As an administrator, you use Workstation to create and manage the virtual machines you distribute to end users. Following is a list of prerequisites for the machine that hosts Workstation:

- If your company already has a library of standard virtual machines, you need network access to that library from your host computer.
- If you are creating virtual machines, you need access to installers for the guest operating systems and application software that you plan to install in the virtual machines.

You can install operating systems from CDs, DVDs, ISO image files on a local drive or on the network, or a PXE server. You can install application software from CDs, DVDs, or installers on a local drive or on the network.

- You need to provide adequate disk space for virtual machine files and package files. The files for each virtual machine can be as large as several gigabytes. The package files can also be large. The default location for the package files is the `Packages` folder inside the virtual machine's folder.
- Workstation needs a substantial amount of temporary working space when it creates a package. The total disk space required is about twice the combined sizes of all the components of the package. The New Package wizard displays information about the amount of space needed and the locations where the space is needed.
- Workstation must be installed on a Windows host.

Overview of Creating and Deploying ACE Packages

The following is an overview of the tasks you must perform to create, deploy, and manage ACE instances.

- 1 With Workstation on a Windows host, create or clone a virtual machine that meets the requirements of your end users.

The procedures are the same as for any virtual machine. For the network type, VMware recommends using Network Address Translation (NAT) or bridged networking with an IP address a DHCP server provides.

- 2 Make sure the virtual machine is powered off, display the summary view for the virtual machine, and click **Enable ACE Features** in the **Commands** list.

ACE-specific commands are added to the **Commands** list in the summary view, and the **VM > ACE** menu is enabled.

- 3 Use the **VM > Settings** menu to configure the virtual machine.

(Optional) Use the ACE Options settings panel to associate the virtual machine with an ACE Management Server. You can then use the server to activate and track instances and make changes to policies, instance customization data, and other data for each ACE instance.

Because managed ACE instances check periodically for updates, the updates are dynamic. You do not need to create and deploy new update packages. See the *VMware ACE Management Server Administrator's Guide*.

- 4 Install a guest operating system, VMware Tools, and other software in the virtual machine.

The procedures are the same as for any virtual machine. For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources >**

Compatibility Guides, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link

- 5 Set policies for the ACE instance.

Policies control such things as what network access end users have from ACE instances and what devices on their host computers they may use in the instances. See [Chapter 19, "Setting and Using Policies and Customizing VMware Player,"](#) on page 389.

- 6 Specify deployment settings for the ACE instance.

Deployment settings control such things as encryption, package lifetime, and security IDs. See [Chapter 20, “Deploying ACE Packages,”](#) on page 435.

- 7 Create packages to deploy to end users.

Workstation guides you through the process. See [“Creating a Package”](#) on page 449 or [Chapter 21, “Pocket ACE,”](#) on page 457.

- 8 Distribute packages to end users.

Distribute the packages on CD, DVD, or portable media, or make them available on a network. See [“Deploy Packages”](#) on page 456 or [“Deploying the ACE Package on a Portable Device”](#) on page 461.

- 9 Install ACE instances on end users’ machines.

See [“Installing ACE Packages”](#) on page 465 or [“Run the Pocket ACE Instance”](#) on page 463.

You can install multiple ACE instances on the same machine. They can be from different vendors and be governed by different policies. You can also uninstall individual ACE instances or Workstation while leaving other ACE instances installed.

- 10 Keep users up-to-date.

If you need to update the guest operating system, update a program running inside the ACE instance, or change policies set for the ACE package, you can create and distribute a new package.

Package updates do not upgrade the virtual machine version. You can use a package update to provide end users with VMware ACE 2.6 policies, but the update package does not update ACE Player or the virtual machine to version 2.6.

Overview of the ACE User Interface

Use any of the following methods to access the policy editor, deployment settings editor, and packaging wizards:

- Select the ACE-enabled virtual machine and choose a command from the **VM > ACE** menu.
- In the summary view for the ACE-enabled virtual machine, click an ACE-related command in the **Commands** list.

The **ACE** tab in the summary view lists the current settings for policies and deployment.

- Click a button in the ACE toolbar.
- Right-click the ACE-enabled virtual machine in the sidebar and choose an ACE-related command.

ACE Management Server has two interfaces:

- In Workstation, select an ACE Management Server in the sidebar to display the instance view.
- Use the VMware Help Desk application. Because this interface is browser-based, you can use it from machines that do not have Workstation installed.

Both interfaces offer the same basic functionality. Administrators can view and control all managed ACE instances. An advanced search function allows you to locate instances in the database quickly. You can customize the interface by adding searchable custom fields. See the *VMware ACE Management Server Administrator's Guide*.

Troubleshooting Users' Problems

End users might need help with lost passwords, expired ACE instances, or copy-protected ACE instances that they have moved to a different location.

Use one of the following methods to fix those problems:

- **Managed ACE instances** – Use ACE Management Server. See the *VMware ACE Management Server Administrator's Guide*.
- **Standalone ACE instances** – Use the `vmware-acetool` command-line program to fix those problems directly on the users' machines. See [“Using the vmware-acetool Command-Line Tool”](#) on page 479.

You can also use the hot-fix feature to respond to these problems. See [“Setting Hot-Fix Policies for Standalone ACE Instances”](#) on page 421 and [“Respond to Hot Fix Requests”](#) on page 481.

You might find it useful to modify the configuration of an ACE instance on an end-user's computer. Administrator mode enables you to access and use the virtual machine settings editor when running the ACE instance with VMware Player on the user's computer. See [“Setting Administrator Mode Policies”](#) on page 419.

Setting and Using Policies and Customizing VMware Player

19

This chapter describes how to set policies for an ACE-enabled virtual machine and customize the VMware Player interface for end users. This chapter includes the following topics:

- [“Benefits of Using Policies”](#) on page 390
- [“Set Policies for ACE Instances”](#) on page 390
- [“Setting Access Control Policies”](#) on page 391
- [“Setting Host to Guest Data Script Policies”](#) on page 397
- [“Setting Expiration Policies”](#) on page 399
- [“Setting Copy Protection Policies”](#) on page 400
- [“Setting Resource Signing Policies”](#) on page 401
- [“Setting Network Access Policies”](#) on page 402
- [“Setting Removable Devices Policies”](#) on page 411
- [“Setting USB Device Policies”](#) on page 412
- [“Setting Virtual Printer Policies”](#) on page 414
- [“Setting Runtime Preferences Policies”](#) on page 415
- [“Setting Snapshot Policies”](#) on page 418
- [“Setting Administrator Mode Policies”](#) on page 419
- [“Setting Kiosk Mode Policies”](#) on page 420
- [“Setting Hot-Fix Policies for Standalone ACE Instances”](#) on page 421
- [“Setting the Policy Update Frequency for Managed ACE Instances”](#) on page 421
- [“Control Which ACE Instances Run on a Host”](#) on page 422
- [“Writing Plug-In Policy Scripts”](#) on page 424
- [“Customizing the VMware Player Interface on Windows Hosts Only”](#) on page 428

Benefits of Using Policies

Policies give you control over many aspects of the ACE instances you distribute to end users. For example, you can set policies for the following security purposes:

- Permit the ACE instance to be used only by certain users and groups defined in an Active Directory domain.
- Specify which network resources end users may access from the virtual machine.
- Permit users to connect and disconnect certain removable devices configured for the virtual machine.
- Set an expiration date for an ACE instance.

You set policies with the policy editor. You can change some or all of the policies for an ACE instance at any time by editing the policies and creating and distributing a new package that contains only the policies.

For ACE-enabled virtual machines that ACE Management Server manages, you can dynamically change some policies and deploy those changes to the ACE instances on users' machines.

Set Policies for ACE Instances

Policy settings offer several levels of security for daily use of ACE instances. For information about the encryption aspect of security, see [“Edit Deployment Settings”](#) on page 435.

Before you can use the policy editor on a virtual machine, you must enable ACE features for that virtual machine. See [“Overview of Creating and Deploying ACE Packages”](#) on page 385.

To set policies for ACE instances

- 1 Select the ACE-enabled virtual machine and choose **VM > ACE > Policies**.
- 2 In the policy editor, select an item in the **Policy** list.
- 3 Complete the settings panel for that policy and either click **OK** or select another policy to edit.

For assistance with the fields on a settings panel, click **Help**.

Setting Access Control Policies

Activation and authentication policies control access to installed ACE packages and the instances created from those packages. The activation policy specifies who can access an installed ACE package and turn it into an ACE instance. The authentication policy specifies who can run an ACE instance.

The settings you choose for these policies determine the default settings for package and encryption policies, which protect the ACE packages and files in transit. See [“Encryption Settings”](#) on page 436.

The settings for these policies and how they are implemented vary depending on how your ACE instances are managed and (optionally) tracked. The possible management setups are:

- **Server, with Active Directory** – ACE instances are managed by an ACE Management Server, and the server is integrated with Active Directory.

An end user must enter Active Directory user credentials each time the ACE instance is run. Only the user who activates the instance can authenticate (run) the instance. The activation step is performed whenever an ACE package is installed.

- **Server, no Active Directory** – ACE instances are managed by an ACE Management Server, and the server is not integrated with Active Directory.

The administrator chooses whether the end user must enter a password to activate the ACE instance and run it.

- **Standalone** – ACE instances are standalone, which means they are not managed by a server.

The administrator chooses whether the end user must enter a password to activate the ACE instance and run it.

If you use ACE Management Server, the server also verifies the following items before the instance is allowed to run:

- The revocation flag is not set and the instance is not blocked from running because of any policy errors.
- The expiration date set for the instance, if any, has not been reached. See [“Setting Expiration Policies”](#) on page 399.

Create or Edit an Access Control Policy

After you enable ACE features for a virtual machine, you can create a policy to control which end users can access an installed ACE package and turn it into an ACE instance. This policy also controls which users can power on an ACE instance.

To create or edit an access control policy

- 1 Select the ACE-enabled virtual machine and choose **VM > ACE > Policies**.
- 2 In the policy editor, select **Access Control** and complete the fields in the settings panel.
- 3 Click **OK**.
- 4 Verify that the new settings appear correctly on the **ACE** tab in the virtual machine's summary view.

If you change an activation setting, the policy takes effect when a new instance from this package is installed and activated. You can also edit an imported keyword list.

- 5 (Optional) To change the authentication setting from one type to another, create a policy update package and distribute it to the user.

Activation Settings

Use activation settings to control which users can activate an ACE instance after it is installed. The activation date is used for the expiration policy.

If you use an ACE Management Server with Active Directory, the controls in the **Activation** section enable you to open the Active Directory Users and Groups dialog box. The machine on which Workstation runs must be in the same domain for which the ACE Management Server is configured. User-list changes are effective at the next startup of the instance.

If you do not use Active Directory or if you are creating standalone ACE instances, the settings panel includes the following options for activation passwords or keys:

- **None** – No password or key is required. Any user can activate this instance.
- **Password** – The user must enter the password that the administrator uses to activate this ACE instance. You must provide the user with the password through email or other means.

For standalone ACE-enabled virtual machines, you set the password during the packaging process.

- **Activation key** – This option is available if you use ACE Management Server without Active Directory integration. You specify one or more keys and the end user must enter a key that is in that list.

Activation keys are serial numbers (free-form strings) that can be tracked as used or unused by the server. You can enter the keys or import them from a text file.

To import keys, you need a text file that contains the list of activation tokens. Each token is one line in the file. Blank lines are ignored.

For an ACE-enabled virtual machine, **Allow multiple activations per key** is selected by default. To restrict allowing multiple activation of an ACE-enabled virtual machine per key, deselect this option.

Authentication Settings

The authentication step is performed whenever the user runs the instance, unless **Authentication** is set to **None**.

If you use ACE Management Server with Active Directory, the controls in the **Authentication** section enable you to open the Active Directory Users and Groups dialog box. The machine on which Workstation runs must be in the same domain that which ACE Management Server is configured for.

If you do not use Active Directory or if you are creating standalone ACE instances, the settings panel includes the following options for authentication control:

- **None** – No password is required. Any user can run this instance after it is activated.
- **User-specified password** – The instance does not run until the user enters the correct password. Each user must set a password during activation, the first time the instance is powered on.

You can create password policies to control such things as the minimum number of characters, types of characters, and number of password attempts before the user is locked out for a specified amount of time.

- **Script** – A custom authentication script is run to determine who can use the instance. See [“Using an Authentication Script”](#) on page 394.
- **Authenticate again when host resumes from suspend state** – Enables or disables authentication for ACE instances if the host is resumed from a suspended state. This option is available for standalone ACE instance, managed ACE instance without Active directory, and managed ACE instance with Active directory.

Using an Authentication Script

You can create a custom authentication script that runs on the end user's computer to determine who can use the instance.

To require that the user signs the script before deployment to prevent tampering, set a resource signing policy. See [“Setting Resource Signing Policies”](#) on page 401.

For instructions on creating and deploying the script, see [“Specify a Script and a Command to Run It”](#) on page 398.

Include a Power-On and Power-Off Script in the Package

You can provide a script that runs when an ACE instance powers on that determines whether the ACE instance can be run. You can provide a script that runs when an ACE instance powers off to reset any changes made to the host from a power-on script, reset authentication settings, or perform other procedures as the instance powers off.

To require that the user signs the script before deployment to prevent tampering, set a resource signing policy. See [“Setting Resource Signing Policies”](#) on page 401.

The power-on or power-off script provides a customizable way of controlling access to an ACE instance in addition to the authentication policy.

To include a power-on and power-off script in the package

- 1 Create the script and save it in the ACE Resources folder.
- 2 On the access control policy page, select **Script** and click **Power-on/off scripts**.
- 3 Select one or both check boxes for the scripts you want to run.
- 4 Click **Set** to specify the path to the script and enter the command to run the script.
- 5 If you are enabling a power-on or power-off script after you deployed packages, provide an update package or a custom package for the ACE Resources directory.

When the script runs on the user's system, the script prints “TRUE” for power on or “FALSE” for power off. It must also conform to standard script exit code rules. The following is an example of a power-on script:

```
# VMware Sample Script
#
# Sample script for ACE power-on hook
#
# Description:
# This sample script implements a power-on hook for ACE. This can be used
# in addition to authentication to control the circumstances under which an
# ACE is allowed to run.
```

```

#
# This script assumes that the username is defined in the environment
# variable TEST_USERNAME (a fictitious environment variable used for this
# sample) and returns TRUE if the user is allowed to run, and FALSE
# otherwise.
#
# Input to script:
# None.
#
# Returns:
# TRUE if username is on white list.
# FALSE if username is not on white list or is undefined.
#
# Expected output:
# One of the strings "TRUE" or "FALSE"
#

my @white_list = ("alan", "bob", "mary", "sonia", "chris");

my $username = $ENV{TEST_USERNAME};
if (! defined $username) {
    print "FALSE";
    exit(0);
}

my @grepNames = grep(/$username/, @white_list);
if (@grepNames == 1) {
    print "TRUE";
    exit(0);
}

print "FALSE";
exit(0);

```

Scripts can be in any language. For example, you can use a **.bat** file on Windows operating systems or **perl** or **sh** on Linux operating systems. A script provides Workstation with a command-line executable file or a script file in the **ACE Resources** directory. The guidelines a script must follow depend on which policy the script is implementing.

The script must exit with a 0 (zero) value to be considered a success. Any other output results in failure. Upon success, the **stdout** output of the script is examined. For a given policy, this should be a specific value such as **TRUE** or **FALSE**. For a power-on script, output should be **TRUE** or **FALSE**. The authentication script output is used as a password. The host to guest data script is a string in a particular format such as **guestinfo.var1="value1"\nguestinfo.var2="value2"**.

Set a Recovery Key for Encrypted ACE Instances

You can specify the key to be used for access to encrypted ACE instances. This key enables you to reset the password for a deployed ACE instance, activate an expired instance, and run a copy-protected instance.

To set a recovery key for encrypted ACE instances

- 1 On the access control policy page, click **Recovery key**.
- 2 In the Recovery Key dialog box, select **Use recovery key**.
- 3 Do one of the following:
 - To use an existing PEM-format key pair, click **Browse for Existing Key** and navigate to the public key of the pair to use.
 - To create a PEM-format key pair, click **Create New Recovery Key** and complete the dialog box that appears.

- 4 Click **OK** to generate the keys.

After several seconds, the newly generated public key is listed in the field on the **Recovery Key** tab. The two parts of the key are stored in the location you indicated, with the names you specified followed by the extensions `.pub` for the public key and `.priv` for the private key.

- 5 Record the private key password and location of the private key file so that you can supply it if you need to reset a password.

Set Activation Limit

The activation limit is the maximum number of ACE instances that can be activated from the specified ACE-enabled virtual machine. This option is available if you use ACE Management Server.

To set an activation limit

- 1 On the access control policy page, under **Activation limit**, in **Total number of activations**, choose how many instances can be activated from this ACE-enabled virtual machine.

You can use the drop-down menu or type in a number.

- 2 Select **Allow multiple activation per user** to allow users multiple activation of the ACE-enabled virtual machine.

This option is available for an ACE instance managed by ACE Management Server with Active Directory.

Active Directory Password Change Proxying

You can provide additional security for your ACE instances by integrating with Active Directory.

You can specify password expiration and change requirements, set up the domain to expire passwords, and require password changes periodically. These settings are in addition to ACE access control policy settings.

In cases in which Active Directory users need to change their passwords, you can configure ACE Management Server as an Active Directory password change proxy. In this mode, ACE Management Server makes the password change request to the Active Directory domain controller on the user's behalf.

Setting Host to Guest Data Script Policies

You can provide a host to guest data script that runs when the ACE instance is powered on. It passes values to the guest. Use this policy setting to share specific host information with the guest operating system when the ACE instance is powered on.

The script, which runs on the host, should output a set of key-value pairs, which become available to the applications that are running inside the guest. The VMware Tools service provides this ability. The set of acceptable keys consists of `machine.id` and keys prefixed with `guestinfo`, such as `guestinfo.ipAddress`.

Keys can contain alphanumeric characters and symbols, including the period (`.`), underscore (`_`), backslash (`\`) and pipe (`|`) characters. The new line, `#`, space, and forward slash (`/`) characters are invalid for the key. Values can contain alphanumeric characters. The `#`, space, and pipe (`|`) characters are invalid for the key. Any key-value pair that contains invalid characters is ignored silently.

Since spaces are invalid, using a phrase like `My Documents` as part of a folder path value does not work. Instead, enclose the phrase in quotation marks: `"My Documents"`. Alternatively, you can use the short 8.3 DOS name (in this case, `mydoc~1`), which does not contain a space. To obtain the short 8.3 DOS names for the subdirectories in a directory, enter `dir /x` at the command prompt.

To query key values that have already been set

Do one of the following:

- From a Windows guest, enter the following at a command prompt:

```
cd "C:\Program Files\VMware\VMware Tools"
vmtoolsd.exe --cmd "machine.id.get"
vmtoolsd.exe --cmd "info-get guestinfo.<key_to_query>"
vmtoolsd.exe --cmd "info-get guestinfo.script_status"
```

- From a Linux guest, enter the following at a command prompt:

```
vmtoolsd --cmd "machine.id.get"
vmtoolsd --cmd "info-get guestinfo.<key_to_query>"
vmtoolsd --cmd "info-get guestinfo.script_status"
```

If the ACE-enabled virtual machine for an instance is configured for both Windows and Linux platforms, you can provide scripts for both Windows and Linux systems.

Changes to a script require that you deploy an update package that includes the new script.

For instructions on creating and deploying the script, see [“Specify a Script and a Command to Run It”](#) on page 398.

Specify a Script and a Command to Run It

The procedure for using authentication scripts and host-guest data scripts is identical.

Use this procedure for the following scripts:

- **Access control authentication script** – Custom authentication script that runs on the end user's computer to determine who can use the ACE instance.

If you plan to use the script with a Pocket ACE that will run on both Windows and Linux hosts, make sure that the script outputs on both platforms are exactly the same, including characters for line endings or new lines.

- **Host-guest data script** – Script for sharing host information such as the host machine ID and IP address with applications that run on the guest.

To specify a script and a command to run it

- 1 Create the script and save it in the ACE Resources directory inside the virtual machine's directory.
- 2 In Workstation, select the ACE-enabled virtual machine and choose **VM > ACE > Policies**.

- 3 In the policy editor, do one of the following:
 - If the script is a custom authentication script, select **Access Control** and in the **Authentication** section, select **Script** and click **Set Script**.
 - If the script is for passing host information to the guest, select **Host-Guest Data Script**, select **Run a host-guest script at power on**, and click **Set**.
- 4 In the dialog box that appears, browse to the script file and click **Open**.
 If the deployment platform setting in the deployment settings editor is set to **Both Windows and Linux**, this dialog box contains text fields for both Windows and Linux.
- 5 Type the command for running the script.
 Include the script file in the command line, as well as any needed executable file for running the script and any arguments to the script.
- 6 (Optional) Select **Timeout** and type a timeout interval in seconds, in case the script does not run to completion.
 The user is denied access if the timeout interval elapses before the script runs to completion.
- 7 Click **OK**.
- 8 If you are enabling this script for an ACE-enabled virtual machine that you already deployed, do one of the following:
 - For standalone instances, include the script in the update package you distribute to end users.
 - For managed instances, use a policy and server update package or a custom package that includes the ACE **Resources** directory to provide end users with the script.

Setting Expiration Policies

Expiration policies are useful, for instance, if you want to prevent a contract employee from using a virtual machine past a certain date or for more than a certain number of days.

When an instance expires, the files remain on the user's computer, but the instance cannot be used. This way, the user can request an extension to the expiration date.

If you specify a date range, the instance can be powered on and run no earlier or later than the start and end dates. You can deploy ACE instances with expired date ranges.

You can also set and customize a warning message that appears each time an instance powers on as the expiration date approaches. An expiration message appears when the instance expires and the instance can no longer be powered on.

A standalone ACE instance has the same expiration policy as all instances created from the corresponding ACE package. The fixed expiration date or the fixed date range is established at activation time. Each time the user powers on the instance, the date or date range is checked. Expiration checks are also performed while the instance is running. If the expiration is reached, an expiration message appears and the instance is suspended.

With a managed ACE instance, the expiration policy works similarly as for standalone instances, but the expiration policy value can be specified for individual instances. A valid date range for an ACE-enabled virtual machine applies to each of its associated ACE instances until an instance is individually configured with its own date range. After that configuration, any changes to the ACE-enabled virtual machine's expiration policy do not affect the instance. All expiration values, both for ACE-enabled virtual machines and for all ACE instances, are dynamic. This means that after you change the value and publish the policy update to ACE Management Server, ACE instances get the new value the next time they check for policy updates.

Setting Copy Protection Policies

Copy protection policies ensure that an ACE instance runs only from the location where it was originally installed. If you copy-protect an ACE instance, its files can be moved or copied, but the instance cannot run from the new location.

For standalone ACE instances, you can specify whether copying and moving are allowed. For managed ACE instances, you can specify whether both copying and moving are allowed or whether only moving is allowed. In this case, only one copy of the ACE instance is allowed to run at a time.

If the user moves or copies a copy-protected ACE instance and tries to run it, an error message appears. It lists an alphanumeric string that the user can send to the system administrator or help desk assistant to get the copy protection changed.

For managed instances, you can also dynamically change the copy protection settings, switching the settings so that moved or copied instances will run or not run. This means that after you change the value and publish the policy update to ACE Management Server, ACE instances get the new value the next time they check for policy updates.

Every ACE instance has a copy protection identifier (CPID) that contains the path to the ACE instance on the host file system. For standard ACE instances, the CPID also contains the system's BIOS ID. For Pocket ACE instances, the CPID contains the file system ID. If copy protection is on, Workstation compares the current CPID with the stored CPID. If they do not match, the instance was moved or copied.

For standalone ACE instances, you can set the CPID by using `vmware-acetool` or by sending hot fixes (on Windows systems, if hot fixes are enabled). See [“Using the vmware-acetool Command-Line Tool”](#) on page 479 and [“Respond to Hot Fix Requests”](#) on page 481.

For managed ACE instances, the CPID is stored on the server and the administrator can update it. See the *ACE Management Server Administrator's Guide*.

Setting Resource Signing Policies

You can set the resource signing policy so that an ACE instance cannot be run if resource files, such as policy scripts or custom EULA text files, are tampered with.

A resource is considered any file in the ACE **Resources** subdirectory in the virtual machine directory on the Workstation host. Files that are put in this directory on the end user's machine are not resources in this sense and are not signature checked.

Signature checking is performed on the end user's machine at power on and then every time a script is run. You can specify whether to verify all files in the ACE **Resources** directory or just the policy scripts in that directory.

If you are creating a package that has substantial resources, such as large files or large numbers of files, signature checking might take a long time. In this case, consider verifying scripts only or not using resource signing.

NOTE If you set the encryption package setting options to **None**, any verification specified in the resource signing policy is not performed. The encryption package setting overrides the resource signing policy. See [“Encryption Settings”](#) on page 436.

Setting Network Access Policies

The network access feature uses a packet-filtering firewall to enable you to specify which machines or subnets an ACE instance or its host system may access. This means that you can, for example, configure the instance so that it is allowed to connect only to your VPN server, which then controls access to other resources.

You can also customize the network access settings to filter on the basis of network addresses, traffic direction, protocol, and ports. You can set the following types of network access restriction definitions:

- Network zones
- Network access for an ACE instance's host machine (also known as "host network access")
- Network access for an ACE instance's guest operating system (also known as "guest network access")

Network access policies can be dynamic if the ACE instance is associated with an ACE Management Server. This means that after you publish a policy update to ACE Management Server, ACE instances get the new policy the next time they check for policy updates. You can quickly lock ACE instances out of all or part of your network to help combat the spread of a worm or virus without deploying update packages. See the *VMware ACE Management Server Administrator's Guide*.

Before You Begin Setting Host Policies

Use the following guidelines as you plan network access policies:

- A host machine for ACE instances can have only one host policy file. If you try to install an ACE package with a host policy file on a machine that already has a different host policy file, installation of the new package fails.
- A host policy is in effect even when no ACE instances are running. The policy starts immediately after installation and starts working every time the host system boots.
- Any restrictions on the host's network access also restrict network access for an ACE instance that uses NAT networking, because the NAT connection is affected by all the policies you apply to the host. If you set up restricted host access by using the ACE ruleset editor and rules editor rather than the Network Access wizard, configure the ACE-enabled virtual machine's virtual NICs to use bridged networking.
- If you are setting up a managed ACE-enabled virtual machine, you must allow the host to access ACE Management Server, communicating through TCP over the appropriate port that you configure.

- Host policies do not apply to Pocket ACE instances. If you specify a restricted host policy for an ACE-enabled virtual machine and then create a Pocket ACE package with that ACE-enabled virtual machine, the package is created but the host policy is not included in the package.
- You cannot view changes to host policies in the preview mode. If you want to test the effects of such changes, you must perform a test deployment. See [Chapter 20, “Deploying ACE Packages,”](#) on page 435.

Use the Network Access Wizard to Configure Network Access

VMware recommends that you use the Network Access wizard to configure basic settings and then use the zone editor and ruleset editor to fine-tune the settings if necessary. The Network Access wizard is initiated when you click **Quick Setup**.

The Network Access wizard creates or changes rules for the following zones:

- If you choose the **Desktop Configuration** option, the wizard creates a new guest access ruleset for the Everywhere zone. This ruleset restricts ACE instance access to your VPN or other specified network hosts.
- If you choose the **Laptop Configuration** option, the wizard creates a new internal zone that restricts the network address and, optionally, the domain on which the ACE instance can run. It can also create a new host access ruleset for this zone to restrict access to the internal network. For example, you can specify a proxy server. Finally, you can configure the same remote access for the **Desktop Configuration** option.

If you use this option and you do not modify any of the default settings that the wizard provides, the host is still allowed to communicate with DNS and DHCP servers so that the zone-detection mechanism can function properly.

To use the Network Access wizard to configure network access

- 1 In the policy editor, select **Network Access**.
- 2 Select **Restrict network access of the ACE instance and/or its host** and click **Quick Setup**.

3 Complete the wizard.

Depending on which configuration type you choose, a new zone might be added to the Network Access settings panel, and new rulesets might appear in the **Host Network Access** and **Guest Network Access** columns in the table.

4 (Optional) To view or edit the zones or rulesets you created with the wizard, click the zone or ruleset name in the table on the Network Access settings panel.

When you use the Network Access wizard to create an internal zone, choosing the **Laptop Configuration** option enables you to specify the network address, domain, and subdomains. If you want to also configure DNS, DHCP, WINS, or gateway servers, use the zone editor. See [“Guidelines for Specifying Zone Conditions”](#) on page 404.

Guidelines for Specifying Zone Conditions

Zone conditions describe the characteristics of a network zone. Workstation examines the networks that are directly connected to network adapters on the host computer to see if a match exists for all the criteria for any adapter in any of the zone definitions.

The zone editor appears when you click a name in the Zones column of the Network Access policy page. It shows the following details about the zone:

- You can specify a zone by using up to six conditions:

- Domain
- Subnet
- DNS servers
- DHCP servers
- Gateway servers
- WINS servers

For a match to occur, all specified conditions must be met.

- All zone conditions except the domain condition allow users to specify a list of addresses. The match is made if the host's address matches any of the address-list entries in a specified condition.

When the host connects to a network, a check is performed to determine whether the network matches the conditions for a zone. The checking starts with the topmost zone in the table and continues down the table until a match is made or the Everywhere Else zone is reached. When a match is made, the zone checking stops and filter rules for that zone are applied.

There are trade-offs between using shorter and longer lists of conditions. If you use a longer list, you minimize the chances of a false-positive result or a misidentification. Minimizing the chance of a false-positive result or a misidentification can be important if you are providing an ACE package to someone who connects a host computer to multiple networks at different times. If one of the other networks matches the characteristics you define in the zone definition, the host and instance access policies are applied, even if the host is not connected to your network.

In some cases, however, using a longer list might also increase the likelihood that a user could circumvent the detection mechanism. For example, such an error might be made if you switch the host to use a static IP address instead of DHCP and configure the host with only a subset of the characteristics defined for your zone, such as only network address, or network address and DNS server information.

Also consider that the addresses or names of certain servers can change over time. Such changes can also introduce detection issues.

Using a smaller set of information in a zone description, such as only the network address and the subnet mask, is safer. The disadvantage is that it increases the chance that a false positive or misidentification can occur. Such false positives are especially likely if your network is using a common netblock, such as 10/8, 172.16/12, or 192.168/16, that is also used by other networks.

Descriptions of the Zone Condition Settings

Each zone description must contain one or more of the following setting options describing the conditions of the zone:

- **Domain** – Specifies the domain name of the network, such as `mycompany.com`. Enter only one domain name. The value of **Allow subdomains of this domain** governs the interpretation of this option.
- **Allow subdomains of this domain** – Modifies the **Domain** option. It specifies whether, for the **Domain** zone condition to be met, a domain name must exactly match the domain name specified in the **Domain** box or whether a match of the domain name is made any time the string contains `<domain_name>`. For example, if this option is selected, `corp.mycompany.com` is considered a match for `mycompany.com`. If this option is not selected, `corp.mycompany.com` is not considered a match for `mycompany.com`.
- **Network address** – Specifies an IP address or subnet range that the network uses. The value of `<subnet>`, if you include a subnet range, must be the number of bits in the netmask. A network adapter matches this condition if it is using an IP address that lies within any of the specified ranges.

- **DNS servers** – Specifies one or more IP addresses or host names for DNS servers on the network. A network adapter matches this condition if it is using at least one of these servers.

If the value of the **Match at least** option is greater than 1, the host must be using the specified number of DNS servers on the list before a network adapter is considered to be on the defined network.

Because multiple methods exist for assigning DNS domain names to a Linux host, using just the DNS domain name to define a zone can be error prone. To define a zone for a Linux host, use criteria in addition to the DNS domain names.

For Web sites, a DNS domain name might resolve to more than one address. To ensure that the zone is defined exactly as you intend, enter each IP address, rather than just the DNS domain name.

- **DHCP servers** – Specifies one or more IP addresses or host names for DHCP servers on the network. A network adapter matches this condition if it is using at least one of these servers.
- **Gateway servers** – Specifies one or more IP addresses or host names for default gateways on the network. A network adapter matches this condition if it is using at least one of these gateways.
- **WINS servers** – Specifies one or more IP addresses or host names for WINS servers on the network. A network adapter matches this condition if it is using at least one of these servers. Linux hosts ignore WINS server settings during zone detection.

If the value of the **Match at least** option is greater than 1, the host must be using the specified number of WINS servers on the list before a network adapter is considered to be on the defined network.

Add or Edit a Network Zone

Use the zone editor to configure the network address, domain, DNS, DHCP, WINS, or gateway servers that an ACE instance can use for network connections.

Before you open the zone editor, determine what criteria to use for connecting to internal and external networks. See [“Guidelines for Specifying Zone Conditions”](#) on page 404 and [“Descriptions of the Zone Condition Settings”](#) on page 405.

To add or edit a network zone

- 1 In the policy editor, select **Network Access** and do one of the following:
 - To add a zone, click **Add Zone** and click the **New Zone** entry that appears in the table.
 - To edit a zone, click the name of the zone in the Zones column of the table.
- 2 Complete the fields in the zone editor that appears and click **OK**.

Using the Ruleset Editor to Configure Host and Guest Access

Each access setting for an ACE instance's host machine and for the ACE instance's guest system is based on a set of access rules. Whenever you use the Network Access wizard, a default ruleset is used for host and guest network access. You can use the ruleset editor to change the parameters of those rules.

Network access policies are applied by filtering on the IP address, the protocol number from the IP header, the direction of traffic, and TCP and UDP port values. The filtering does not involve deep packet inspection. For DNS and DHCP access, the TCP and UDP ports on which those services traditionally reside are opened.

Consider the following aspects of the filtering actions:

- If you move your services to different ports, the network access rules for those services no longer work.
- The host or instance is open to all traffic on these protocols and ports.

To understand the particulars of how traffic is being blocked or allowed for DNS, DHCP, and ICMP protocols and ports, see the rules displayed in the ruleset editor.

Add or Edit Rulesets and Rules for Network Access

The rules in the ruleset editor are listed in the order in which they are to be evaluated. When a network traffic packet arrives or is to be sent from the host or guest, it is compared with each rule in the ruleset, in order from the top down. If the following packet settings match the rule conditions, the packet is allowed or blocked according to the rule's action:

- Source address for incoming packets
- Destination address for outgoing packets, protocol, and ports

The packet is compared to each rule in order until it matches a rule or it was compared with all of the rules. When a match is made, the packet-to-rule comparison ends. The packet is not compared to subsequent rules in the ordered list. If it was compared to all rules without a match, the default rule action is applied.

To add and edit rulesets and rules for network access

- 1 In the policy editor, select **Network Access**, and click the link in the table column that applies to the access setting to edit.

The Zone and Access Type information just below the **Ruleset Name** text box shows the name of the zone and whether the access setting applies to host network access or to the network access for ACE instances (guest access).

- 2 Use the ruleset editor to change the order of rules in the set, edit rules, and specify whether the host or guest is allowed to use DNS, DHCP, or ICMP.

By default, **DNS**, **DHCP**, and **ICMP** are included in the network access setup for both host and instance access. VMware recommends that you keep **DHCP** and **DNS** selected because they are important for zone detection.

Whether the following settings apply to the host or to the ACE instance (guest access) depends on whether you are editing a host network access ruleset or a guest network access ruleset:

- **DNS** – Allows the guest or host to use a DNS server to resolve IP addresses. Select this option if the DNS server is not included in any other network access setting for this host or ACE instance.
- **DHCP** – Allows the host or guest to obtain its IP address from a DHCP server. Select this option if the DHCP server is not included in any other network access setting for the host or ACE instance.
- **ICMP** – Enables you to use the `ping` command. For guests, `ping` enables you to check network connectivity to and from the ACE instance. For hosts, it enables you to check network connectivity with other hosts in the network and with the ACE instance.

- 3 (Optional) To add or edit a rule, do one of the following:
 - To change a specific rule's settings, click the row for that rule in the table in the ruleset editor and click **Edit**.
 - To add a rule, click **Add**.

- 4 (Optional) Use the Rule Editor dialog box to specify the type of traffic, whether to block or allow traffic from specified network locations, the protocol, and ports or port ranges.

- **Addresses** – To edit an existing host name or address, double-click that item and edit it. The wildcard setting for all IP addresses is 0.0.0.0/0.
- **Protocol** – To allow or block communication for a specific protocol, select **Custom** from the **Protocol** list. The protocol number is in the packet. If that number matches the number supplied in the **Custom** field, the packet is allowed or blocked as the rule specifies. The protocol number is used in the protocol field of IPv4 packets.

For a list of protocol numbers, see the Internet Assigned Numbers Authority (IANA) organization's Web site. Most protocol numbers are permanently assigned.

- **Remote Ports and Local Ports** – If you are using either TCP or UDP and want to qualify the rule with specific port numbers for this type of traffic, type the port numbers or port-number ranges.

The wildcard port setting is "" (double quotation marks).

Usually you specify filtering on either local or remote ports, not both, because both specifications have to match for the rule to be applied. (DHCP represents an exception to this general rule.)

The local port is the source port for outgoing packets and the destination port for incoming packets. Typically you specify a local port when the host or guest is being used as a server obtaining remote connections on some port.

The remote port is the source port for incoming packets and the destination port for outgoing packets. Typically you specify a remote port when the host or guest is a client and is contacting a remote server on some port.

Change NAT Settings

You can use the NAT feature of the network access policy to specify the IP address range for the virtual network VMnet8 on the ACE instance's host system. You deploy this network properties setting with the ACE package.



CAUTION If you set this property, the setting affects all of the ACE instances and virtual machines on this instance's host system.

To change NAT settings

- 1 In the policy editor, select **Network Access**.
- 2 Click **Host Virtual Network** on the policy page.
- 3 In the NAT section of the dialog box, select **Assign IP addresses from this subnet**.
- 4 Type the subnet IP address to use, enter zero (0) as the last byte in the address, and click **OK**.
- 5 Create an ACE package and deploy the package.

The NAT setting is not a dynamic policy setting. This means that simply publishing a policy update to ACE Management Server does not cause ACE instances to change NAT settings. You can change the setting for a deployed ACE instance only by changing it in the policy and then creating and deploying a new ACE package.

Configure Which Physical Network Adapter to Use

If the host is likely to have multiple network adapters, you can specify which one to use for a bridged network connection. For example, you can specify that only the wireless adapter or only a VPN is to be used.



CAUTION If you set this property, the setting affects all of the ACE instances and virtual machines on this instance's host system.

To configure which physical network adapter to use

- 1 In the policy editor, select **Network Access**.
- 2 Click **Host Virtual Network** on the policy page.
- 3 Select one of the radio buttons in the **Automatic Bridging** section.
- 4 If you select **Device name**, also enter part or all of the device name.

For example, if device name of the local area connection is Broadcom NetXtreme 57xx Gigabit Controller #2, you might enter **Broadcom** or **broadcom netxtreme**. On Windows hosts, to determine the device name, go to the **Network Connections** item in the Control Panel.

- 5 Click **OK**.
- 6 Create an ACE package and deploy the package.

This automatic bridging setting is a host policy, which means that you can change the setting for a deployed ACE instance only by changing it in the policy and then creating and deploying a new ACE package

Understanding the Interaction of Host and Guest Access Filters with Tunneling Protocols

Host and guest access filters can differ in their interactions with tunneling protocols.

A host network access filter sees traffic before packets are encapsulated in the tunneling protocol (for example, VPN). A guest network access filter sees traffic after the packets are encapsulated in the tunneling protocol.

Because of this guest access filter behavior, a user might be able to circumvent guest access restrictions by using tunneling protocols or proxies.

Updating a Network Access Policy

You must create and deploy a new package for the host policy to take effect.

If you use a managed ACE-enabled virtual machine to create packages that do not contain a host policy and later edit the ACE-enabled virtual machine's network access policy to include a host policy and publish the change, instances created from packages of that ACE-enabled virtual machine do not have a host policy applied. A warning appears on the network access policy page if you attempt to apply a host policy in this way.

You can package just the host policy in a custom package, keeping the package size small.

Setting Removable Devices Policies

Removable devices policies allow you to control whether users can connect and disconnect removable devices from their ACE instances.

A removable devices policy is applied to an ACE-enabled virtual machine and affects all users of all instances created from that ACE-enabled virtual machine.

When you select **Removable Devices** in the policy editor, all removable device types for this ACE-enabled virtual machine are displayed in a list. You can specify which devices to allow end users to access.

Setting USB Device Policies

You can set USB device policies to restrict the ACE user's access to USB devices. The policies are dynamic. This means that you can change the settings on deployed ACE instances by publishing a policy update to ACE Management Server.

Access Levels for USB Devices

You can set restrictions at various levels of specificity, and you can mix levels of restriction in a policy setting. The levels of restriction are:

- **Specific USB device** – For example, allow use of a specific type of digital camera but disallow use of iPod mobile digital devices.

If a rule exists for a specific device, that rule overrides any rules set for device classes in which the device belongs.

All entries in the list of specific USB devices are maintained in a device database that is included with the files for this ACE-enabled virtual machine. You can copy and share the database. It is not write-protected. The default location for the file is:

On Windows XP: C:\Documents and Settings\All Users\Application Data\VMware\VMware Workstation\usbhistory.ini

On Windows Vista and Windows 7: C:\ProgramData\VMware\VMware Workstation\usbhistory.ini

- **Device class** – For example, allow use of human input devices (HIDs), such as mice and keyboards, but disallow use of communications devices, such as modems and cell phones.

If no specific device rule exists for a device and more than one device class rule applies to that device, the most restrictive rule is applied. For example, a device might include both a fax function and a print function and therefore can belong to more than one class. If one rule blocks a fax device but another rule allows a print device, the combination fax and print device is blocked.

- **All USB devices** – Allow or deny access to all connected USB devices. Device class rules and specific device rules override general access rules.

Set an Access Policy for USB Devices

You might want to set a policy that prevents end users from connecting such USB devices as mass storage devices, printers, or modems to the ACE instance.

Before you use the policy editor, determine a strategy for setting the policy. If you want a restricted environment, you can plan to generally block access to all USB devices and then specify exactly which classes or specific devices to allow. See [“Access Levels for USB Devices”](#) on page 412.

To set an access policy for USB devices

- 1 In the policy editor, select **USB Devices**.
- 2 Use the **General access to all USB devices** radio buttons to specify whether to allow or block general access to USB devices.
- 3 To specify a USB policy by device class:
 - a If the device does not appear in the **Access to specific types of USB devices** list, click **Add**, select the device in the USB Device Classes dialog box, and click **OK**.

You can Ctrl-click and Shift-click items to select more than one class.

- b Select the **Allow** and **Block** check boxes in the **Access to specific types of USB devices** list to specify the rule for each device in the list.
- 4 To specify a USB policy by specific device:
 - a If the device does not appear in the **Access to individual USB device models** list, click **Add**, select the device in the USB Device List dialog box, and click **OK**.

If the device does not appear in the USB Device List dialog box, do one of the following:

- Connect the device to the host and click **Refresh**.
 - Determine the device’s vendor ID (VID) and product ID (PID) and click **Manual Add** to enter the information. This information is available from the Windows Device Manager when you connect the USB device to a Windows computer.
- b Select the **Allow** and **Block** check boxes in the **Access to individual USB device models** list to specify the rule for each device in the list.
 - c (Optional) To change the information for a device, click **Remove** and add the device again with the new information.
 - 5 Click **OK** in the policy editor.

Setting Virtual Printer Policies

VMware ACE includes a virtual printer that allows users to print to any printer available to the host computer without installing additional drivers in the virtual machine.

The virtual printer feature is available for ACE instances running with these Windows host and guest operating systems:

- Host – Windows XP, 2003, or Vista, 7 32-bit only
- Guest – Windows 2000, XP, 2003, Vista, 7 (32- and 64-bit), Red Hat Enterprise Linux 4 (32 bit only), Ubuntu, and SUSE

After you enable the virtual printer policy, a serial port is added to the virtual machine. This serial port appears on the **Hardware** tab of the virtual machine settings editor, with the summary **Used by Virtual Printer**. You cannot add or remove this serial port by using the virtual machine settings editor. To add or remove it, you must enable or disable the option in the virtual printer policy.

NOTE If the ACE-enabled virtual machine already has four serial ports, you cannot add another serial port for the virtual printer. To enable the virtual printer, delete an existing serial port.

After end users install the ACE instance, they can use the **VM > Virtual Printers** menu command to specify which printers from the host are available to the guest. If end users on Windows hosts have problems, make sure the TP AutoConnect Service Windows service is started.

NOTE When the ACE Virtual Printer policy is enabled, **Virtual Printer** is available in **VM > Settings > Hardware**, and cannot be deselected until the ACE Virtual Printer policy is disabled.

Setting Runtime Preferences Policies

You can set options on the Runtime Preferences policy page to specify which Workstation runtime attributes the user can choose.

Runtime Preferences Settings

Use the following information to decide which features to enable:

- **Always run in full screen** – VMware Player fills the full screen when it starts, hiding the host operating system. You might find this useful, for example, to avoid confusion about the differences between the host system environment and that of the ACE instance.

Users can return to the host operating system by clicking the minimize button on the toolbar. If the mouse pointer is not available, pressing Ctrl+Alt minimizes the display.

- **Always hide the full screen toolbar** – End users cannot display the toolbar that usually appears at the top of the screen when in full screen mode.
- **Always run in appliance view** – The ACE instance opens in appliance view and the user cannot change to console view.

To use this setting, you must also enable appliance view for the virtual machine. See [“Configure the Appliance View for a Virtual Machine”](#) on page 182. If you attempt to use this policy without enabling appliance view, an error message appears when the user attempts to start the ACE instance.

- **Allow users to modify the memory allocation** – The **Change Memory Allocation** command appears in the **VM** menu of VMware Player.
- **Reduce virtual machine memory size if needed when powering on** – The virtual machine powers on even if the amount of available memory is less than the amount configured for the virtual machine. If you do not use this feature and the required amount of memory is not available, users need to modify the memory allocation to power on the virtual machine.

Enhanced Virtual Keyboard Settings

Use the following information to decide which features to enable:

- **Require enhanced virtual keyboard for secure input** – This setting applies only to Windows hosts running Windows guests. This feature provides better handling of international keyboards and keyboards with extra keys. It also provides security improvements because it processes raw keyboard input as soon as possible, bypassing Windows keystroke processing and any malware that is not already at a lower layer.

If an ACE instance uses this feature, when end users press Ctrl+Alt+Delete, the guest system only, rather than both guest and host, responds to the command.

Before you create a runtime policy for this feature, turn on the enhanced keyboard filter with the virtual machine settings editor. See [“Use the Enhanced Virtual Keyboard for Windows Hosts”](#) on page 339.

When the ACE instance is installed and the guest operating system starts for the first time, a special keyboard filter driver is installed on the host. After installation, the end user must restart the host computer. Keyboard filtering is then enabled.

- **When a suspected keylogger is detected** – Keystroke logging is a method of recording user keystrokes, including determining user passwords. VMware ACE now includes a feature that can detect (but not disable) keyloggers.

If you select **Ask user**, end users can exit or continue using the virtual machine and only log that the keylogger was detected. If you allow end users to continue using the virtual machine when a keylogger is detected, the keylogger still records the users' keystrokes. To avoid this possibility, select **Exit**.

Exit Behavior Settings

Use the following information to decide which features to enable:

- **When closing a non-Pocket ACE instance** – If you select **User Preference**, the user has access to **Suspend** and **Power off** in the Preferences dialog box in VMware Player (**File > Preferences**). If you select one of the other choices, the end user's virtual machine is suspended or powered off when the user chooses **File > Exit** or clicks the close box in VMware Player.

- **When closing a Pocket ACE instance** – If you select **User Preference**, the user has access to **Go mobile** and **Ask to go mobile or stay connected to the computer** in the Preferences dialog box in VMware Player (**File > Preferences**).
- **Always Go** – The virtual machine is powered off and synchronized to the host. After synchronization, the user can unplug the USB device and use it in another machine.
- **Always Stay** – The user wants to exit VMware Player but does not want to unplug the device. The virtual machine is suspended and no synchronization occurs.
- **Always Discard** – The user wants to exit VMware Player but does not want to synchronize. All changes are lost.
- **Allow users to manually power off or reset the virtual machine** – The **Reset** and **Power off and Exit** commands will appear in the **VM > Power** menu. If you do not select this option, the user must exit VMware Player to power off or suspend the ACE instance.

Pocket ACE Cache Settings

For performance reasons, when you use Pocket ACE, files from the USB device are cached as needed on the host. When you are finished using the Pocket ACE, you synchronize changes so that the updated files are written to the USB device.

You can disable this caching if you do not have enough disk space on the host. For example, if the virtual disk on the Pocket ACE has 8GB, you might potentially need 8 GB of disk space on the host for caching. You can also disable caching for security reasons if you do not want to create a cache on the host.

If you disable caching, the exit behavior in the **When closing a Pocket ACE instance** list changes to **Always Go** but synchronization does not occur because it is not necessary.

Setting Snapshot Policies

You can set policy options for two types of snapshots:

- **Reimage snapshots** – At installation time, a snapshot is taken after all of the required instance setup steps are complete, including, if applicable, encryption, instance customization, and domain join. The snapshot is taken before the virtual machine runs for the first time.

NOTE Manually disable the automatic reimage snapshot by editing the ACE-enabled virtual machine's `aceMaster.dat` file. Edit the `packaging.takeReimageSnapshot` option.

Reimage snapshots allow the ACE administrator, or the user if the administrator enables reimage snapshot options for the user, to revert the ACE instance to its known good starting state or to the known good updated reimage state.

If you enable reimage snapshot options, commands for the options appear in the **VM > Snapshot** menu.

If you choose not to enable the reimage snapshot options for the user, you can replace the reimage snapshot or revert to it on the user's machine by providing administrator mode access through the Administrator Mode policy. See [“Setting Administrator Mode Policies”](#) on page 419.

- **User snapshots** – You can enable users to take a snapshot of the ACE instance either when the instance is running or immediately after powering it off. You can also enable them to delete that user snapshot.

User snapshots enable the user to return the virtual machine to a known stable state. User snapshots can be taken, reverted to, and deleted without affecting the reimage snapshot. Only one user snapshot can be saved at a time.

If you enable user snapshot options, commands for the options appear in the **VM > Snapshot** menu.

NOTE You cannot take snapshots of a Pocket ACE instance. For more about Pocket ACEs, see [Chapter 21, “Pocket ACE,”](#) on page 457.

Setting Administrator Mode Policies

You can use the administrator mode policy to set an administrative password so that you can do any of the following:

- Run the ACE instance on the user's machine and enter administrator mode to access the virtual machine settings and make changes to the instance's configuration. You can only edit the settings. You cannot add or remove virtual hardware devices.
- Run the ACE instance on the user's machine and enter administrative mode to access all the snapshot commands. See ["Setting Snapshot Policies"](#) on page 418.
- Use the `vmware-acetool` command-line program on an ACE user's system to fix a limited set of problems for standalone ACE instances.

Use Administrator Mode on an ACE Instance

Using administrator mode on an end user's virtual machine enables you to troubleshoot and access features and commands that might not be available to the end user.

To use administrator mode on an ACE instance

- 1 Start VMware Player on the end user's machine and choose **VM > ACE > Enter Administrator Mode**.
- 2 Enter the password for administrator access.
- 3 Choose the appropriate commands as follows:
 - To edit virtual machine settings from the user's machine, choose **VM > Settings**. This command is available only on Windows hosts.
 - To use the user snapshot commands, choose **VM > Snapshot**.
 - To use the reimage snapshot commands, choose **VM > Snapshot > Revert to Reimage Snapshot**.
 - To use the ACE Tools, see ["Using the vmware-acetool Command-Line Tool"](#) on page 479.
- 4 When you finish changing the virtual machine settings or using the snapshot commands, choose **VM > ACE > Exit Administrator Mode**.

Setting Kiosk Mode Policies

When an ACE instance runs in kiosk mode, the user cannot access the host system at all. For example, the user cannot shut down the host machine. The virtual machine runs in full screen mode and does not display the ACE menu bar or ACE Player online help.

If an ACE instance has the kiosk mode policy turned on, by default, a message appears at startup to provide the following information:

- Warns the user that the virtual machine is about to go into kiosk mode.
- Tells the user which key combination to use to exit kiosk mode. The default is the hot-key combination for ungrabbing input from a virtual machine (often Ctrl+Alt). See [“Change the Key Combination for Exiting Kiosk Mode”](#) on page 420.
- If the policy includes an administrator password, tells the user that host access is available only if the user enters the password after pressing the key combination to exit kiosk mode.

When a user exits kiosk mode, the virtual machine is powered off or suspended, according to the runtime preference policy for exit behavior. Pocket ACE instances are powered off and synchronized. When the virtual machine is powered off, the ACE Player prompts the user to exit kiosk mode.

On Linux hosts, you must set some additional properties after installing the ACE instance. See [“Prepare a Linux Host for Running in Kiosk Mode”](#) on page 472.

For information about startup options for kiosk mode, see [“Change Default Kiosk Mode Startup Behavior”](#) on page 475 and [“Use Multiple Virtual Machines in Kiosk Mode”](#) on page 476.

Change the Key Combination for Exiting Kiosk Mode

You can use Ctrl, Alt, Shift, the Windows key, or a combination of these keys with a regular key.

To change the key combination for exiting kiosk mode

- 1 In the policy editor, select **Kiosk Mode**.
- 2 Select **Always run in kiosk mode** and select **Custom hot key to exit kiosk mode**.
- 3 Click in the **Type hot key here** field and press a key combination.

For example, press Alt+X rather than typing the characters **Alt+X**.

Setting Hot-Fix Policies for Standalone ACE Instances

This policy enables users of standalone ACE instances to request hot fixes if they lose or forget the ACE password, try to run an expired ACE instance, or move a copy-protected ACE instance to a new location.

To address these types of problems for managed rather than standalone ACE instances, use the VMware Help Desk Web application or the instance view in Workstation. For more information, see the *ACE Management Server Administrator's Guide*.

The hot-fix request is a file that the user must submit to an administrator for action. You configure whether the user submits the file to an administrator manually or through email generated by the Hot Fix Request wizard.

For automatically generated email, the Hot Fix Request wizard on the user's computer attempts to use a MAPI email client on the host operating system. The hot-fix request file is included as an attachment to the email message. The message uses the email address and subject line that you specify.

If you choose email and the automatic submission fails, the Hot Fix Request wizard allows the user to save the hot-fix request as a file. The user must then send the file to an administrator manually.

The administrator uses Workstation to respond to hot-fix requests. See [“Respond to Hot Fix Requests”](#) on page 481.

Setting the Policy Update Frequency for Managed ACE Instances

This policy controls how often an ACE instance connects to ACE Management Server to download policy updates while it is running. It also controls how long a managed ACE instance can be used if it cannot connect to ACE Management Server.

This policy applies only to managed ACE instances. To deploy policy updates for standalone ACE instances, you must create policy update packages. Policy changes are applied when the instance is started after the update package is installed.

The settings for offline usage include text for warning and timeout messages. You can customize messages by adding text to them. You cannot edit the existing standard text except by using the controls on the panel to change the number of minutes, hours, or days shown.

Policy updates take effect while the instance is running, with the following exceptions:

- Updates to access control policies, which include user and group lists, passwords, and scripts, take effect the next time the instance is powered on.
- Updates to policy update frequency policies, if set to **Only when the ACE instance powers on**, take effect the next time the instance is powered on.

Control Which ACE Instances Run on a Host

You can set restrictions such as the following:

- Specify whether virtual machines that are not ACE instances can run on the machine. This is a host-wide policy, which requires an administrator to install the package.
- Specify that only ACE instances with a specific creator ID can run on the machine.

You can control which virtual machines and ACE instances can be run on a host by editing the `aceMaster.dat` file in the virtual machine directory.

Before you begin, if you plan to run multiple ACE instances on the end user's machine, determine which ACE-enabled virtual machine you want to use for setting host-wide policies.

To control which ACE instances run on a host

- 1 On the administrator machine where Workstation is installed, power off and close the ACE-enabled virtual machine.
- 2 Use a text editor to open the `aceMaster.dat` file for the ACE-enabled virtual machine.

This file is located in the same directory as the configuration file (`.vmx` file) for the ACE-enabled virtual machine.

- 3 (Optional) To specify that non-ACE virtual machines cannot run on the host, find the `allowVMs` property and change it from 1 to 0.
- 4 Find the `requiredCreatorID` property and set it to an identifier.

For example, to set the required creator ID to `creator1`, edit the line as follows:

```
requiredCreatorID = "creator1"
```

You set `requiredCreatorID` once for each host. You do not need to set this property on other ACE instances that run on the same host.

This is a host-wide policy, which requires an administrator to install the package.

- 5 Find the `creatorID` property and set it to the same identifier.

For example, to set the creator ID to `creator1`, edit the line as follows:

```
creatorID = "creator1"
```

Only ACE instances with this creator ID can run on the same host.

The ID string is in plain text in the `aceMaster.dat` file on the administrator's machine, but it is hidden in the policy file.

If you publish the policy set of an ACE instance to `requiredCreator=yourPolicySetting` and install it on a host, only you (or others with access to the administrator files) know what the creator ID is. Without knowing the `requiredCreator` policy setting, you cannot create your own ACE instance that can run on the host.

- 6 Do one of the following:
 - If you are creating a new ACE instance, create a package for this ACE-enabled virtual machine and install it on the end user's host.
 - If you are creating an update for a standalone ACE instance, create an update package.
 - If you are creating an update for a managed ACE instance, open the virtual machine and publish the changes to ACE Management Server.

Changes to the `allowVMs` property or the `requiredCreatorID` property represent changes to host-wide policies. Packages that include these host policies require administrator privileges to install.

- 7 (Optional) If you plan to run multiple ACE instances on the end user's machine, do the following:
 - a Edit the `aceMaster.dat` file for the other ACE-enabled virtual machines and set the `creatorID` property to the same value that you used in [Step 5](#).

Set only the `creatorID` property and not the `requiredCreatorID` property for these other virtual machines.
 - b Repeat [Step 6](#).

Writing Plug-In Policy Scripts

You can write scripts to control certain policies in VMware Player. You may use any language that is supported on the user's computer.

For security reasons, scripts must be deployed as part of a package and installed by the package installer. Users cannot modify these scripts.

When scripts run, they must write the appropriate values to the StdOut file. Output to the StdOut file might be up to 4096 bytes long.

Place any scripts you want to use for a package in the ACE Resources directory in the virtual machine directory. Do not place them in a subdirectory of the ACE Resources directory. If the scripts need any additional resource files, place those files in the main ACE Resources directory. Make sure the script uses relative paths to reference those resources.

Scripts can also write messages to the StdErr file. Output to the StdErr file may be up to 4096 bytes long. Any messages generated on the StdErr file are captured in the log file on the end user's machine at the following location:

```
<UserAppData>\VMware\VMware ACE\<package_name>\Virtual  
Machines\<VM_name>\vmware.log
```

The exit code of a script indicates whether the script succeeded or failed.

Table 19-1 describes the environment variables set in the script execution environment.

Table 19-1. Environment Variables

Variable	Description
VMWARE_MASTER_ID	The ID of the ACE-enabled virtual machine (ACE master).
VMWARE_PACKAGE_ID	The ID of the package the virtual machine was instantiated from.
VMWARE_INSTANCE_ID	A Boolean value that is set to TRUE the first time the virtual machine is powered on. Otherwise, it is set to FALSE.

All scripts run each time the end user starts VMware Player or resets the virtual machine. Some might run more often. For example, an expiration script is run every 24 hours.

The sample scripts presented in “Examples of Policy Scripts” on page 425 are installed with VMware Player in the following location:

```
C:\Program Files\VMware\VMware Player\Samples
```

The topics that follow show the format for the output that your scripts must write to the StdOut file to control various policies.

Examples of Policy Scripts

Examples include an authentication script, a host to guest data script, and a power-on hook script.

Sample scripts are installed with VMware Player in the following location:

C:\Program Files\VMware\VMware Player\Samples

Example of an Authentication Script

This script example includes the basic elements required for any authentication script. The purpose of an authentication script is to do one of the following:

- If the user is to be granted access to the virtual machine, generate the data used to create the key for this user and send it as output. The data must be unique for each user. If access is granted, the exit code is 0.
- If the user is to be denied access to the virtual machine, the script exits with a non-zero exit code. This is a reference to the exit code, not the output value.

The output of the script is hashed to create a key to encrypt and decrypt virtual machine files. The first time this script is run, the output is hashed to encrypt the virtual machine. When a virtual machine is decrypted, the script must return the same value. If the script returns a different value, the virtual machine is not decrypted and the user sees an error message.

The script may return any value. To ensure best security, a value that includes only printable characters should be at least 32 bytes long. For binary data, the value should be at least 16 bytes long to ensure proper entropy. The output is sent to the StdOut file.

The following example is written in Perl. It is installed by Workstation as `sample_auth.pl`. Compile it with a Perl interpreter to run it.

```
#
#   VMware Sample Script
#
#   Sample script for ACE script authentication
#
#   Description:
#   This sample script looks up the user as defined in the environment
#   variable TEST_USERNAME and returns seed data that is used to make a key
#   for authentication purposes.
#
#   It assumes that the username is defined in the environment variable
#   TEST_USERNAME (a fictitious environment variable used for this sample)
#   and returns the seed data from a hardcoded map of username to seed data.
#
#   Input to script:
```

```

#   None.
#
#   Returns:
#   0 if successful (user is correctly authenticated).
#   -1 if TEST_USERNAME is not set, or the user is unrecognized.
#
#   Expected output:
#   Seed data for creating script authentication key on stdout.
#
#   Notes:
#   If the script returns success, its output will be used to create a key.
#   Therefore, it is important that the output of this script be unique for
#   each user, and that there is enough data to make a meaningful key (at
#   least 16 bytes).
#
#

my %user_map= ( 'charlie'      => 'E1C4F612135B4D98A33B2C9BD595025D',
                'kathy'       => 'C79AFFEF773D61225751C2566858DB08',
                'beth'        => '05B169B439B26AAB2EA4F755B7E3800C',
                'ernie'       => '8CE63D4AA2068BD8AFF2D1B05F3495A5',
                'bert'        => '"172B1619B2EFBE0E4F381AA1C428F049'
                );

my $username = $ENV{TEST_USERNAME};
if (! defined $username) {
    print "You should set the TEST_USERNAME environment variable.\n";
    exit(-1);
}

my $key_seed = $user_map{$username};
if (! defined $key_seed) {
    print "Unrecognized username.\n";
    exit(-1);
}

print $key_seed;
exit(0);

```

Example of a Host to Guest Data Script

The following example is written in Perl. It is installed by Workstation as `sample_hostdata.pl`. You need a Perl interpreter to run this script.

```

#
#   VMware Sample Script
#
#   Sample script for ACE Host-Guest Data script
#

```

```

# Description:
# This sample script passes information defined on the host to the guest.
# It assumes that the machine name is defined in the environment variable
# TEST_MACHINENAME and that the asset tag is defined in the environment
# variable TEST_ASSETTAG. (These are fictitious variables used for this # #
# sample).
#
# Input to script:
# None.
#
# Returns:
# 0 if successful.
#
# Expected output:
# Set of acceptable key/value pairs where the values are fetched from the
# environment variables. These values can be retrieved from within the
# Guest operating system using the VMware Tools.

my $machine_name = $ENV{TEST_MACHINENAME};
my $asset_tag = $ENV{TEST_ASSETTAG};
my $host_mac = $ENV{TEST_MACHINEMAC};

if (defined $machine_name) {
    print "machine.id = " . $machine_name . "\n";
}

if (defined $asset_tag) {
    print "guestinfo.assetTag = " . $asset_tag . "\n";
}

if (defined $host_mac) {
    printf "guestinfo.mac = " . $host_mac . "\n";
}

exit(0);

```

Example of a Power-On Hook Script

The following example is written in Perl. It is installed by Workstation as `sample_poweron.pl`. You need a Perl interpreter to run this script.

```

#
# VMware Sample Script
#
# Sample script for ACE power-on hook
#
# Description:
# This sample script implements a power-on hook for ACE. This can be used
# in addition to authentication to control the circumstances under which an
# ACE is allowed to run.

```

```

# This script assumes that the username is defined in the environment
# variable TEST_USERNAME (a fictitious environment variable used for this
# sample) and returns TRUE if the user is allowed to run, and FALSE
# otherwise.
# Input to script:
# None.
#
# Returns:
# TRUE if username is on white list.
# FALSE if username is not on white list or is undefined.
#
# Expected output:
# One of the strings "TRUE" or "FALSE"
#
#

my @white_list = ("alan", "bob", "mary", "sonia", "chris");

my $username = $ENV{TEST_USERNAME};
if (! defined $username) {
    print "FALSE";
    exit(0);
}

my @grepNames = grep(/$username/, @white_list);
if (@grepNames == 1) {
    print "TRUE";
    exit(0);
}

print "FALSE";
exit(0);

```

Customizing the VMware Player Interface on Windows Hosts Only

You can customize several aspects of the VMware Player user interface for ACE instances that run on Windows hosts. You save these customizations in a text file and identify that text file, called the skin file.

Create and Specify a Skin File

A skin file contains parameter settings for customizing the VMware Player user interface. Use this file to change application icons, the text that appears in the title bar, and to change the way removable devices are presented.

This feature is available only for VMware Player running on Windows hosts.

To create and specify a skin file

- 1 Use a text editor to create a skin file that includes the parameters to customize.

Use one line for each parameter and use the following form:

```
<parameter> = "<value>"
```

For a list of values to use in parameters, see [Table 19-2](#), [Table 19-3](#), and [Table 19-4](#).

To comment out a line in the skin file, begin the line with the pound (#) sign.

- 2 Save the skin file with the filename `skin.txt` in the `ACE Resources` directory in the virtual machine directory for the ACE-enabled virtual machine.

The filename must be `skin.txt`.

- 3 (Optional) To display application icons other than the VMware Player icon, place the new `.ico` icon files in the `ACE Resources` directory.

For icons sizes and skin file parameters, see [“Customizing the VMware Player Icons”](#) on page 429.

- 4 In Workstation, close the ACE-enabled virtual machine.
- 5 Use a text editor to open the `aceMaster.dat` file in the virtual machine directory and add the following line:

```
vmplayer.skin = "skin.txt"
```

Because the skin file is in the `ACE Resources` directory, you do not need to specify the directory path to the file.

- 6 Save and close the `aceMaster.dat` file.
- 7 (Optional) To determine whether the parameters are set correctly, preview the virtual machine in VMware Player.

See [“Use Preview Mode to Test Policy and Deployment Settings”](#) on page 448.

Customizing the VMware Player Icons

VMware Player has separate large and small application icons. The large icon is used in the application switching interface (visible when you press Alt+Tab). The size of the large icon is usually 32x32 pixels, but VMware Player uses whatever size is specified for icon size in the system preference. The small (16x16 pixels) icon is used in the VMware Player title bar and on the Windows taskbar button for VMware Player.

The icons used for these purposes must be in `.ico` file format and located in the `ACE Resources` subdirectory in the virtual machine directory. The applicable parameters in the skin file include the following:

```
player.iconSmall = "<filename>"
player.iconLarge = "<filename>"
```

One `.ico` file can contain multiple icons of different sizes. You can specify the same `.ico` file for `player.iconSmall` and `player.iconLarge`. VMware Player extracts the icon of the appropriate size for each use.

Customizing the Title Bar Text

You can specify what text appears in the VMware Player title bar. You can also specify the font and font size used to display the text.

The text displayed in the title bar consists of three sections: a prefix, the virtual machine name, and a suffix. The parameters listed in [Table 19-2](#) allow you to set any prefix and suffix, or to omit the prefix, the suffix, or both. They also allow you to include or omit the virtual machine name.

If you leave the defaults for all values, the title bar displays only the virtual machine name at 32 points in the MS Shell Dlg font.

[Table 19-2](#) describes the VMware Player title text parameters.

Table 19-2. VMware Player Title Text Parameters

Parameter	Type	Default	Controls
player.title.prefix	string	""	Title bar prefix
player.title.useVMName	Boolean	"TRUE"	Whether the virtual machine name is displayed
player.title.suffix	string	""	Title bar suffix
player.title.font.face	string	"MS Shell Dlg"	Font name (the font must be on the user's computer)
player.title.font.size	integer	32	Point size for the text

Customizing the Removable Device Display

Removable devices are represented in the VMware Player interface either by buttons on a toolbar or by menu items on a **Devices** menu. You can specify the type of display. You can also specify text, icon, or a combination of the two and specify custom icons.

If you use custom icons, copy the icon files to the `ACE Resources` directory in the virtual machine directory for the ACE-enabled virtual machine.

Settings you make in the skin file override any settings the user makes in the VMware Player preferences dialog box.

Use the following parameter to control whether devices are shown as toolbar items:

```
player.deviceBar.toplevel = [TRUE | FALSE]
```

Set the parameter to TRUE for a toolbar or FALSE for a menu.

Use the parameters shown in [Table 19-3](#) to customize the display for each removable device configured in the virtual machine.

Table 19-3. Removable Devices Parameters

Parameter	Type	Default	Controls
player.deviceBar.<deviceName>.buttonStyle	string (text, icon, texticon)	"text"	Appearance of toolbar button or menu item
player.deviceBar.<deviceName>.buttonText	string	User-friendly device name	Text that appears on the toolbar button or menu item when device is connected
player.deviceBar.<deviceName>.buttonTextDisconnected	string (optional)	Normal button text	Text that appears on the toolbar button or menu item when device is disconnected
player.deviceBar.<deviceName>.tooltip	string	""	Text that appears in the tooltip when device is connected
player.deviceBar.<deviceName>.tooltipDisconnected	string (optional)	Normal tooltip	Text that appears in the tooltip when device is disconnected
player.deviceBar.<deviceName>.icon	filename	Icon representing this type of device	Custom icon file when device is connected
player.deviceBar.<deviceName>.iconDisconnected	filename (optional)	Normal icon	Custom icon file when device is disconnected
player.deviceBar.<deviceName>.shortcutKey	keySpec		Shortcut key combination to switch the device between connected and disconnected (see “Shortcut Key Values” on page 432)

Following are the device names you can use for <deviceName> in the parameter name:

- floppy0, floppy1
- serial0, serial1, serial2, serial3
- parallel0, parallel1, parallel2
- ide0:0, ide0:1, ide1:0, ide1:1 (IDE CD-ROM or hard drives)
- scsi0:0 – scsi0:7 (SCSI CD-ROM or hard drives)

Shortcut Key Values

Use virtual key codes to specify keyboard shortcuts. Virtual key codes use hexadecimal format, which is a hexadecimal number preceded by 0x. For example, to use the virtual key code of 5A as a value, type **0x5A**.

Microsoft provides a reference list of virtual key codes on its MSDN Web site.

You can also use the Ctrl, Alt, and Shift modifier keys, or a combination of those keys. [Table 19-4](#) provides the shortcut key values.

Table 19-4. Shortcut Key Values

Modifier key	Value
No modifier	0x0
Alt	0x1
Ctrl	0x2
Shift	0x4
Ctrl+Alt	0x3
Alt+Shift	0x5
Ctrl+Shift	0x6
Ctrl+Alt+Shift	0x7

When you list a key plus a modifier, type the virtual key code for the key followed by a comma, followed by the value for the modifier key or keys. For example, the value entry for Ctrl+Shift+F1 is 0x70, 0x6.

Keep the following limitations in mind when defining shortcut keys:

- Do not use the Pause key with the Ctrl key.
- If you use F12, you must use one or more modifier keys. You cannot use F12 alone.
- You cannot use combinations that include only the Shift, Ctrl, and Alt keys. You can use these keys only as modifiers in combination with some other key.

Sample Skin File

```

player.title.prefix = "Our Company <<"
player.title.suffix = ">> Environment"
# player.title.useVMName = "FALSE"

# player.deviceBar.toplevel = TRUE
player.deviceBar.floppy0.buttonStyle = "icon"
player.deviceBar.floppy0.buttonText = "First Floppy Drive"
player.deviceBar.floppy0.shortcutKey = "0x30,0x7"
player.deviceBar.floppy0.icon = "custom-floppy.ico"
player.deviceBar.floppy0.tooltip = "Click to disconnect"
player.deviceBar.floppy0.tooltipDisconnected = "Click to connect"
# player.deviceBar.ethernet0.buttonStyle = "icon"
# player.deviceBar.idel1:0.buttonStyle = "icon"
# player.deviceBar.audio.buttonStyle = "icon"

```


Deploying ACE Packages

20

This chapter provides instructions for specifying deployment settings for ACE packages, creating ACE packages, and deploying packages to end users. This chapter includes the following topics:

- [“Edit Deployment Settings”](#) on page 435
- [“ACE Resources Directory”](#) on page 446
- [“Review the Configuration of an ACE-Enabled Virtual Machine”](#) on page 447
- [“Use Preview Mode to Test Policy and Deployment Settings”](#) on page 448
- [“Creating a Package”](#) on page 449
- [“Perform an End-to-End Deployment Test”](#) on page 455
- [“Deploy Packages”](#) on page 456

Edit Deployment Settings

Deployment settings enable you to configure package characteristics, such as instance customization and encryption, and then apply those settings to as many packages as you choose. Changes to deployment settings affect only packages created after the changes are made. They do not apply to existing packages.

Before you can use the deployment settings editor on a virtual machine, you must enable ACE features for that virtual machine. See [“Overview of Creating and Deploying ACE Packages”](#) on page 385.

To edit deployment settings

- 1 Select the ACE-enabled virtual machine and choose **VM > ACE > Deployment Settings**.
- 2 In the deployment settings editor, select an item in the **Setting** list.
- 3 Complete the settings panel for that deployment setting and click **OK** or select another setting to edit.

For assistance with the fields on a settings panel, click **Help**.

Encryption Settings

Encryption settings are of two types:

- **Package protection** – Protects package files from being copied or altered while in transit. If you set package protection to **Encrypted**, the New Package wizard encrypts the virtual machine when a package is created.
- **Instance protection** – Protects ACE instance files from being copied or altered after installation and activation. You must specify an authentication method if you want the installer to encrypt the ACE instance.

The activation and authentication policies you choose determine which default encryption settings are applied to the package and files. See [“Setting Access Control Policies”](#) on page 391. VMware recommends these default settings for production environments. The files do not need to be encrypted when you deploy a package in a test environment.

NOTE If you set the encryption settings to **None**, any verification specified in the resource signing policy is not performed. The encryption package setting overrides the resource signing policy setting. See [“Setting Resource Signing Policies”](#) on page 401.

Package Lifetime Settings

You can specify a time period during which an ACE package is installable. If a user attempts to install a package outside of this time period, an error message appears and the package is not installed.

The administrator can change the package lifetime settings on managed packages even after package creation.

Change Package Lifetime Settings for a Managed Package

If you use the ACE Management Server, you can change the package lifetime settings or deactivate a package immediately.

Before you begin, make sure Workstation is connected to the ACE Management Server. For information about installing and setting up the server, see the *ACE Management Server Administrator's Guide*.

To change package lifetime settings for a managed package

- 1 Select the ACE-enabled virtual machine and choose **View > Current View > Summary**.
- 2 Click the **Packages** section tab.
- 3 Right-click the package and do one of the following:
 - To change the package lifetime settings choose **Properties > Settings**.
 - To deactivate the package immediately choose **Deactivate**.

Instance Customization on Windows Guests Only

Instance customization applies only to ACE instances that have a Windows guest operating system installed. The instance customization process is built around the standard Microsoft Sysprep deployment tools. It provides the following benefits:

- Automates the Sysprep process (the use of the Microsoft Sysprep deployment tools). It gives you better control of some Sysprep parameters, such as computer name.
- Automates joining ACE instances to a domain from a remote site. See [“Set Up a Remote Domain Join”](#) on page 443.
- For managed ACE instances, the instance customization process on the user's machine reports the success or failure of the process to the server. The information is available in the instance view of Workstation. Besides status, the process also reports the MAC address and the new computer name.

Instance Customization Process During Packaging

If you specify instance customization deployment settings, the following events occur when you complete the New Package wizard:

- 1 A snapshot of the ACE-enabled virtual machine is taken and saved.
- 2 The ACE-enabled virtual machine is powered on, and all the required deployment tools and files, including the appropriate Microsoft Sysprep tools, are copied into the guest.

There is no visible indication showing the copying process. See [“Download the Microsoft Sysprep Deployment Tools”](#) on page 440.

- 3 The Microsoft deployment tools run inside the guest operating system to seal the guest and prepare for deployment.
- 4 The guest operating system shuts down.
- 5 The ACE-enabled virtual machine is cloned into the package directory.

The virtual machine files are copied into the directory, encrypted if set to do so, and divided to be put on media if set to do so.

- 6 The ACE-enabled virtual machine reverts to the snapshot.
- 7 The snapshot is deleted.
- 8 The installer files are copied into the package directory.

Instance Customization on the End User's Machine

On the ACE user's machine, after the installation and instance activation, the following events occur:

- 1 All information required for resolving placeholder variables is obtained.
- 2 Placeholder variables are resolved and replaced with the actual values for the ACE instance.

See [“Placeholder Values to Use in Instance Customization”](#) on page 442.

- 3 The Microsoft Mini-Setup process runs unattended.

If the Mini-Setup process fails, the ACE instance shuts down.

- 4 (Optional) Additional commands to execute other scripts that you specified in the instance customization deployment settings are executed.

- 5 (Optional) If you configured a remote domain join, the software executes the script you specified, connects the ACE instance to the VPN server, and joins the virtual machine to the domain.

See [“Set Up a Remote Domain Join”](#) on page 443.

- 6 For managed instances, instance customization is reported to the server if it is successful.

Prerequisites for Using Instance Customization

Instance customization is available for both managed and standalone ACE instances.

Before you specify instance customization settings, perform the following tasks:

- Install a Windows 2000, 32-bit or 64-bit XP Professional, Server 2003, Vista, or 7 guest operating system on an ACE-enabled virtual machine.
- Install the latest version of VMware Tools on the guest operating system. See [“Installing VMware Tools”](#) on page 104.
- Download the Microsoft Sysprep tools. See [“Download the Microsoft Sysprep Deployment Tools”](#) on page 440.
- Gather the following information:
 - The Windows product ID for the guest operating system installation.
 - If the ACE instance will be joined to a domain (whether the instance is local or remote to the domain), the user name and password for an account that has permission to add computers to the domain.
 - Remote domain join parameters if a remote ACE instance will be joined to a domain. See [“Set Up a Remote Domain Join”](#) on page 443.

Download the Microsoft Sysprep Deployment Tools

You do not need to download Microsoft Sysprep deployment tools if you have a Windows Vista and Windows 7 operating system. They are included with the Windows Vista and Windows 7 installation.

To download the Microsoft Sysprep deployment tools

- 1 Go to the Microsoft Web site and search for Sysprep deployment tools.
- 2 Follow the instructions on the site for downloading the Sysprep deployment tools.

Download all versions that correspond to the guest operating systems that you plan to deploy. These tools include Sysprep deployment tools for Windows 2000, Windows 2003, and Windows XP Professional SP1 and SP2. The SP1 version works with Windows XP Professional with no service pack and Windows XP Professional SP1.

- 3 Unzip the files into the corresponding version-specific directory in the `Resources\SysprepTools` directory.

For example, for Windows XP SP3, unzip the files to:

```
C:\Program Files\VMware\VMware Workstation\Resources\SysprepTools\xp3
```

Specify Deployment Settings for Instance Customization

Before you begin, install all required files for customization scripts. See [“Prerequisites for Using Instance Customization”](#) on page 439.

To specify deployment settings for instance customization

- 1 Select the ACE-enabled virtual machine and choose **VM > ACE > Deployment Settings**.
- 2 Select **Instance Customization** and complete the settings panel.

- 3 Select **System Options** and complete the settings panel.

Use the following information to complete the fields:

- **System options** – You can use placeholder variables for the system name, organization name, and computer name. For details on the placeholder variables, including an example, see [“Placeholder Values to Use in Instance Customization”](#) on page 442.



CAUTION The Mini-Setup process fails if you enter **administrator** in the **Name** field or the **Computer Name** field or for Windows Vista and Windows 7 guests, if the computer name is more than 15 characters.

If you set the %logon_user% placeholder in those fields and the placeholder variable resolves to **administrator**, the software automatically changes the value to a random alphanumeric string of 10 characters.

- **Security ID** – A new SID is always generated for Windows Vista and Windows 7 guests, regardless of the setting you choose here.
- 4 Select **Initialization Scripts** and type the additional commands to run scripts in the guest operating system at the end of the Mini-Setup process on the ACE user's machine.

For more information about commands, see the Microsoft deployment tools documentation.

Specify the path to the batch file without using quotation marks. Quotation marks are added automatically. For more information, see the Microsoft knowledge base article about troubleshooting `Cmdblins.text` during an unattended setup.

- 5 Select **Workgroup or Domain** and complete the settings panel using the following information:
 - Instance customization supports only IP addresses that DHCP servers provide. Static IP addresses are not supported.
 - To allow this ACE instance to join the domain from a location remote to the domain, see [“Set Up a Remote Domain Join”](#) on page 443.
- 6 Specify other types of deployment settings or click **OK**.

To create a package with these settings, see [“Creating a Package”](#) on page 449.

Placeholder Values to Use in Instance Customization

Use placeholder values to construct machine-specific names inside the guest operating system during the Mini-Setup process.

Following are the available placeholders:

- `%logon_user%` or `%logon_user(n)%` – The user logged in to the host machine at the time the Microsoft Mini-Setup process begins.

You can use `%logon_user(n)%`, where `<n>` is the maximum number of characters obtained from the actual logged-in user when the name is resolved. Use `<n>` if you the user name must be resolved to no more than a certain number of characters. For example, if you specify that 3 random characters are to be added to the actual user name and you want to limit the resolved name to 15 characters, set `<n>` to 12. Your entry in the **Name** field in the **System Options** panel is `%logon_user(12)%random_alpha_digit(3)%`.

Including `(n)` in the placeholder is optional. If you use only `%logon_user%` or if you set `<n>` to zero (0), the placeholder resolves to the full logged-in user name.

- `%host_name%` or `%host_name(n)%` – The name of the host computer (usually used with some additional random number or name).

You can use `%host_name(n)%`, where `<n>` is the maximum number of characters obtained from the actual computer host name when the name is resolved. Use `<n>` if the host name must be resolved to not more than a certain number of characters. For example, if you specify that 3 random characters are to be added to the actual host name and you want to limit the resolved name to 15 characters, set `<n>` to 12. Your entry in the **Computer Name** field in the **System Options** panel is `%host_name(12)%random_alpha_digit(3)%`.

Including `(n)` in the placeholder is optional. If you use only `%host_name%`, or if you set `<n>` to zero (that is, the placeholder resolves to the full host name.

- `%random_alpha_digit(n)%` – A randomly generated string of letters and numbers, where `<n>` is the number of characters. You must specify `<n>`.
- `%random_alpha(n)%` – A randomly generated string of letters, where `<n>` is the number of characters. You must specify `<n>`.
- `%random_digit(n)%` – A randomly generated string of numeric characters, where `<n>` is the number of characters. You must specify `<n>`.

For Windows Vista and Windows 7 guests, if the computer name is more than 15 characters, the Mini-Setup process fails on the user machine.

Specify Additional License Information for Windows Server Products

To supply additional license information for Windows Server products, you can add a file named `sysprep_license.txt` to the ACE-enabled virtual machine directory.

To specify additional license information for Windows Server products

- 1 Use a text editor to create a file named `sysprep_license.txt` in the virtual machine directory for the ACE-enabled virtual machine.

- 2 Add the following line to the file:

AutoMode=[PerSeat | PerServer]

This line indicates whether the license is for one client license or for a certain number of client licenses for a server.

- 3 If **AutoMode** is set to **PerServer**, add the following line to the file, where `<n>` indicates the number of client licenses for the server:

AutoUsers=<n>

- 4 Save and close the file.

For more information, go to the Microsoft TechNet Web site and in the Windows Server Library, search for [LicenseFilePrintData] (Sysprep).

If this file is not found in the virtual machine directory, a default is used. **AutoMode** is set to **PerServer** with 5 client licenses.

If you supply this file, the license portion of the Mini-Setup process appears unchanged during preview. You always see **AutoMode=PerServer** and **AutoUsers=5** in the Mini-Setup user interface. The license information you supply is nevertheless set correctly by the Mini-Setup process.

Set Up a Remote Domain Join

The remote domain join feature provides an automated way to join ACE instances to a domain from a remote site.

After the ACE package is installed on the end user's machine and the ACE instance is activated and authenticated, the Microsoft Mini-Setup process runs. The script for joining the remote ACE instance to the domain executes at the end of that process, and the machine is joined to the domain.

Before you begin, perform the following tasks:

- Determine which VPN client to download. The VPN client must support a command-line interface so that a script can be used for logging in to the VPN server. You might need to contact the VPN product's technical support to find out whether the VPN client supports a command-line interface.
- Obtain a VPN account for logging in to the server. Credentials include a user name and password. Randomly generated security tokens cannot be used as passwords. For example, you cannot use an RSA security token.
- Determine the following information to use for the VPN client profile: the company's group and password information and the name of the VPN server to contact to establish a secure connection.
- Determine the name of the domain that you plan to add the ACE instance to.
- Determine the user name and password for an account that has permission to add computers to the domain.

To set up a remote domain join

- 1 In the guest operating system of the ACE-enabled virtual machine, install a VPN client that supports a command-line interface.
- 2 Use the VPN client software to configure a profile for this client.

The profile in the VPN client contains a company's group and password information and determines which server to contact to establish a secure connection.

- 3 Write a `.bat` script that allows remote execution during the instance customization process.

Following is an example of a `.bat` script for a Cisco VPN client:

```
"net" start "Cisco Systems, Inc. VPN Service"
"C:\Program Files\Cisco Systems\VPN Client\vpnclient.exe" connect
    <profile_name> user <vpn_user_name> pwd %1 >> vpnlogs.txt
```

This example consists of two lines. The command in the first line starts the Cisco VPN client's background service. The command in the second line connects to the Cisco VPN using a command-line interface. It supplies the name of the VPN profile and the credentials for logging in to the VPN server. The example uses the password placeholder variable, but you could also use a static password for the VPN account. A static password included in a script is sent in clear text.

- 4 Save the **.bat** file on the **C:** drive of the guest's file system.
- 5 In Workstation, select the ACE-enabled virtual machine and choose **VM > ACE > Deployment Settings**.
- 6 Select **Workgroup or Domain**.
- 7 In the settings panel, select **Domain** and specify an organizational unit and user name for an account that has permission to add computers to the domain.

An example of an entry in the OU full path file is

OU=orgunits,DC=dpt,DC=domain,DC=com.

If the ACE-enabled virtual machine is managed, passwords and commands are stored on ACE Management Server.

If the ACE-enabled virtual machine is standalone, passwords and commands are stored with the package. Be sure to use encryption for the package.

- 8 Select **Enable Remote Domain Join**.
- 9 Specify the password for logging in to the VPN server.

You can then use the **%password%** placeholder variable in the **Command** text box to refer to this password.

- 10 Enter the command that executes the script.

For example, if you name the **.bat** script **vpn.bat** and want to use the password placeholder variable, enter the following command:

C:\vpn.bat%password%

If you use a password placeholder variable (**%password%**) in the **Command** field, the placeholder variable is resolved and replaced with the value from the **Password** field when the script executes.

- 11 Click **OK**.

To create a package with these settings, see [“Creating a Package”](#) on page 449.

Custom EULA Settings

You can provide a custom end-user license agreement (EULA) that appears when an ACE instance is activated. The user must see and accept the agreement before the instance can run for the first time.

The custom EULA must be a text file located in the ACE **Resources** directory for the ACE-enabled virtual machine. The file can use the following formats:

- For Windows hosts, use a `.txt` or `.rtf` file.
- For Linux hosts, use a `.txt` file.
- If you plan to deploy the package to both Windows and Linux computers, use a `.txt` file.

To specify whether to deploy to Windows hosts, Linux hosts, or both, use the **Deployment Platform** setting in the deployment settings editor.

Deployment Platform Settings

By default, ACE packages are created for Windows hosts. Change this setting to deploy to Linux or both Linux and Windows hosts.

ACE Resources Directory

The ACE **Resources** directory is a subdirectory of the ACE-enabled virtual machine's directory. All files placed in this directory are copied into the ACE package so that they can be used in end users' virtual machines.

Place the following types of files in the ACE **Resources** directory:

- Authentication scripts
See [“Using an Authentication Script”](#) on page 394.
- Power-on and power-off scripts
See [“Include a Power-On and Power-Off Script in the Package”](#) on page 394.
- Other resource files that authentication, power-on, or power-off scripts call
- Device files such as ISO images or FLP images that the virtual machine is configured to point to
- The skin file, which you can create to customize the VMware Player icons, removable device icons, and title bar text used in the VMware Player user interface on Windows guests
See [“Create and Specify a Skin File”](#) on page 428.

- Icon files for removable devices or the VMware Player application
See [“Customizing the VMware Player Icons”](#) on page 429 and [“Customizing the Removable Device Display”](#) on page 430.
- Custom EULAs
See [“Custom EULA Settings”](#) on page 445.

When you use the ACE Resources directory, take the following considerations into account:

- Do not place files in a subdirectory of the ACE Resources directory. If scripts or skin files reference other files, place those other files in the main ACE Resources directory. Make sure the script uses relative paths to reference those resources.

A resource is considered any file in the ACE Resources directory. You can specify whether to verify all files in the ACE Resources directory or just the policy scripts in that directory. For more information, see [“Setting Resource Signing Policies”](#) on page 401.
- If you change a policy or package setting that requires the ACE Resources directory, you must create an update package to deploy the change to end users.

Review the Configuration of an ACE-Enabled Virtual Machine

To finish preparing your ACE-enabled virtual machine and its files for packaging, review its configuration and policies and ensure that the appropriate operating system and software are installed in it.

To review the configuration of an ACE-enabled virtual machine

- 1 Verify that the ACE-enabled virtual machine has the necessary operating system, application software, and VMware Tools installed.

See [“Installing VMware Tools”](#) on page 104. For guest operating system support, known issues, and installation instructions, see the online *VMware Compatibility Guide*. Go to the VMware Web site and select **Resources > Compatibility Guides**, and click the **View the Guest/Host OS tab on the VMware Compatibility Guide Web site** link.
- 2 To review configuration settings, select the ACE-enabled virtual machine and choose **View > Current View > Summary**.
- 3 To review virtual machine devices and virtual hardware, click the **Devices** tab in the summary view.

- 4 To review virtual machine configuration options, click the **Options** tab.
- 5 To make changes to devices or options, click **Edit virtual machine settings** in the **Commands** list.
- 6 To review policies and deployment settings, click the **ACE** tab.
- 7 To make changes to policies or deployment settings, click **Edit policies** or **Edit deployment settings** in the **Commands** list.

Use Preview Mode to Test Policy and Deployment Settings

Preview mode enables you to see the effects of changed policies without having to package and deploy them. Preview mode also enables you to see the effects of setup choices without having to create, deploy, and install a full package.

Before you begin, verify that the settings and deployment platforms you want to test are appropriate for preview mode. Because ACE features are available only in the Windows version of Workstation, you cannot use preview mode to run ACE instances created for Linux hosts. You also cannot test a host policy in preview mode. To test ACE instances that you plan to deploy on Linux hosts, or for which you want to test a host policy, see [“Perform an End-to-End Deployment Test”](#) on page 455.

You can run the ACE instance in preview mode in VMware Player and also run the ACE-enabled virtual machine in Workstation without having to shut down the preview.

NOTE You can run any ACE-enabled virtual machine directly in Workstation to be sure that the guest operating system and applications perform as expected. However, an ACE-enabled virtual machine running in Workstation does not respect any policies that restrict its functionality.

To use preview mode to test policy and deployment settings

- 1 Open the ACE-enabled virtual machine to test.
- 2 In the summary view, click **Edit policies** in the **Commands** list.
- 3 In the **Policy** list, select the policy to change, complete the settings panel for that policy, and click **OK**.

- 4 In the summary view, click the **Preview in Player** in the **Commands** list.

A package based on a linked clone is created in a new directory, **Preview Deployment**, inside the ACE-enabled virtual machine's directory. The linked clone is created from a snapshot of the virtual machine's current state. Unlike a package that is deployed to an ACE user's machine, this package is not installed.

VMware Player allows you to activate and authenticate the ACE instance (if those policies are set). If configured, instance customization is also performed. The guest operating system starts.

- 5 Test the policy change in the running ACE instance to ensure that it is the one you want to make.

Preview mode enables VMware Player to run interactively so that you can see any instance customization errors and make corrections as needed.

- 6 (Optional) To make additional changes to policies or deployment settings, shut down the virtual machine and repeat this procedure.

You can have only one preview instance per ACE-enabled virtual machine. When you click **Preview in Player** a second or subsequent time, a message asks if you want to replace the current preview instance with a new deployment or use the existing deployment.

To change only policies and not repeat the activation and instance customization steps, use the existing deployment.

- 7 If ACE Management Server is managing the virtual machine, click **Publish Policies to Server**.

Creating a Package

After you create an ACE-enabled virtual machine and configure policies, devices, and deployment settings, use the New Package wizard to create a package that you can deploy to users.

NOTE To create a Pocket ACE package for distribution on portable devices, use the Pocket ACE Package wizard rather than the New Package wizard. See [“Create a Pocket ACE Package”](#) on page 460.

For packages that you plan to deploy to Windows hosts, you can specify that the package be distributed through a network image or through DVDs or CDs. For DVD and CD distribution, the package is divided into files that fit on standard discs.

Overview of Package Creation and Validation

Depending on whether you want to deploy a new ACE instance or update an installed one, you can create any of the following types of packages:

- **Full** – Includes an installer and the additional files needed to install an ACE package and the VMware Player application that runs the ACE instance. A full package allows you to create a completely new ACE instance.



CAUTION If you replace an existing ACE instance by supplying a new full package, end users lose any data or custom settings stored in the older ACE instance.

- **Policy Update or Server Update** – Includes just the policy-related files.
 - For standalone ACE-enabled virtual machines, the option is **Policy Update**.
 - For managed virtual machines, the option is **Server Update**.
 Among other policies, a server update package allows you to change the server that the ACE-enabled virtual machine is associated with or change an activation-only server setup to an activation and tracking setup.
- **Custom** – Allows you to choose specific items to deploy.
- **Pocket ACE** – The components for a Pocket ACE package vary slightly from those for the full package. For information about the Pocket ACE package, see [“Create a Pocket ACE Package”](#) on page 460.

The deployment settings and device settings that you already set for an ACE-enabled virtual machine allow you to create multiple packages quickly. You can use the same settings again and again.

Package validation occurs after you complete the New Package wizard. Package validation does the following:

- Checks that all files that the ACE-enabled virtual machine requires are present. Those files include:
 - Disk and snapshot files
 - Script files (if any policy is using scripts)

NOTE Package validation does not check for device files (ISO images, FLP images, and so on). To include device files in the package, put the files in the ACE Resources folder for the ACE-enabled virtual machine and set the devices to point to that location.

- Checks that the ACE-enabled virtual machine can be cloned: that it is powered off, multiple snapshots are enabled, and it is not read-only.
- Checks that the latest version of VMware Tools is installed.
- If instance customization is enabled, checks that the SysprepTools directory for the ACE-enabled virtual machine's guest operating system is not empty.
- If the guest operating system is Windows 2000, Windows XP, or Windows 2003, checks that the folders in the Program Files\VMware\VMware Workstation\Resources\SysprepTools folder are not empty.

You can deploy a package over a network or on DVD or CD. If you deploy the package on discs, the first disc of the set includes the Autorun files needed to start the installer automatically when the user inserts the disc in the host computer's drive.

Turn Off the VMware Tools Check for Test Deployments

If you do not have the latest version of VMware Tools installed in the guest operating system, the wizard fails to create the package. To create packages without installing the latest VMware Tools version each time—for example, if you want to perform a test deployment—you can turn off the VMware Tools check.

To turn off the VMware Tools check for test deployments

- 1 Close Workstation.

Use a text editor to open the `preferences.ini` file, which is located in the following directory:

- On Windows XP: `C:\Documents and Settings\<user>\Application Data\VMware`
- On Windows Vista and Windows 7:
`C:\Users\<test>\AppData\Roaming\VMware`

- 2 Add the following line to the file:

```
pref.ignoreToolsPkgCheck = "TRUE"
```

Setting this line to FALSE reinstates the VMware Tools check.

- 3 Save and close the `preferences.ini` file.

Before you create packages that you plan to deploy in production environments, reinstate the VMware Tools check.

Prerequisites for Using the Packaging Wizards

The following prerequisites apply to the New Package wizard and the Pocket ACE Package wizard:

- Ensure that the guest operating system and the most recent version of VMware Tools are installed in the ACE-enabled virtual machine. See [“Installing VMware Tools”](#) on page 104.
- Defragment virtual disks to ensure that the package is as compact as possible. See [“Defragment Virtual Disks”](#) on page 239.
- Preview the ACE instance to verify that all settings are working correctly. See [“Use Preview Mode to Test Policy and Deployment Settings”](#) on page 448.
- Determine the passwords used for the policies and deployment settings. These can include the following:
 - **Activation password** – Access control policy is set to **Password**.
 - **Domain join credentials** – Access control policy for the ACE instance is set to **Password**, and the **Instance Customization** deployment setting for **Domain** is enabled. This password is for the user account that has permission to add computers to this domain.
 - **Remote domain join credentials and VPN credentials** – The **Instance Customization** deployment settings for **Domain** and **Enable remote domain join** are enabled. The domain password is for the user account that has permission to add computers to this domain. The password in the **Remote domain join** section is for the user account that has permission to access the VPN server.
- Verify that you have enough disk space for temporary files created during packaging. You must have twice the combined sizes of all the components of the package.

The wizard displays information about the amount of space needed and the locations where the space is needed. If you do not have enough free space, you can move or delete files on the target drives to make room for the wizard's working files.
- Determine the type of package you want to deploy: full, update, or custom. See [“Overview of Package Creation and Validation”](#) on page 450.
- To distribute the package on DVDs or CDs, determine how much disk space is available. You can then specify the maximum file size used when the package is divided into multiple files.

To use instance customization, verify that the following prerequisites are satisfied:

- Make sure that the guest operating system is Windows XP, Windows 2000, or Windows Server 2003, Windows Vista, or Windows 7.
- Copy the Microsoft Sysprep Deployment Tools into the correct folder for the virtual machine. See [“Download the Microsoft Sysprep Deployment Tools”](#) on page 440.

If these tools are not available, the packaging operation fails. The failure might not occur until well into the packaging process and might cause you to lose substantial time.

- Use preview mode to test whether instance customization runs unattended. For example, verify that a valid Windows product ID is used so that no dialog box prompts for the product ID during the Mini-Setup process.
- If you configured automatic login, use preview mode to verify that automatic login works correctly. If it fails, instance customization fails.

Use the New Package Wizard

The New Package wizard creates an executable file that contains an ACE-enabled virtual machine, its policies, deployment settings, scripts, and a copy of VMware Player. You can easily deploy and install the package on end user’s machines.

Before you begin, verify that the packaging prerequisites are satisfied. See [“Prerequisites for Using the Packaging Wizards”](#) on page 452.

To use the New Package wizard

- 1 Open the ACE-enabled virtual machine to use as the basis for the package.
- 2 Make sure the virtual machine is powered off rather than suspended.

When you exit preview mode, by default VMware Player suspends the virtual machine. If necessary, use Workstation to power off the virtual machine.

- 3 Choose **VM > ACE > New Package**.
- 4 Complete the New Package wizard.
- 5 (Optional) If you are prompted to select a package distribution format and you select **Multiple folders for creating DVDs or CDs**, write down the disc label prefix you specify.

When you later use disc-burning software to create the discs, the name you enter for each disc must be the same as the name of the folder the wizard creates to hold that disc’s contents (for example, DISC1, DISC2).

- 6 To begin the packaging process, click **Next** on the Package Summary page.

Package creation takes a substantial amount of time, especially for packages that include large virtual machines or instance customization settings.

During the instance customization stage, if the guest operating system does not shut down after approximately 10 minutes, the problem might be that the Sysprep tools were not in place. The operation is cancelled and an error message tells you that instance customization failed.

The Package Creation Complete page appears when the process is complete. It lists the location of the newly created package and provides a link to the package directory.

- 7 Depending on which distribution method you chose, do one of the following:

- If you created a single file for network distribution, copy the file to the appropriate location on a network.
- If you created one or more files for distribution on CD or DVD, use disc-burning software to create the discs. Follow these guidelines:
 - The disc label you enter in your disc-burning software for each disc must be the same as the name of the folder the wizard creates to hold that disc's contents.
 - Burn the contents of each disc onto the top level of the disc.

The package installer expects to find only the contents of the folder, and not the folder itself, at the root level on the disc. If you burn the folder itself onto the disc, when you attempt to install the contents of the second or subsequent discs on the user's machine, the error 1309, "Error reading from file <filename>", appears.

View Package Properties and Add Notes

Use the Package Properties dialog box to view properties of the packages that you created. Also add or edit notes that appear in the summary view of the ACE-enabled virtual machine.

To view package properties and add notes

- 1 Open the ACE-enabled virtual machine.
- 2 Choose **View > Current View > Summary**.

- 3 On the **Packages** tab, double-click the package name.
- 4 In the Package Properties dialog box, click the tabs to view the properties.
- 5 Click the **Notes** tab to add or edit notes.

Existing notes might have been added when the package was created using the New Package wizard. These notes are not be seen by end users. They are visible only in the Workstation window.

Perform an End-to-End Deployment Test

Perform an end-to-end test to deploy a new ACE package rather than a package update. Also use an end-to-end test if using preview mode is not appropriate.

Because Workstation runs only on Windows hosts, you cannot use preview mode to run ACE instances as they will run on Linux hosts. You also cannot test a host policy in preview mode.

NOTE This test might take a substantial amount of time because packaging and encryption processes can be lengthy.

Before you begin, if you plan to use an ACE Management Server to manage the ACE instances, install and configure a test ACE Management Server. See the *VMware ACE Management Server Administrator's Guide*.

To perform an end-to-end deployment test

- 1 If you use the ACE Management Server, select the ACE-enabled virtual machine, choose **File > Connect to ACE Management Server**, and connect to the test server.
- 2 In the virtual machine's summary view, click **Create new package** in the **Commands** list.
- 3 Complete the New Package wizard.
- 4 Navigate to the package location and copy the package directory to a client test machine.
- 5 On the client test machine, run the ACE instance's `setup.exe` file and complete the pages of the installation wizard.

- 6 Start the ACE instance and activate it when prompted.

Depending on how you configured the package, a **Start** menu item or a desktop shortcut or both are created on the client machine. Depending on the runtime preferences you set, the ACE instance might start in full screen mode when the host system starts.

- 7 Verify that the ACE instance is configured as you intended and runs as you expect.
- 8 If you use ACE Management Server, connect the ACE-enabled virtual machine to the production server.

On the administrator machine, in Workstation, select the ACE-enabled virtual machine and choose **File > Connect to ACE Management Server**, and connect to the production server.

- 9 If you use ACE Management Server, create a new package.

The package you created for the test refers to the server you used for testing. Instances created from that package refer to the test server.

Deploy Packages

Deploying packages means making the ACE package available to end users. You specify the distribution method when you create the package.

To deploy packages

Depending on the type of package, do one of the following:

- For a full, policy update, server update, or custom package, distribute the package on CD or DVD, or make the package available on a network.
- For a Pocket ACE package, see [“Deploying the ACE Package on a Portable Device”](#) on page 461.

The Pocket ACE feature enables you to store ACE instances on portable devices such as USB keys (flash memory drives), Apple iPod mobile digital devices, and portable hard drives. ACE users attach these portable devices to x86 host computers, run their ACE instances with VMware Player, and then detach the portable devices. The next time they need access to their ACE instances, they can attach the devices to the same host computers or to different computers.

Use Pocket ACE to package a daily computing environment and allow end users to take that environment—including documents, settings, applications, and VPN access—wherever they need to go.

This chapter includes the following topics:

- [“Use Cases for Pocket ACE”](#) on page 458
- [“Portable Device Requirements”](#) on page 459
- [“Policies and Deployment Settings for Pocket ACE”](#) on page 460
- [“Create a Pocket ACE Package”](#) on page 460
- [“Deploying the ACE Package on a Portable Device”](#) on page 461
- [“Run the Pocket ACE Instance”](#) on page 463

Use Cases for Pocket ACE

Use the following scenarios to determine when to use Pocket ACE and which kinds of policies to set for various situations:

- **Providing access to employees working remotely** – Employees often use their own home computer for accessing enterprise resources remotely. Unmanaged clients can be infected by malware or spyware. In addition, there is a risk of lost data if a remote user downloads sensitive data to a personal computer. There is also the added burden of deploying and managing the software needed by remote users.

Using Pocket ACE, IT administrators can deploy a trusted, managed, and more secure virtual desktop instance to remote users. The virtual disk of the Pocket ACE can be encrypted to minimize the risk of lost data. By setting specific network quarantine policies, administrators can strictly control traffic between the untrusted client and Pocket ACE instance, protecting the enterprise from creating a compromised host.

- **Increasing the security and mobility of mobile users** – Mobile users often access or carry sensitive data outside the enterprise using laptops or other mobile devices. The question for IT organizations is not if, but when, a mobile user's laptop will be lost or stolen, leading to the loss of sensitive or confidential data.

Using Pocket ACE to deploy a desktop environment to mobile users, IT administrators can reduce the risk of lost data while also increasing users' mobility because Pocket ACE instance can be used with any supported x86 system. A desktop instance with an encrypted disk can be deployed to mobile users. Using ACE Management Server, a lost or stolen Pocket ACE can be disabled remotely.

- **Providing temporary access to contract workers using untrusted hosts** – Contractors and business partners often connect to the enterprise network from unknown or untrusted clients. Pocket ACE can be used to provide a standardized, trusted, and managed environment to these users while enabling safe connectivity to enterprise resources.

For contractors, the Pocket ACE instance can be configured to be available only during the length of the contract. When the expiration date is reached, the contractor can no longer use the Pocket ACE instance.

- **Providing access to offshore outsource partners** – Typically, offshore partners manage and own the desktop systems they use. Because these resources are owned by an outside organization, they do not fall under standard IT policy. In some cases, desktop systems are purchased, imaged, and shipped to an offshore partner for accessing the enterprise. This is often a lengthy and costly process.

With Pocket ACE, IT administrators can easily deploy a trusted, managed, and more secure virtual desktop instance to offshore partners. The virtual desktop instances can be distributed using portable media or download. Security features include the data encryption feature and the network quarantine and restriction features already mentioned.

- **Providing disaster recovery** – Using Pocket ACE, organizations can easily package desktop instances with all the necessary enterprise applications for use in the case of a disaster. These instances can be deployed to portable media devices and stored safely in a secure offsite facility. If a disaster occurs, the Pocket ACE instances can be quickly distributed and used.
- **Distributing beta or trial software** – Using Pocket ACE, ISVs can distribute software preinstalled as a virtual appliance either by download or on a portable media device. An ISV can provide a complete working environment, ensuring no compatibility issues. Custom EULAs can be created and used to ensure that a user accepts the agreement prior to using an ACE instance. In addition, an expiration period can be set that disables an ACE instance after an allotted period of time.

Portable Device Requirements

You can install ACE packages on the following types of devices:

- Flash memory drives (USB keys)
- Flash-based Apple iPod mobile digital devices
- Hard drive–based Apple iPod mobile digital devices
- Portable hard drives

For USB devices, use USB 2 high-speed devices only.

When a Pocket ACE package is deployed to a removable device, the virtual disk is preallocated to full capacity for enhanced performance. Make sure that the removable device has enough disk space to store the virtual disk's total capacity, memory, and approximately 300MB for overhead. See [“Use the New Virtual Machine Wizard”](#) on page 89.

Policies and Deployment Settings for Pocket ACE

Some policies apply only to Pocket ACE. You can set Pocket ACE close behavior by editing the runtime preferences policy.

Close behavior determines whether the ACE instance is powered off or suspended when the user exits and whether changes are synchronized on the removable device. See [“Pocket ACE Cache Settings”](#) on page 417.

Pocket ACE ignores some policies. Although you can set host and snapshot policies and create a package that includes them, Pocket ACE instances ignore these policies. Administrators cannot revert to reimage snapshots when running a Pocket ACE in administrator mode in VMware Player.

Create a Pocket ACE Package

Before you begin, determine the following information, which is specific to Pocket ACE:

- Make sure the portable device meets the hardware and disk space requirements for Pocket ACE. See [“Portable Device Requirements”](#) on page 459.
- Determine whether you want to deploy the Pocket ACE to Windows machines, 32-bit Linux machines, 64-bit Linux machines, or some combination. Your choices affect the disk space requirements.
- Determine the password you want to use for anyone who attempts to deploy the package to a portable device.

If you do not want to require a password, make sure the access control policy's authentication type is set to **None**. Make sure the encryption deployment setting for package protection is set to **None**.

In addition, complete the tasks listed in [“Prerequisites for Using the Packaging Wizards”](#) on page 452.

To create a Pocket ACE package

- 1 Open the ACE-enabled virtual machine to use as the basis for the package.
- 2 Make sure the virtual machine is powered off rather than suspended.

When you exit preview mode, by default VMware Player suspends the virtual machine. If necessary, use Workstation to power off the virtual machine.

- 3 To create a new Pocket ACE or an update package, choose **VM > ACE > New Pocket ACE Package**.
- 4 Complete the wizard.

When you specify a location on the Name the Package page, choose a location on the administrator machine. Do not specify a location on the portable device. You deploy the package to the device after the package is created.

The Completing the Pocket ACE Package Wizard page appears when the process is complete.

- 5 (Optional) To deploy the package immediately, select **Deploy to a portable device now**.

If you do not deploy the package immediately, see [“Deploying the ACE Package on a Portable Device.”](#)

Deploying the ACE Package on a Portable Device

You can deploy multiple ACE packages on a single portable device. The only limitation on the number of packages is the amount of available space on the device.

Run the `deploy.exe` file to use the GUI deployment utility. Use the `bulkDeploy.exe` program to use the command-line deployment utility. You can create a batch file that contains multiple `bulkDeploy` commands to deploy multiple ACE packages to a portable device.

The wizard automatically preallocates disk space and splits the disk into 2GB segments.

The Pocket ACE instance is reencrypted during the deployment instead of after the user’s first run of the instance. For this reencryption, the policy applied is the package protection policy that was in place at the time of packaging.

Use the Graphical Utility to Deploy Pocket ACE Packages

Before you begin, make sure the removable device meets the hardware and disk space requirements. See [“Portable Device Requirements”](#) on page 459.

To use the graphical utility to deploy Pocket ACE packages

- 1 Navigate to the package location you specified in the New Pocket ACE Package wizard.
- 2 Double-click the `deploy.exe` file.

- 3 If the Enter Password dialog box appears, enter the deployment password.
- 4 Complete the VMware Pocket ACE Deploy Utility dialog box and click **Deploy**.

When you distribute the Pocket ACE, give it directly to the user and tell the user to keep the Pocket ACE secure until the user runs the ACE and changes the user password.

Use the Command-Line Utility to Deploy Pocket ACE Packages

The `bulkDeploy.exe` utility is a command-line version of the VMware Pocket ACE Deploy Utility dialog box (`deploy.exe`). Use `bulkDeploy.exe` commands in a batch file to deploy one or more Pocket ACE packages to the same or multiple target directories or removable devices.

Before you begin, make sure the removable device meets the hardware and disk space requirements. See [“Portable Device Requirements”](#) on page 459.

If you plan to deploy the Pocket ACE package to a custom folder rather than a removable drive, create the folder.

To use the command-line utility to deploy Pocket ACE packages

- 1 Open a command prompt and change directories to the package location you specified in the New Pocket ACE Package wizard.

For example, enter the following command:

```
cd C:\Documents and Settings\Administrator\My Documents\
Virtual Machines\ACE-Enabled Virtual Machine\Packages\Pocket ACE Package
```

- 2 Enter the following bulk deployment command and specify the necessary parameters:

```
bulkDeploy.exe <deployment_directory> <parameters>
```

The `<deployment_directory>` value can specify a removable drive or a custom folder.

Table 21-1. Deployment Commands

Parameter	Usage
-p	Deployment password. Required when the package is password protected.
-s	Path to the .vmx file on the host. Use this parameter only if you use a <code>bulkDeploy.exe</code> file that is not located inside the same Pocket ACE package as the .vmx file you want to deploy.

Table 21-1. Deployment Commands (Continued)

Parameter	Usage
-q	Parameter to turn off reporting the progress of the bulk deployment.
-t	Performs a speed test to determine whether the USB device and the host USB stack are fast enough for Pocket ACE. If the test is successful, 0 is returned. If it fails, a negative number is returned. This test is always done at runtime when the Pocket ACE is opened. It is done when you use the <code>bulkDeploy</code> command only if you use the <code>-t</code> parameter.

For example,

```
bulkDeploy.exe E: -p password -s C:\pocketACEPackage\VM\packagedVMX.vmx
-q -t
```

- 3 (Optional) To deploy a Pocket ACE package to multiple locations, or to deploy multiple packages to the same or multiple locations, create a batch file with a `bulkDeploy.exe` command on each line.

Use quotation marks for paths that contain spaces. Following is an example of a batch file:

```
"C:\My VMs\vm_1\Packages\Pkg_1\bulkDeploy.exe" E: -p password -q -t
"C:\My VMs\vm_1\Packages\Pkg_1\bulkDeploy.exe" F: -p password -s
"C:\My VMs\vm_2\Packages\Pkg_2\VM\Pkg_2.vmx" -q -t
"C:\My VMs\vm_1\Packages\Pkg_1\bulkDeploy.exe" F: -p password -s
"C:\My VMs\vm_3\Packages\Pkg_3\VM\Pkg_3.vmx" -q -t
```

Run the Pocket ACE Instance

After you deploy a Pocket ACE package to a removable device, running it usually involves only plugging it in.

Before you begin, make sure that the host computer's clock is set to the correct time. If you move a Pocket ACE from one host computer to another and the clock of the second host is earlier than the clock of the first, the Pocket ACE does not run.

When the ACE instance runs, its disk and checkpoint caches are initialized. If the Pocket ACE has a session on this host, that session continues. Otherwise a new session is started.

The checkpoint state and virtual disk are cached on the host during use and synchronized back to the portable device later. The checkpoint state and virtual disk are protected with the same encryption level used for the ACE instance on the portable device.

The Pocket ACE runs primarily from the host cache, although it occasionally reads from the parent disk on the portable device. The ACE instance does not write to the parent disk until synchronization.

To run a pocket ACE instance

- 1 Plug the portable device into the host computer.
- 2 If the host system's Autorun configuration is not set to start the ACE instance automatically, do one of the following:

- On Windows hosts, navigate to the removable device and run the Pocket ACE.

Usually, starting the Pocket ACE manually is not necessary. The Autorun program is included in the package and checks whether VMware Player is installed. If not, VMware Player is installed automatically.

- On Linux systems, install VMware Player from the `Player` directory on the USB drive.

For example, if the USB drive is mounted at `/media/USBFLASH`, navigate to `/media/USBFLASH/player`.

- Install VMware Player as described in [“Manually Install VMware Player on a Linux Host”](#) on page 469.
- Use VMware Player to open the `.vmx` file and start the ACE instance (see [“Install the ACE Instance on a Single Linux Host”](#) on page 470).

Installing ACE Packages

This chapter includes the following topics:

- [“Installing an ACE Package on a Windows Host”](#) on page 465
- [“Installing an ACE Package on a Linux Host”](#) on page 469
- [“Upgrading ACE Instances to ACE 2.6”](#) on page 473
- [“Start and Use an ACE Instance”](#) on page 474
- [“Install an ACE Client License”](#) on page 478
- [“Quit VMware Player”](#) on page 479
- [“Troubleshooting Tools”](#) on page 479

Installing an ACE Package on a Windows Host

If an end user’s computer does not already have VMware ACE or VMware Player installed, the first time you install an ACE package, VMware Player is installed along with the ACE instance.

You can install ACE instances on one host at a time, or you can use the silent installation features of the Microsoft Windows Installer to quickly install an ACE instance on multiple computers.

Install an ACE Instance on a Single Windows Host

If VMware Player is not already installed on the machine, the installation program installs it before installing the virtual machine files that make up the ACE instance.

Before you begin, consider the following prerequisites:

- Make sure the host computer has enough disk space for the ACE instance.
- If this is the first installation of an ACE instance on the user's machine, a user with administrative privileges must run the installation. Only a user with administrative privileges can install and uninstall VMware Player.
- If the ACE instance includes a host policy, a user with administrative privileges must run the installation. A host policy is a host network access policy or a policy that restricts which virtual machines can run on a host. See ["Setting Network Access Policies"](#) on page 402 and ["Control Which ACE Instances Run on a Host"](#) on page 422.

Only one set of host policies can be deployed to a particular host. If a package contains host policies and the host already contains host policies from another package, installation of the second package fails.

To install an ACE instance on a single Windows host

- 1 If VMware Player is not yet installed on the user's machine, log in to the host computer as the Administrator user or as a user who is a member of the Windows Administrators group.
- 2 Depending on whether you are installing from a CD, DVD, or network location, do one of the following:
 - For CDs and DVDs, insert the first disc.
 - For a network location, navigate to the location of the installer.
- 3 Find the `setup.exe` file and double-click it.
- 4 Follow the prompts.

Installing an ACE Package Silently on Multiple Windows Hosts

If you are installing a VMware ACE package on a number of Windows host computers, you might want to use the silent installation features of the Microsoft Windows Installer. This type of installation requires that the host computers have version 2.0 or later of the MSI runtime engine. This version of the installer is available in versions of Windows beginning with Windows XP. If the runtime engine is not installed, see ["Install the MSI 2.0 Runtime Engine from an ACE Package"](#) on page 467.

Install the MSI 2.0 Runtime Engine from an ACE Package

The installer for the MSI 2.0 runtime engine is included in the VMware ACE package as the `instmsiw.exe` file.

To install the MSI 2.0 runtime engine from an ACE package

- 1 On the host computer, open a command prompt.
- 2 Enter the following command:

```
instmsiw.exe /Q
```

For additional details on how to use the Microsoft Windows Installer, see the Microsoft Web site.

Install an ACE Instance on Multiple Hosts

You can use the Microsoft Windows Installer command-line interface to silently install an ACE instance on many computers. End users are not prompted for information during the installation process.

Before you begin, verify that the host computers have version 2.0 or later of the MSI runtime engine.

You can customize the basic package installation command to specify one or more of the following:

- Installation directory for the ACE instance
- Installation directory for VMware Player
- Installation without a desktop icon

You can also install an upgrade silently. An upgrade is always installed in the same directory or directories as the previous package.

To install the ACE instance on multiple hosts

- 1 On the host computer, open a command prompt.
- 2 Enter the following command:

```
setup.exe /s/v"/qn"
```

This command installs the package and VMware Player (if included) into the default locations and creates a shortcut for the ACE instance on the desktop. The default location for the VMware Player application is `C:\Program Files\VMware\VMware Player`.

The default location for the virtual machine files:

- On Windows XP is C:\Documents and Settings\All Users\Application Data\VMware\VMware ACE\<ACE_name>.
- On Windows Vista and Windows 7 is C:\ProgramData\VMware\VMware ACE\

3 To customize the package, enter the following command:

```
msiexec -i package.msi <installation_options>
```

Enter the command on one line. The installation options follow.

Table 22-1. Installation Options

Option	Description
DESKTOP_SHORTCUTS	When set to 0, skips installation of the ACE instance shortcut on the desktop. The default is 1.
INSTALLDIR	Sets the root installation directory for the ACE instance.
PLAYER_INSTALLDIR	Sets the root installation directory for the VMware Player application.

The following example command illustrates the options and their usage:

```
msiexec -i package.msi DESKTOP_SHORTCUTS=0  
INSTALLDIR="G:\packages"  
PLAYER_INSTALLDIR="C:\VMware\VMware Player" /qn
```

Uninstall VMware Player or an ACE instance from a Windows Host

Uninstalling VMware Player does not uninstall the ACE instance. Only the Administrator user or a user who is a member of the Windows Administrators group can uninstall VMware Player.

Uninstalling an ACE instance does not uninstall the VMware Player application. When you remove an ACE instance, the ACE instance's data files, shortcuts, and registry entries are removed. You do not need to be an Administrator user to uninstall an ACE instance.

To uninstall VMware Player or an ACE instance from a Windows host

- 1 Go to **Start > Control Panel > Add or Remove Programs > Change or Remove Programs**.
- 2 Select the VMware Player program or the ACE instance and click **Remove**.

- 3 Follow the instructions in the wizard.
- 4 (Optional) If you used Pocket ACE on this host and want to remove the Pocket ACE cache to conserve disk space, delete the following folder:
 - On Windows XP: `C:\Documents and Settings\<user>\Local Settings\Application Data\VMware\Roaming VM cache\`
 - On Windows Vista and Windows 7: `C:\Users\<USER>\AppData\Local\VMware\Roaming VM cache`

In this path, <user> represents a user-specific directory. If more than one user used Pocket ACE on the host, you must remove the directory for each user.

Installing an ACE Package on a Linux Host

If an end user's computer does not already have VMware ACE or VMware Player installed, VMware Player is automatically installed when you run the ACE package's `VMware-Player.bundle` file as root or sudo.

You can install ACE instances on one host at a time, or you can silently install an ACE instance on multiple computers.

Manually Install VMware Player on a Linux Host

Manually install VMware Player on systems where the end user does not have root access and does not already have VMware ACE or VMware Player installed.

To manually install VMware Player on a Linux host

- 1 In a terminal window, enter the following command to become the root user:


```
su
```
- 2 Mount the ACE package, and locate the VMware Player installer in the package directory.

Depending on whether the host is a 32-bit computer or a 64-bit computer, you see one of the following filenames:

- `VMware-Player-i386.bundle`
- `VMware-Player-x86_64.bundle`

- 3 Copy the `.bundle` file to a temporary directory on the hard drive.

For example, if you have a 64-bit computer and you want to put the file in the `/tmp` directory, enter the following command:

```
cp VMware-Player-x86_64.bundle /tmp
```

- 4 Enter the following command to change to the directory to which you copied the file:

```
cd /tmp
```

- 5 Enter the following command to run the installation program:

```
sh VMware-Player-<architecture>.bundle
```

The `<architecture>` value is either `i386`, for 32-bit systems, or `x86_64`, for 64-bit systems.

- 6 Follow the wizard prompts that appear.

On most Linux distributions, a GUI wizard appears. On Red Hat Enterprise Linux 5.1 and some other distributions, a command-line wizard appears. In the command-line wizard, to quickly scroll to the end of the license agreement prompt, press **q** and accept the agreement.

- 7 When installation is completed, enter the following command to exit from the `root` account:

```
exit
```

Install the ACE Instance on a Single Linux Host

Only the user who installs the ACE instance or a user with necessary permissions (such as `root`) is allowed to run that ACE instance. If VMware Player is not already installed on the machine, it is automatically installed when you run the ACE package's `sh VMware-Player-<architecture>.bundle` as `root` or `sudo`.

Before you begin, consider the following prerequisites:

- Make sure the host computer has enough disk space for the ACE instance.
- The ACE package must be accessible to the Linux user machines for installation.

- If this is the first installation of an ACE instance on the user machine, a root user must run the installation. Only a root user can install and uninstall VMware Player.
- If the ACE instance includes a host policy, a root user must run the installation. A host policy is a host network access policy or a policy that restricts which virtual machines can run on a host. See [“Setting Network Access Policies”](#) on page 402 and [“Control Which ACE Instances Run on a Host”](#) on page 422.

Only one set of host policies can be deployed to a particular host. If a package contains host policies and the host already contains host policies from another package, installation of the second package fails.

To install an ACE instance on a single Linux host

- 1 Copy the `.bundle` file for the package to the host computer.
- 2 Open a terminal window and change to the package directory.
- 3 Enter the following command to run the installation program:
`./vmware-install.pl`
- 4 Follow the wizard prompts that appear.

On most Linux distributions, a GUI wizard does not appear. On Red Hat Enterprise Linux 5.1 and some other distributions, a command-line wizard appears. In the command-line wizard, to quickly scroll to the end of the license agreement prompt, press **q** and accept the agreement.

Install an ACE Package Silently on Multiple Linux Hosts

You can silently install an ACE instance on many computers. End users are not prompted for information during the installation process.

To install the ACE instance on multiple Linux hosts

- 1 Copy the `.bundle` file for the package to the first host computer.
- 2 Open a terminal window and enter the following command:
`./vmware-install.pl`
- 3 Repeat this procedure for other hosts.

Prepare a Linux Host for Running in Kiosk Mode

On Linux hosts, if you plan to use kiosk mode to prevent users from accessing the host operating system, you must set some additional properties. If you do not prepare the host, users might be able to use keyboard shortcuts or other mechanisms to access the host when in kiosk mode.

Before you begin, create an ACE instance that uses a kiosk mode policy and install it on a Linux host. See [“Setting Kiosk Mode Policies”](#) on page 420 and [“Installing an ACE Package on a Linux Host”](#) on page 469.

The preferred window managers for running ACE instances in kiosk mode are F Virtual Window Manager (FVWM) and Metacity.

To prepare a Linux host for running in kiosk mode

- 1 Use a text editor to add the following lines to the host's `~/ .vmware/preferences` file:

```
pref.grabOnKeyPress = "TRUE"
pref.grabOnMouseClicked = "TRUE"
```

- 2 Add the following lines to create a `ServerFlags` section in the `/etc/X11/xorg.conf` file:

```
Section "ServerFlags"
    Option "DontZoom" "true"
    Option "DontZap" "true"
    Option "DontVTSwitch" "true"
EndSection
```

- 3 Restart the X session.
- 4 Manually disable all keyboard shortcuts in host's window manager.
- 5 If the Deskbar applet program is used in the panel on the host, remove it by right-clicking it and selecting **Remove from Panel**.

If you do not remove this applet, a user can press the keyboard combination for exiting kiosk mode and then press **Alt+F3** to access the host file system.

- 6 To prevent the host's file browser from opening when a removable device is connected to the host, disable the applicable options in the host's system preferences and file browser preferences.

For example, open a file browser on the host and select **Edit > Preferences > Media** and deselect the **Browse media when inserted** check box. Also, from the host's **System** menu, select **Preferences > Removable Devices**, or similarly named tabs, and deselect the check boxes.

Uninstall VMware Player or an ACE Instance from a Linux Host

ACE users can uninstall only the ACE instances that they installed. Only the root user can uninstall others' ACE instances. Uninstalling an ACE instance does not uninstall the VMware Player application. When you uninstall an ACE instance, the ACE instance's data files, shortcuts, and registry entries are uninstalled.

Uninstalling VMware Player does not uninstall the ACE instance. Only the root user can uninstall VMware Player.

To uninstall VMware Player or an ACE instance from a Linux host

- 1 On the host computer, open a terminal window.
- 2 Do one or both of the following:
 - To uninstall an ACE instance, enter the following command:
`<path_to_instance_directory>./vmware-uninstall-ace.pl`
 - To uninstall VMware Player, enter the following command:
`vmware-installer -u vmware-player`
- 3 (Optional) If you used Pocket ACE on this host and want to remove the Pocket ACE cache to conserve disk space, delete the following directory:
`/home/<user>/.vmware/roamcache`

In this path, <user> represents a user-specific directory. If more than one user used Pocket ACE on the host, you must remove the directory for each user.

Upgrading ACE Instances to ACE 2.6

If you have ACE 2.0 instances, you can use Workstation 7.0 and ACE Management Server 2.6 to send new ACE 2.6 policies to end users.

Although new policies, such as Pocket ACE cache settings and network adapter settings can be used on ACE 2.0 endpoints, the virtual machine version is not changed. To upgrade end users' virtual machine hardware version, you must create a full package and use it to replace the existing ACE instance.

When you uninstall the older ACE instance and VMware Player from the user's computer, the end user loses any data or custom settings stored in the old ACE instance. Take this consideration into account when choosing between upgrading the hardware version and continuing with the current hardware version but adding new ACE 2.6 policies.

Start and Use an ACE Instance

When you run an ACE instance, VMware Player starts and opens the instance. You start the instance in the same way that you start other applications on the host.

One exception is if the administrator configures the ACE instance to start and run in full screen mode when the host system starts. See [“Setting Runtime Preferences Policies”](#) on page 415.

Depending on how the ACE instance is configured, end users might be required to enter no password, one, or two passwords when they run the instance for the first time. The possibilities are:

- No passwords are required at the first run of the instance or on subsequent runs.
- You must enter one password at the first run, and that password is supplied to you by the administrator. On subsequent runs of the instance, no passwords are required.
- You must create a password at the first run. On subsequent runs, you must enter that password.
- You must enter an administrator-supplied password at the first run and also create a password. On subsequent runs, you must enter only the password that you created.

The administrator can also restrict how many characters or which characters can be used in passwords that end users create. See [“Authentication Settings”](#) on page 393.

To start and use an ACE instance

- 1 Depending on the host operating system, do one of the following:
 - On Windows hosts, use the desktop icon or the **Start** menu to start the ACE instance.
 - On Linux hosts, use the **Applications** menu or enter the following command in a terminal window:


```
vmplayer <path_to__package_directory>/<name_of_ACE_vmx_file>.vmx
```
- 2 If prompted to enter or create a password, do so.
- 3 If the Enter Serial Number dialog box appears, do one of the following:
 - If your administrator provided a serial number, enter it.
 - If you need to purchase a license, click **Get Serial Number**.

- 4 Click inside the VMware Player window to begin using the guest operating system and the applications installed in the ACE instance.

You can use the operating system and applications just as you would if they were running directly on a physical computer.

- 5 (Optional) To change a password that you created, choose **VM > ACE > Change Password**.
- 6 (Optional) For more information about using VMware Player, choose **Help > Help Topics**.

Change Default Kiosk Mode Startup Behavior

If an ACE instance is configured to run in kiosk mode, the virtual machine runs in full screen mode and does not display the ACE menu bar or ACE Player online help.

Before going into kiosk mode, a dialog box appears, requiring the user to consent to entering kiosk mode. For more information, see [“Setting Kiosk Mode Policies”](#) on page 420.

You can use a command-line command to start an ACE instance in kiosk mode without displaying the usual warning message.

You can also start the ACE instance so that it is not in kiosk mode. You can then use the VMware Player menus to change preference settings or enter administrator mode if the ACE instance is configured for that mode.

To change default kiosk mode startup behavior

- 1 Open a command prompt on Windows hosts or a terminal window on Linux hosts.
- 2 To suppress the dialog box usually shown at startup, do one of the following:

- On Windows, enter the following command:

```
<path>\vmplayer.exe -k "<config-file>"
```

In this command, `<path>` is the path on your system to the VMware Player application file and `<config-file>` is the path to the virtual machine configuration (.vmx) file.

- On Linux, enter one of the following commands:

- **vmplayer -k "<config-file>"**

- **vmplayer --noKioskWarning "<config-file>"**

In these commands, `<config-file>` is the path to the virtual machine configuration (.vmx) file.

- 3 To start the ACE instance without entering kiosk mode, do one of the following:

- On Windows, enter the following command:

```
<path>\vmplayer.exe -K "<config-file>"
```

Notice the capital **K**. In this command, `<path>` is the path on your system to the VMware Player application file and `<config-file>` is the path to the virtual machine configuration (.vmx) file.

- On Linux, enter one of the following commands:

- **vmplayer -K "<config-file>"**

- **vmplayer --forceNoKiosk "<config-file>"**

In these commands, `<config-file>` is the path to the virtual machine configuration (.vmx) file.

- 4 If you use a command to start the instance without entering kiosk mode, enter the administrator password when prompted.

This procedure describes typing the command at the command line, but you can also use the command to create a batch file or a desktop shortcut. See [“Using Startup Options in a Windows Shortcut”](#) on page 487.

Use Multiple Virtual Machines in Kiosk Mode

You can start multiple ACE instances that are configured to run in kiosk mode. You can then switch between virtual machines by using a keyboard shortcut.

Before you begin, create and package multiple ACE instances that use the same administrator password for kiosk mode and the same hot-key combination for exiting kiosk mode. See [“Setting Kiosk Mode Policies”](#) on page 420.

When multiple virtual machines run in kiosk mode, end users can press the hot-key combination along with the right arrow or left arrow key to switch to the next or previous virtual machine. For example, if the hot-key combination is Ctrl+Alt, users can press Ctrl+Alt+right arrow to switch to the next virtual machine or Ctrl+Alt+left arrow to switch to the previous virtual machine.

To use multiple virtual machines in kiosk mode

- 1 Install the ACE instances on the host machine.
- 2 Use the following examples to write a batch file or script to start the virtual machines:

Windows batch file:

```
cd Program Files\VMware\VMware Player
start vmplayer.exe -k "C:\Documents and Settings\user1\My Documents\My
    Virtual Machines\ace1\ace1.vmx"

sleep 20
start vmplayer.exe -k "C:\Documents and Settings\user1\My Documents\My
    Virtual Machines\ace2\ace2.vmx"

sleep 20
start vmplayer.exe -k "C:\Documents and Settings\user1\My Documents\My
    Virtual Machines\ace3\ace3.vmx"
```

Linux script file:

```
#!/bin/bash
vmplayer -k ~/vmware-ace/ace1/ace1.vmx & sleep 20
vmplayer -k ~/vmware-ace/ace2/ace2.vmx & sleep 20
vmplayer -k ~/vmware-ace/ace3/ace3.vmx &
```

The `-k` flag suppresses the kiosk mode dialog box so that you do not need to click **OK** to enter kiosk mode.

- 3 If any virtual machines that are not set to run in kiosk mode are open or running on the host, power them off and close them.

The script cannot start and run virtual machines in kiosk mode if any non-kiosk-mode virtual machines are open.

- 4 Run the batch file or script to start the virtual machines in kiosk mode.

The virtual machines are started in the order listed in the batch file or script. The first virtual machine started defines the administrator password for kiosk mode and the hot-key combination for exiting kiosk mode. If a subsequent virtual machine in the list has a different password or hot-key, it does not start. If a subsequent virtual machine in the list is not configured to start in kiosk mode, it is not allowed to start.

Install an ACE Client License

An ACE client license is a device-specific license. Devices include PCs, laptops, and portable media devices such as USB flash drives (storing a Pocket ACE). The details of the licensing terms are provided in the end user license agreement (EULA) for ACE published on www.vmware.com.

A licensed device can run any number of ACE instances. The ACE client license is associated with the device it is installed on and is not restricted to a specific ACE instance.

If you purchase a volume license, you do not need to install client licenses.

NOTE If you are not using an ACE volume license key, be aware that when you deploy a Pocket ACE to a portable media device, you should enter an ACE client license immediately. The Pocket ACE will run locally on that copy of Workstation, but if it is moved to another unlicensed device without having the ACE client license entered, it will not power on.

To install an ACE client license

- 1 Obtain the ACE client license serial number from your ACE administrator.
- 2 Double-click the desktop shortcut for the installed ACE instance.
- 3 At the prompt, enter the serial number in the appropriate field and enter your name and the organization name in the dialog box.
- 4 Click **OK**.

Change the ACE Client License

You can use a VMware Player menu command to change or update a license.

To change the ACE Client License

- 1 Choose **Help > Enter ACE Client License**.
- 2 Do one of the following:
 - Enter the serial number in the dialog box.
 - If you need to purchase a license, click **Get Serial Number**.
- 3 Click **OK**.

Quit VMware Player

As a best practice, quit VMware Player before you shut down the host computer.

To quit VMware Player

Choose **File > Exit** on Windows hosts or **File > Quit** on Linux hosts.

Depending on the configured exit behavior, the ACE instance is suspended or shuts down and the window closes.

Also depending on the configuration, end users might be able to change the exit behavior in the Preferences dialog box (**File > Preferences**).

Troubleshooting Tools

VMware ACE includes some troubleshooting tools that allow administrators and help desk assistants to fix some common problems that users have with ACE instances, such as forgotten user passwords. The tools are:

- For standalone ACE instances:
 - The ACE Tools, which is a command-line tool. See [“Using the vmware-acetool Command-Line Tool”](#) on page 479.
 - The hot fix feature, which users access from buttons in dialog boxes. See [“Respond to Hot Fix Requests”](#) on page 481.
- For managed ACE instances, see the *VMware ACE Management Server Administrator’s Guide*.

Using the vmware-acetool Command-Line Tool

The `vmware-acetool` command-line tool is a troubleshooting tool that enables ACE administrators to fix a limited set of problems for standalone ACE instances directly on an ACE user’s system.

You can provide the following solutions with `vmware-acetool`:

- Set the user’s password, so the user can run the ACE instance.
- Set copy protection, so the user can run the ACE instance in a new location.
- Set the expiration date, so the user can continue to use an ACE instance that is past its scheduled expiration date.

The configuration file (.vmx file) for the ACE instance must be on the ACE user's machine. That is, you cannot use `vmware-acetool` to make fixes to files associated with the instance unless the configuration file is on the same machine as those files.

You can actually use the `vmware-acetool` program to reset passwords and fix expiration dates on another machine, but you must have the .vmx, .vmp1, and ace.dat files from the user all set up in the same directory. The following is an example of a `vmware-acetool` command:

```
vmware-acetool <command> <ACEconfigurationfile> <parameters>
```

Table 22-2. Commands and Parameters for `vmware-acetool`

Command	Parameters	Description
setPassword	Path to recovery key file	Set the ACE instance's password.
setExpirationDate	New expiration date	Set the ACE instance's expiration date.
allowCopy		Allow the ACE instance to run from its current location.
updateCurrentTime		Update the internal policy clock of an ACE instance to the current time.
cloneToVM	Net clone configuration file Path to recovery key file	Clone a regular virtual machine from an ACE-enabled virtual machine.

Password Prompts

All commands prompt for the administrative tools password. See [“Setting Administrator Mode Policies”](#) on page 419.

The `setPassword` command also prompts for the recovery key password for the private recovery key file, a new ACE instance password, and confirmation of that new password. See [“Set a Recovery Key for Encrypted ACE Instances”](#) on page 396. Following is an example of the command:

```
vmware-acetool setPassword myACE.vmx recKey.priv
```

Expiration Dates

The new expiration date can be passed as one of the following:

- A number of days from the current date
- An absolute date in the format YYYY-MM-DD
- A start date and an end date in the format YYYY-MM-DD YYYY-MM-DD
- The special value "never", so that the instance never expires
- The special value "expired", so that the instance expires immediately

Following are examples of the command:

```
vmware-acetool setExpirationDate myACE.vmx 30
```

```
vmware-acetool setExpirationDate myACE.vmx 2007-06-16
```

```
vmware-acetool setExpirationDate myACE.vmx "never"
```

```
vmware-acetool allowCopy myACE.vmx 30
```

Respond to Hot Fix Requests

If you enable the hot fix feature for standalone ACE instances, users can easily request help to resolve the following problems:

- Lost or forgotten password
- Expired ACE instance
- Copy-protected ACE instance run from a new location

For information about enabling the hot fix feature, see [“Setting Hot-Fix Policies for Standalone ACE Instances”](#) on page 421. For information about setting a recovery key, which you must have to send a hot fix for a lost or forgotten user password, see [“Set a Recovery Key for Encrypted ACE Instances”](#) on page 396.

When the hot fix feature is enabled, if an end user sees a notification that the ACE instance is expired or copy protected, a **Request Hot Fix** button appears in the dialog box. The user clicks this button, which launches the Hot Fix Request wizard. This wizard generates a hot fix request file. The user can submit this file to the administrator as an email attachment or in some other way.

To respond to a hot fix request

- 1 When you receive the hot fix request file, save it to a location that you can access from the administrator machine where Workstation is installed.
- 2 Open the ACE-enabled virtual machine for the instance that requires the hot fix.
- 3 Choose **File > Open**.
- 4 Navigate to the location of the hot fix request file and click **Open**.

A hot fix tab opens in the Workstation window. The hot fix tab displays the user's name and email address, the problem that led to the hot fix request, and any additional note the user entered.

- 5 Click **Approve hot fix**.
- 6 Enter the appropriate information in the dialog box.
- 7 Select one of the following methods for sending the response:
 - Click **Send hot fix** on the hot fix tab and click **OK**.
 - Send the hot fix file. It is in the same folder as the hot fix request. The file extension for the fix file is `.vmhf`.

The display on the hot fix tab shows the status of the hot fix request, approved or denied, and the date on which you took action.

The user applies the hot fix by double-clicking the hot fix file.

Troubleshooting Setup Issues

Occasionally ACE end users have problems logging in to a domain after running the **Revert to Reimage Snapshot** command. They might sometimes also have problems with domain validation and name resolution.

Login Issues After Reverting to a Reimage Snapshot

Problem: The ACE user cannot log the ACE instance back in to a domain after choosing **VM > Snapshot > Revert to Reimage Snapshot**.

Description: The ACE instance has a Windows guest operating system installed and the machine account password for the domain is periodically renewed by default. If the password is renewed by the time the user reverts the ACE instance to the snapshot, the snapshot's password is invalid and login fails.

Solution: To avoid this problem, ensure that the following security policy is enabled: **Refuse machine account password changes**.

You can enable this policy on the ACE-enabled virtual machine (affecting all instances created from it) or on the primary domain controller. For details about how to change the policy, see the following Microsoft articles:

- **Local Security Policies** – Go to the Microsoft Support site, enter the Microsoft knowledge base article ID 175468 in the search criteria, and click the first search result.
- **PDC Security Policies** – Go to the Microsoft TechNet Web site and enter Domain controller: Refuse machine account password changes, in the search criteria.

Issues with Domain Validation or Name Resolution

Problem: When you try to join an ACE-enabled virtual machine to a domain, domain validation or name resolution does not work.

Description: Some ACE-enabled virtual machines with certain network configurations might demonstrate these problems.

Solution: Consult the Microsoft knowledge base article. Go to the Microsoft Support Web site, enter the Microsoft knowledge base article ID 314108 in the search criteria, and click the first search result.

Issues with Domain Joins for Windows Vista and Windows 7 Guests

Problem: The Windows Vista and Windows 7 ACE instances cannot join the local domain and instance customization failed with the message “NetDomainJoin function Error 1722: Could not join domain.”

Description: Windows Vista and Windows 7 ACE instances might have this problem.

Solution: Tell the user to power off the instance and power it on again to retry instance customization. The problem is intermittent and restarting might solve the problem.

Appendix: Workstation Command-Line Reference

This appendix discusses the command-line options that are available for the `vmware` program.

For information about using the `vmware-fullscreen` command to use full screen switch mode, see [“Using vmware-fullscreen to Run a Virtual Machine”](#) on page 377.

For information about using the `vmrun` program to operate teams or virtual machines from the command line, see manual called *Using vmrun to Control Virtual Machines*.

This appendix includes the following topics:

- [“Startup Options for Workstation and Virtual Machines”](#) on page 485
- [“Using Startup Options in a Windows Shortcut”](#) on page 487

Startup Options for Workstation and Virtual Machines

[Table A-1](#) describes options available when you run Workstation from the command line. You can type these commands in a Linux terminal window or at the Windows command prompt. You can also create scripts to run multiple commands.

The syntax for this command is:

- On a Linux host operating system:

```
/usr/bin/vmware [-n] [-x] [-X] [-m] [-t] [-q] [-s <variablename>=<value>]
                [-v]
                [/<path_to_virtual_machine>/<virtual_machine_name>.vmx]
                [X toolkit options]
```

- On a Windows host operating system:

```
C:\Program Files\VMware\VMware Workstation\vmware.exe [-B] [-n] [-x] [-X]
[-t] [-q] [-s <variablename>=<value>] [-v]
[<path_to_virtual_machine>\<virtual_machine_name>.vmx]
```

Table A-1. Command-Line Options for the vmware Program

Option	Description
-n	Opens a new Workstation window.
-B	(Windows hosts only) Opens a new Workstation window but hides the sidebar and toolbars. Only the tabs of open virtual machines are shown. Using this option has the same effect as clicking the Workstation icon in the upper-left corner of the Workstation window and choosing Hide Controls from the menu that appears.
-t	Opens a virtual machine or team in a new tab in the existing Workstation window.
-x	Powers on the virtual machine when Workstation starts. This is equivalent to clicking the Power On button in the Workstation toolbar.
-X	Powers on the virtual machine and switches the Workstation window to full screen mode.
-m	Starts the program in quick switch mode.
-q	Closes the virtual machine's tab when the virtual machine powers off. If no other virtual machine is open, it also exits Workstation. This option is useful when the guest operating system can power off the virtual machine.
-s	Sets the specified variable to the specified value. Any variable names and values that are valid in the configuration file can be specified on the command line with the -S switch.
-v	Displays the product name, version, and build number.
<path_to_VM_or_team>	Launches a virtual machine by using the specified virtual machine or team configuration file (.vmx or .vmtm file).

On Linux hosts, X toolkit options can be passed as arguments, although some of them (most notably the size and title of the Workstation window) cannot be overridden.

X toolkit options are not relevant on a Windows host.

Using Startup Options in a Windows Shortcut

The most convenient way to use the startup options is to incorporate them into the command that a Windows shortcut generates.

To create the shortcut, right-click the shortcut and click **Properties**. In the **Target** field, add any switches to use after the `vmware.exe` filename. For example, the following command launches the Windows Me virtual machine specified, powers it on, and switches to full screen mode:

```
"C:\Program Files\VMware\VMware Workstation\vmware.exe -X C:\Documents and  
Settings\<username>\My Documents\My Virtual Machines\Windows  
Me\Windows Me.vmx"
```

Enclose the entire command string in quotation marks. The configuration file has a `.vmx` extension by default.

Glossary

B **bridged networking**

A type of network connection between a virtual machine and the host's physical network. With bridged networking, a virtual machine appears as an additional computer on the same physical network as the host. *See also* [host-only networking](#).

C **clone**

A duplicate of a virtual machine. *See also* [full clone](#), [linked clone](#).

custom networking

Any type of network connection between virtual machines and the host that does not use the default bridged, host-only, or network address translation (NAT) networking configurations. For instance, different virtual machines can be connected to the host by separate networks or connected to each other and not to the host. Any network topology is possible.

D–E **disk mode**

A property of a virtual disk that defines its external behavior (how the virtualization layer treats its data) but is completely invisible to the guest operating system. Available modes include persistent mode (changes to the disk are always preserved across sessions), nonpersistent mode (changes are never preserved), and undoable mode (changes are preserved at the user's discretion).

F **Favorites list**

A list in the left panel of the main Workstation window that shows the names of virtual machines that a user has added. You can use the **Favorites** list to launch a virtual machine or to connect to the virtual machine's configuration file and make changes in the virtual machine settings.

full clone

A complete copy of the original virtual machine, including all associated virtual disks. *See also* [linked clone](#).

full screen mode

A display mode in which the virtual machine's display fills the entire screen. *See also* [full screen switch mode](#).

full screen switch mode

A display mode in which the virtual machine's display fills the entire screen, and the user has no access to the Workstation user interface. The user cannot create, reconfigure, or launch virtual machines. A system administrator performs those functions. *See also* [full screen mode](#).

G**Go to Snapshot**

A command that allows you to restore any snapshot of the active virtual machine. *See also* [Revert to Snapshot](#).

guest operating system

An operating system that runs inside a virtual machine. *See also* [“host operating system”](#) on page 490.

H–K**host-only networking**

A type of network connection between a virtual machine and the host. With host-only networking, a virtual machine is connected to the host on a private network, which normally is not visible outside the host. Multiple virtual machines configured with host-only networking on the same host are on the same network. *See also* [bridged networking](#), [custom networking](#).

host

The physical computer on which the VMware Workstation software is installed.

host operating system

An operating system that runs on the host machine. *See also* [guest operating system](#).

independent disk

A type of virtual disk that is not affected by snapshots. You can configure independent disks in persistent and nonpersistent modes. *See also* [nonpersistent mode](#), [persistent mode](#), [snapshot](#).

L–M LAN segment

A private virtual network that is available only to virtual machines within the same team. *See also* [virtual network](#), [team](#).

linked clone

A copy of the original virtual machine that must have access to the parent virtual machine's virtual disks. The linked clone stores changes to the virtual disks in a separate set of files. *See also* [full clone](#).

N–O nonpersistent mode

A disk mode in which all disk writes issued by software running inside a virtual machine appear to be written to the independent disk but are in fact discarded after the virtual machine is powered off. As a result, a virtual disk or physical disk in independent-nonpersistent mode is not modified by activity in the virtual machine. *See also* [disk mode](#), [persistent mode](#).

P parent

The source virtual machine from which you take a snapshot or make a clone. A full clone has no continued link to its parent, but a linked clone and a snapshot must have access to the parent's virtual disk files. If you delete the parent virtual machine, any linked clone or snapshot becomes permanently disabled. To prevent deletion, you can make the parent a template virtual machine. *See also* [full clone](#), [linked clone](#), [snapshot](#).

persistent mode

A disk mode in which all disk writes issued by software running inside a virtual machine are immediately and permanently written to a virtual disk that has been configured as an independent disk. As a result, a virtual disk or physical disk in independent-persistent mode behaves like a conventional disk drive on a physical computer. *See also* [disk mode](#), [nonpersistent mode](#).

physical disk

A hard disk in a virtual machine that is mapped to a physical disk drive or partition on the host machine. A physical disk is also referred to as a raw disk. A virtual machine's disk can be stored as a file on the host file system or on a local hard disk. When a virtual machine is configured to use a physical disk, Workstation directly accesses the local disk or partition as a physical device (not as a file on a file system). *See also* [virtual disk](#).

Q quick switch mode

A display mode in which the virtual machine's display fills most of the screen. In this mode, tabs at the top of the screen allow you to switch quickly from one running virtual machine to another. *See also* [full screen mode](#).

R raw disk

See [physical disk](#).

record/replay feature

This feature lets you record all of a Workstation 5.x or 6.x virtual machine's activity over a period of time. Unlike Workstation's movie-capture feature, the record/replay feature lets you exactly duplicate the operations and state of the virtual machine throughout the time of the recording.

redo log

The file that stores changes made to a disk in all modes except the persistent and independent-persistent modes. For a disk in nonpersistent mode, the redo-log file is deleted when you power off or reset the virtual machine without writing any changes to the disk. You can permanently apply the changes saved in the redo log to a disk in undoable mode so that they become part of the main disk files. *See also* [disk mode](#).

Revert to Snapshot

A command that restores the status of the active virtual machine to its immediate parent snapshot. This parent is represented in the snapshot manager by the snapshot appearing to the immediate left of the **You Are Here** icon. *See also* [Go to Snapshot](#), [snapshot manager](#).

S shared folder

A folder on a host computer—or on a network drive accessible from the host—that can be used by both the host and one or more virtual machines. It provides a way of sharing files between host and guest or among virtual machines. In a Windows virtual machine, shared folders appear as folders on a drive letter. In a Linux or Solaris virtual machine, shared folders appear under a specified mount point.

snapshot

A reproduction of the virtual machine just as it was when you took the snapshot, including the virtual machine's power state (on, off, or suspended). If the virtual hard disks are not set to independent mode, a snapshot also includes the state of the data on all the virtual machine's disks. You can take a snapshot when a virtual machine is powered on, powered off, or suspended. *See also* [independent disk](#).

snapshot manager

A control panel used to take actions on any of the snapshots and recordings associated with the selected virtual machine. *See also* [record/replay feature](#), [snapshot](#).

T–U team

A group of virtual machines that are configured to operate as one object. You can power on, power off, and suspend a team with one command. You can configure a team to communicate independently of any other virtual or real network by setting up a LAN segment. *See also* [LAN segment](#), [virtual network](#).

Unity mode

A display mode in which a virtual machine's applications are displayed in application windows directly on the host's desktop. The virtual machine console view is hidden, and you can minimize the Workstation window. In this mode, a virtual machine's applications look just like other application windows on the host.

V–X virtual disk

A file or set of files that appears as a physical disk drive to a guest operating system. These files can be on the host machine or on a remote file system. *See also* [physical disk](#).

virtual hardware

The devices that make up a virtual machine. The virtual hardware includes the virtual disk, removable devices such as the DVD-ROM/CD-ROM and floppy drives, and the virtual Ethernet adapter. You configure these devices with the virtual machine settings editor. *See also* [virtual machine settings editor](#).

virtual machine

A virtualized x86 PC environment in which a guest operating system and associated application software can run. Multiple virtual machines can operate on the same host machine concurrently.

virtual machine configuration

The specification of which virtual devices, such as disks and memory, are present in a virtual machine and how they are mapped to host files and devices.

virtual machine configuration file

A file containing a virtual machine configuration. This `.vmx` file is created when you create the virtual machine. It is used to identify and run a specific virtual machine.

virtual machine settings editor

A point-and-click control panel used to view and modify a virtual machine's settings.

virtual network

A network connecting virtual machines that does not depend on physical hardware connections. For example, you can create a virtual network between a virtual machine and a host that has no external network connections. You can also create a LAN segment for communication between virtual machines on a team. *See also* [LAN segment](#), [team](#).

virtual network editor

A point-and-click editor used to view and modify the networking settings for the virtual networks created by Workstation.

VMware Player

Free software that enables PC users to create and run any virtual machine on a Windows or Linux PC. VMware Player runs virtual machines created by VMware Workstation, VMware Server, or ESX Server and also supports Microsoft virtual machines and Symantec Backup Exec System Recovery disk formats.

VMware Tools

A suite of utilities and drivers that enhances the performance and functionality of your guest operating system. Key features of VMware Tools include some or all of the following, depending on your guest operating system: an SVGA driver, a mouse driver, the VMware Tools control panel and support for such features as shared folders, drag-and-drop in Windows and Linux guests, shrinking virtual disks, time synchronization with the host, VMware Tools scripts, and connecting and disconnecting devices while the virtual machine is running. *See also* [shared folder](#).

Index

Numerics

3D support **173**

A

About tab

 VMware Tools **123**

access control policies, ACE **391, 397**

ACE instance

 defined **383**

 installing on a Linux host **470**

 installing on a Windows host **466**

 offline usage **421**

 removable device policy **411**

 running a Pocket ACE **463**

 setting policies for **390**

 uninstalling from a Linux host **473**

 uninstalling from a Windows
 host **468**

 upgrading **473**

ACE Management Server

 and Active Directory **397**

 defined **383**

ACE New Package wizard **449**

ACE Resources directory **446**

ACE tools, using **479**

ACE-enabled virtual machine

 configuring **447**

 creating packages for **450**

 defined **383**

 deployment platform **446**

ACPI S1 sleep feature **380**

activation policy, ACE **391**

Active Directory

 password change proxying **397**

adapter

 host virtual adapters **301, 410**

 in promiscuous mode on a Linux
 host **316**

 specifying physical, for ACE **410**

 virtual Ethernet **295**

Add Hardware wizard **332, 363**

Add Shared Folder wizard **191**

address

 assigning IP **305**

 assigning MAC manually **309**

 IP on virtual network **304**

 MAC **308**

 network address translation **316**

 using DHCP to assign **304**

administrative tools policy, ACE **419**

Advanced Linux Sound Architecture,
 using **176**

ALSA *See* Advanced Linux Sound
 Architecture

AMD Athlon 64 processor **37**

AMD Opteron processor **37**

AMD Sempron processor **37**

AMD Turion 64 processor **37**

appliance view

 for virtual machines **182**

 policy for ACE instances **415**

assign

 IP address **304**

 network port number in NAT **323**

- Athlon 64 processor **37**
- audio **32, 175, 176**
- AudioPCI **176**
- authentication policy, ACE **391**
- autofit settings **164**
- automatic bridging **297, 410**
- AutoProtect
 - restrictions **214**
 - setting up **215**
- AutoProtect feature
 - See also* snapshot, AutoProtect **214**

B

- background, running virtual machines
 - in **71, 264**
- bandwidth
 - controlling, in team networks **271**
 - LAN segment **281**
- battery information, reporting in
 - guest **180**
- BIOS
 - file in virtual machine **97**
 - provided in virtual machine **30**
 - setup, entering **148**
- .bmp files for screen captures **183**
- bridged networking
 - ACE policy for network
 - adapters **410**
 - and Samba servers **329**
 - configuring options **297**
- browser
 - and appliance views **182**
 - configuring on Linux host **45**
- BSD
 - supported 32-bit guest operating
 - systems **36**
 - supported 64-bit guest operating
 - systems **36**
- BT/KT-958 drivers **86**

- bulkDeploy.exe program **462**
- bundle installer for Workstation **45**
- BusLogic **30, 362**

C

- capacity, disk **236, 249**
- capture
 - screenshot **183**
 - snapshot of virtual machine **203**
 - virtual machine activity **257**
- CD
 - adding drive to virtual machine **250**
 - CD-ROM image file **30**
 - legacy emulation mode for **252**
 - package delivery for ACE **453**
- .cfg file **97**
- change
 - hot-key combinations **74**
 - team name **274**
 - virtual machine name **65**
- Change Version wizard **94**
- clock
 - real-time on Linux host **44**
 - synchronize guest and host **120**
- clone template **221**
- Clone Virtual Machine wizard **222**
- clones
 - creating, for teams **272, 276, 283**
 - creating, in Clone Virtual Machine
 - wizard **221**
 - enable template mode **221**
 - full **220**
 - IP address **222**
 - linked **220, 227**
 - MAC address and UUID of **219**
 - network identity of **222**
 - overview **219**
 - static IP address **222**

- color
 - display on VNC clients **228**
 - screen, in a virtual machine **172**
- comm port
 - See serial connection, serial port
- command-line interface
 - for VMware Tools **132**
 - for Workstation **485**
- commands
 - keyboard shortcuts **72**
 - startup, on the command line **378**, **485**
 - startup, on Windows hosts **487**
- compacting virtual disks **240**
- configure record/replay **259**
- connect
 - CD/DVDs and floppies to ISO images **253**
 - USB devices **353**
- Conversion wizard **133**, **142**, **143**
- converting virtual machines **133**
- copy and paste feature **189**
- copy protection policy for ACE
 - instances **400**
- copy virtual machine **225**
- CPU
 - host requirement **23**
 - provided in virtual machine **29**
- creating
 - ACE packages **449**
 - policies for an ACE instance **390**
 - virtual disks **242**
- Creative Labs **176**
- Creative Labs Sound Blaster **32**
- Ctrl+Alt hot-key combination **340**
- custom EULA ACE package setting **445**

D

- DDNS (dynamic domain name service) **311**
- debugging
 - using serial connection **338**
- default scripts for VMware Tools **125**
- defragmenting virtual disks **239**
- deleting
 - recordings of virtual machine activity **212**, **268**
 - snapshots **208**, **212**
 - virtual machines **158**
- deploy.exe program **461**
- deployment settings, ACE
 - deployment platform **446**
 - encryption **436**
 - EULA **445**
 - instance customization **437**
 - package lifetime **436**
- destinations for imported virtual machines **140**
- device connection policy **411**
- device drivers
 - for generic SCSI devices **363**
 - VMware Tools **102**
- devices
 - ACE policies for USB **412**
 - adding a generic SCSI device **363**, **364**
 - connecting and disconnecting **122**, **181**
 - disconnecting from USB controller **357**
 - processor **29**
 - removable, ACE policies for **411**
 - USB **351**
- Devices tab
 - in Preferences dialog box **67**
 - VMware Tools **122**

DHCP

- assigning IP addresses on a virtual network **304**
- changing settings **300**
- configuring on a Linux host **306**
- configuring on a Windows host **306**
- DHCPD **311**
- lease **300**
- on a virtual network with NAT **317**
- server **286, 300**
- server on virtual network **290, 291**
- stopping **314**

dial-up connection 306**directories, shared 195, 196****disable**

- acceleration **179**
- copying and pasting text and files **190**
- drag-and-drop of files and folders **188**
- folder sharing **192**
- interface features **369**

disc labels for packages 453**disk**

- See also* virtual disk
- IDE drive supported in host **24**
- IDE drives in virtual machine **30**
- independent **207**
- mapping to a drive **199**
- optical drives supported in host **25**
- SCSI drive supported in host **24**
- size **236, 249**
- space required on host computer **24**
- .vmdk virtual disk file **97**

display

- autofit settings for **164**
- color depth **172**
- fitting window to virtual machine **169**
- full screen **162, 164**

multiple monitor 166, 169

- requirements on hosts **24**
- switching virtual machines **165**

Display tab in preferences editor 169**distributing ACE packages 449****DMZ 271****DNS**

- on a NAT network **318**
- setup issues, troubleshooting **482**

domain join, remote 443**domain problems 482**

- domain setting, in ACE instance customization **440**

downgrading virtual machines 94**download components 153****drag-and-drop feature 187****dragging and dropping**

- images, text, and file contents between host and guest **188**

drivers

- SCSI **362**
- sound **176**
- video, in older versions of Windows **105**

drives

- CD/DVD-ROM **30, 250**
- floppy **31, 250**
- IDE **30**
- tape **361**
- virtual IDE **242**
- virtual SCSI **242**

dual-boot computers and virtual machines 254**dual-monitor display 166, 169****DVD**

- adding drive to virtual machine **250**
- legacy emulation mode for **252**

- optical, supported **25**
- package delivery for ACE **453**
- dynamic domain name service **311**

E

- Eclipse
 - installing the Workstation plug-in for **41**
- EHCI controller **31**
- EM64T processor **37**
- encrypt
 - restrictions **156**
- encrypting a virtual machine **155**
- encryption for ACE packages and instances **436**
- enhanced virtual keyboard **339, 416**
- Ethernet adapter
 - adding to virtual machine **295**
 - for teams **282**
 - promiscuous mode **316**
 - virtual network adapters **286**
- Ethernet controller **25**
- Ethernet switches **32**
- exclusive mode **165**
- expand
 - virtual disk **240**
- expiration policy for ACE instances **399**

F

- Favorites list
 - creating folders in **64**
 - overview **63**
 - removing virtual machines from **64**
- files
 - BIOS in virtual machine **97**
 - redo log **97**
 - Samba and file sharing on a Linux host **328**
 - sharing among virtual machines and host **187**

- snapshot **97**
- suspended state **97**
- used by a virtual machine **97**
- used by snapshot **97**
- virtual machine **150**
- firewall **324**
- fit to guest and fit to window **169**
- floppy
 - drives in virtual machine **31, 252**
 - image file **31, 253**
- folders
 - in the Favorites list **64**
 - shared, *See* shared folder
- FreeBSD
 - supported 32-bit guests **36**
 - supported 64-bit guests **36**
 - VMware Tools for **112**
- FTP **318**
- full screen mode **162**
- full screen settings **164**
- full screen switch mode **372, 379**
- full screen toolbar **164, 415**

G

- gated host network **310**
- global configuration file **372**
- graphics
 - See also* display
 - support in virtual machine **30, 172**
- guest
 - autofit **169**
 - defined **22**
 - fit command **169**
- guest network access policies, ACE **402, 411**
- guest operating system
 - for ACE instance customization **439**
 - installing **91**
 - support for 64-bit **37**

- supported **32**
- supported FreeBSD 32-bit **36**
- supported FreeBSD 64-bit **36**
- supported Linux 32-bit **35**
- supported Linux 64-bit **36**
- supported MS-DOS **33**
- supported Solaris 32-bit **36**
- supported Solaris 64-bit **36**
- upgrades **94**
- Windows 32-bit **33**
- Windows 64-bit **34**
- GUID Partition Table (GPT) disks **139**

H

- Hardware tab in virtual machine settings editor **69**
- headless virtual machines (run in the background) **71, 264**
- HIDs (human interface devices) **353**
- host
 - defined **22**
 - hard disk space required **24**
 - network access policies, ACE **411**
 - optical drives supported **25**
 - policies, ACE **402, 466**
 - system requirements **23**
 - virtual adapters **301**
- host-guest data script policies **397**
- host-only networking
 - basic configuration **290**
 - selecting IP addresses **304**
- hot fix, ACE
 - policies **421**
 - responding **481**
- hot keys
 - for full screen switch mode **373, 375**
 - hexadecimal values for **373**
 - in Workstation preferences **340**

- setting **74**
- using Ctrl+Alt+Insert and Ctrl+Alt+Delete **72**
- Hot Keys tab **67**

I

- ICMP **318**
- IDE
 - drive supported in host **24**
 - drives in virtual machine **30**
 - optical drive supported in host **25**
- IDESCSI, setting up virtual disk as **237**
- image file
 - floppy **31, 253**
 - ISO **30, 250, 253**
- import **145**
- importing virtual machines **133, 135**
- independent disk **207**
- initialization scripts for instance customization **440**
- install components **153**
- install ESX 4.0 and ESXi 4.0 on Workstation **90**
- installation requirement
 - ESX 4.0 and ESXi 4.0 **90**
- installing
 - ACE instance on a Linux host **470**
 - ACE instance on a Windows host **466**
 - guest operating systems **91**
 - Pocket ACE on portable device **461**
 - software in a virtual machine **179**
 - VMware Player on a Linux host **469**
 - VMware Tools silently on Windows guests **106**
 - Workstation on Linux host **44**
 - Workstation on Windows host **41**
 - Workstation silently on Windows hosts **42**

- instance customization, ACE
 - deployment settings for **440**
 - guest operating systems for **439**
 - initialization scripts **440**
 - Microsoft Sysprep deployment tools for **439**
 - package settings, overview **437**
 - packages with **453**
 - placeholder values **442**
 - specifying license information for Windows servers **443**
 - workgroup or domain setting **440**
- Intel EM64T processor **37**
- IP address
 - assigning **305**
 - clone **222**
 - static **305**
- IP packet forwarding **307**
- ISO image file **30, 250, 253**

K

- Kbps, for LAN segment **281**
- kernel
 - paravirtual, support for **93**
- key code mapping **345**
- keyboard
 - enhanced virtual, ACE policy **416**
 - enhanced virtual, on Windows **339**
 - language keymaps for VNC clients **341**
 - mapping on a Linux host **342**
 - shortcuts **72, 158**
 - USB **351**
- keyloggers **416**
- keysym
 - defined **344**
 - mapping **345**
- kiosk mode, ACE
 - policies **420**

- preparing Linux hosts for **472**
- starting multiple virtual machines in **476**
- startup behavior **475**

L

- LAN segments
 - and teams **280**
 - changing name **281**
 - configuring connections to **282**
 - deleting **283**
 - setting bandwidth **281**
 - setting Kbps **281**
 - setting packet loss **281**
- leaks, IP packet **306**
- legacy emulation for DVD/CD-ROM drives **252**
- licensing, serial number and **474**
- linked clones **227**
- Linux
 - 32-bit host **27**
 - 64-bit host **27**
 - installing on Linux host **44**
 - supported 32-bit guest operating systems **35**
 - supported 64-bit guest operating systems **36**
 - supported host operating systems **27**
 - uninstalling Workstation on Linux host **47**
 - upgrading on Linux host **51**
- LiveState system image, importing **135**
- local area networking **25**
- location of virtual machine files **83, 150**
- lock files **236**
- log files **97, 379**
- LSI Logic **30, 86, 362**

M

- MAC address
 - and clones **219**
 - assigning manually **309**
 - of virtual Ethernet adapter **308**
- map
 - key code **345**
 - keyboard **342**
 - keysym **345**
- mapped drives, for virtual disks **198**
- mapping virtual disks to a drive **199**
- master boot record (MBR) disks **139**
- memory
 - amount required on host **23**
 - settings **415**
- Microsoft Sysprep deployment tools **440**
- MIDI **175**
- mode
 - exclusive **165**
 - full screen **162**
 - preview **448**
 - promiscuous **316**
 - quick switch **165**
 - Unity **158**
- modifier keys **373**
- monitors
 - specifying the number of **166, 169**
 - using multiple **166, 169**
- mouse
 - driver, installed by VMware Tools **102**
 - USB **351**
- movie capture **184**
- moving a virtual machine **223**
- MP3 **175**
- MS-DOS **33**
- multiple monitors, using **166, 169**
- Mylex **30, 86, 362**

N

- name
 - changing team name **274**
 - changing virtual machine name **65**
- NAT
 - ACE policies for **409**
 - advanced configuration **319**
 - and DHCP **317**
 - and DNS **318**
 - and the host computer **317**
 - external access from a NAT network **318**
 - on virtual network **289, 316**
 - port forwarding **323, 328**
 - sample configuration file for Linux host **327**
 - selecting IP addresses **304**
 - specifying connection from port below 1024 **320**
- NAT.conf file **321, 327**
- NetLogon **324**
- NetWare, Novell **36, 113, 123**
- network
 - adding and modifying virtual Ethernet adapters **295**
 - automatic bridging **297**
 - automatic bridging for ACE instances **410**
 - changing DHCP settings **300**
 - changing subnet settings **300**
 - changing the configuration **295**
 - components **285**
 - configuring bridged networking options **297**
 - DHCP **304**
 - DHCP server **286**
 - dial-up connection **306**
 - dynamic domain name service **311**
 - hardware address **308**

- host-only **290**
 - host-only subnet **304**
 - identity, clone **222**
 - IP forwarding **307**
 - IP packet leaks **306**
 - MAC address **308**
 - NAT **289, 316**
 - NAT as firewall **324**
 - NAT subnet **304**
 - packet filtering **307**
 - promiscuous mode on a Linux host **316**
 - routing between two host-only networks **314**
 - Samba **328**
 - second bridged network on a Linux host **299**
 - switch **285**
 - token ring **289**
 - two host-only networks **302**
 - virtual DHCP server **290, 291**
 - virtual Ethernet adapter **286**
 - virtual network editor **297, 301, 306**
 - virtual switch **285**
 - virtualizing in a team **271**
 - network access policies, ACE **402, 410**
 - network adapters
 - creating, for team networks **282**
 - virtual, adding **295**
 - virtual, overview of **286**
 - network image package delivery for ACE **453**
 - New Package wizard **449**
 - New Virtual Machine wizard **66, 80, 89, 235**
 - NFS ports **320**
 - Novell NetWare
 - supported guests **36**
 - VMware Tools for **113**
 - Novell Open Enterprise Server
 - supported guests **36**
 - NVRAM **97**
- ## O
- offline usage of ACE instances, policy **421**
 - Open Enterprise Server **36**
 - open virtual machine format (.ovf and .ova files) **137**
 - operating system
 - 32-bit Windows host **26**
 - 64-bit Windows host **26**
 - FreeBSD 32-bit guest **36**
 - FreeBSD 64-bit guest **36**
 - installing guest **91**
 - Linux 32-bit guest **35**
 - Linux 32-bit host **27**
 - Linux 64-bit guest **36**
 - Linux 64-bit host **28**
 - MS-DOS guest **33**
 - Solaris 32-bit guest **36**
 - Solaris 64-bit guest **36**
 - support for 64-bit guest **37**
 - Windows 32-bit guest **33**
 - Windows 64-bit **34**
 - Opteron processor **37**
 - optical drive supported in host **25**
 - Options tab
 - virtual machine settings editor **70**
 - VMware Tools **120**
 - .ovf and .ova files **137**
- ## P
- P2V (physical-to-virtual) conversion **133**
 - Package Properties dialog box **454**
 - package settings, ACE
 - custom EULA **445**
 - deployment platform **446**

- encryption **436**
 - instance customization **437**
 - package lifetime **436**
 - placeholder values in instance customization **442**
 - remote domain join **443**
 - workgroup or domain in instance customization **440**
- Packages tab **454**
- packages, ACE
 - burning files onto discs **453**
 - changing lifetime setting **436**
 - creating **449**
 - creation progress **453**
 - deployment for Pocket ACE **461**
 - deployment platform for **446**
 - disc labels for **453**
 - disk space required for **452**
 - distribution format **453**
 - Pocket ACE installation **461**
 - pre-deployment test for **455**
 - previewing before deployment **455**
 - registration **453**
 - testing before deployment **455**
 - viewing history of **454**
- packet
 - filtering **307**
 - leaks **306**
- packet loss, configuring, for LAN segments **281**
- parallel ports
 - configuring on a Linux host **333**
 - in a virtual machine **331**
 - installing in virtual machines **332**
- paravirtualized kernels in Linux guests **93**
- parent snapshot **204**
- pause
 - restrictions **154**
 - pause feature **154**
- physical disk
 - adding physical disks **244**
 - capacity **238**
 - storing virtual disks on **237**
 - using in a virtual machine **238**
- ping **318**
- placeholder values in instance customization **442**
- platform deployment settings, ACE **446**
- Player policy, ACE **415**
- plug-ins
 - writing, for ACE instances **424**
- .png files for screen captures **183**
- Pocket ACE
 - deleting the cache **468, 473**
 - deploying **461**
 - description **88, 457**
 - Disk Size Calculator **88**
 - installing on portable device **461**
 - instructions for running **463**
 - portable device requirements **459**
- Pocket ACE Deploy Utility dialog box **461**
- policies, ACE
 - access control **391**
 - activation **391**
 - administrative tools **419**
 - authentication **391**
 - copy protection **400**
 - device connection **411**
 - expiration **399**
 - host **402, 466**
 - host-guest data script **397**
 - hot fix **421**
 - kiosk mode **420**
 - network access **402**
 - Player runtime **415**
 - removable device **411**

- resource signing **401**
 - runtime preferences **415**
 - setting for an ACE instance **390**
 - snapshot **418**
 - update frequency **421**
 - USB device **412**
 - using scripts **424**
 - virtual printer policy **414**
 - policy editor, using **390**
 - policy update frequency, ACE **421**
 - port
 - TCP and UDP below 1024 **320**
 - VNC **228**
 - port forwarding **323, 328**
 - Power menu
 - disable functions **369**
 - using, for teams **280**
 - power off
 - snapshot options **213**
 - team **279**
 - Power Off button **152**
 - power on
 - a virtual machine **148**
 - team **279**
 - to BIOS **148**
 - Powered On list **65**
 - power-on script for ACE instances **394**
 - preferences
 - display **169**
 - hot keys **340**
 - setting, for Workstation **67**
 - VMware Tools upgrade options **115**
 - workspace **67**
 - Preview in Player icon **448**
 - preview mode, ACE **448, 455**
 - previewing ACE packages **455**
 - printers
 - ACE virtual printer policy **414**
 - using host printers in a virtual machine **180**
 - processor
 - host requirement **23**
 - provided in virtual machine **29**
 - supported for 64-bit guest **23, 37**
 - promiscuous mode **316**
 - publishing ACE policy changes **455**
- ## Q
- quick switch mode **165**
 - quiet mode, install VMware Tools **106**
 - quitting ACE Player **479**
- ## R
- RAM
 - amount required on host **23**
 - raw disk **238**
 - Real Media **175**
 - real-time clock requirement on Linux
 - host **44**
 - record/replay feature **257, 259**
 - recordings of virtual machine execution
 - deleting **212**
 - renaming **210**
 - .REDO file **97**
 - registration
 - of ACE packages **453**
 - of VMware Workstation **75**
 - reimage snapshots **418**
 - remote connections to a virtual machine **228**
 - remote domain join **443**
 - RemoteDisplay.vnc.keyMap
 - property **341**
 - removable devices
 - ACE policies for **411**
 - deploying Pocket ACE packages
 - to **461**
 - disconnecting **357**

- removable drive for Pocket ACE **461**
- removing
 - a virtual disk **243**
 - devices from a virtual machine **181**
- Repair option
 - for VMware Tools installations **105**
- repairing VMware Tools
 - installations **114, 118**
- Replay toolbar **261, 262**
- reporting problems to VMware **76**
- Reset button **152**
- resizing
 - Linux guests **170**
 - Solaris guests **171**
- resolution, screen **164**
- resource signing policy for ACE
 - instances **401**
- restricted user interface **369**
- resume
 - team **279**
 - virtual machine **201**
- reverting to snapshot **211**
- routing
 - between host-only networks **314**
 - host only **310**
- runtime preferences policy, ACE **415**

S

- Samba
 - and file sharing on a Linux host **328**
 - modifying configuration for
 - Workstation **328**
 - on both bridged and host-only
 - networks **330**
- scan code **344**
- scanner **361**
- screen captures **183**

- screen colors
 - for VNC clients **228**
 - setting, for virtual machines **172**
- screen modes
 - full screen **162**
 - quick switch **165**
- screen resolution **171**
- screenshot capture **183**
- screenshots **183**
- scripts
 - creating custom VMware Tools **126**
 - enabling, disabling, and
 - running **122**
 - for ACE instance customization **440**
 - power on, for ACE instances **394**
 - running and disabling **128**
 - running during power state
 - changes **125**
 - startup, for ACE kiosk mode **476**
 - writing, for ACE instances **424**
- Scripts tab in VMware Tools **122**
- SCSI
 - adding a generic SCSI device **363, 364**
 - avoiding concurrent access on a
 - Linux host **363**
 - connecting to generic **361**
 - devices in virtual machine **30**
 - drive supported in host **24**
 - driver for Windows NT guest **362**
 - driver for Windows Server 2003
 - guest **362**
 - driver for Windows XP guest **362**
 - drivers **86, 362**
 - generic SCSI on a Linux host **363**
 - generic SCSI on a Windows
 - host **361**

- optical drives **25**
- permissions for a generic SCSI device on a Linux host **361**
- setting up virtual disk as **237**
- Sempron processor **37**
- serial connection
 - between host application and virtual machine **335**
 - between two virtual machines **335**
 - for debugging **338**
 - to a serial port on the host **335**
- serial number
 - for ACE instances **474**
- serial port, installing and using **335**
- server
 - DHCP **286, 306, 317, 324**
 - DNS **311, 317, 318, 319**
 - WINS **319**
- setting up AutoProtect **215**
- share
 - files on a Linux host with Samba **328**
- shared folder
 - enable and disable **192**
 - mounting, on Linux **196**
 - on Linux and Solaris guests **196**
 - permissions on Linux **196**
 - using **190**
 - viewing **195**
- sharing virtual machines **227**
- shortcuts, keyboard **67, 72, 340**
- shrink
 - virtual disks **123, 240**
 - virtual disks in Netware **123**
- Shrink tab, VMware Tools **123**
- sidebar panel **62**
- size
 - disk **236, 249**
 - virtual disk **30**
- sleep, ACPI **380**
- smart cards in virtual machines **358**
- SMP
 - See virtual SMP
- snapshot **215**
 - and Workstation 4 virtual machines **215**
 - as background activity **206**
 - AutoProtect **214**
 - deleting **208, 212**
 - disabling menu functions **369**
 - excluding virtual disks from **207**
 - files **97**
 - linear process **203**
 - parent **204**
 - policies **418**
 - power-off options **213**
 - preserving AutoProtect **215**
 - process tree **204**
 - renaming **208, 210**
 - restoring **211**
 - reverting to **211**
 - reverting to at power off **211**
 - taking **209**
 - team **283**
 - using **203**
- snapshot manager **208**
- Solaris
 - resizing guests **171**
 - supported 32-bit guest operating systems **36**
 - supported 64-bit guest operating systems **36**
 - VMware Tools for **111**
- sound
 - configuring **175**
 - drivers for Windows 9x and NT guests **176**

- Sound Blaster **176**
 - support in guest **32**
- .spf file, importing **135**
- starting
 - ACE Player **474, 475**
 - Workstation **53**
- startup commands
 - used by VMware Tools **130**
- startup scripts
 - for ACE kiosk mode **476**
 - using VMware Tools **129**
- static IP addresses
 - clone **222**
 - range of **317**
- .std file **97**
- stopping
 - ACE Player **479**
 - recording virtual machine activity **264**
- StorageCraft images, importing **135**
- streaming virtual machines **149, 230**
- stretch guest display setting **164**
- subnet
 - changing settings **300**
 - in NAT configuration **304**
 - on host-only network **304**
- substring matching, for configuring which physical network adapter to use **410**
- Sun Solaris
 - supported 32-bit guest operating systems **36**
 - supported 64-bit guest operating systems **36**
- support scripts, running **76**
- suspend
 - files **97**
 - team **279**
 - virtual machine **201**

- .sv2i file, importing **135**
- SVGA drivers
 - installing, in older Windows guests **105**
- switch
 - virtual network **285**
 - workspaces in Linux guest **340**
- symmetric multiprocessing
 - See virtual SMP
- system requirements **23**
 - for guests **32**
 - host **23**

T

- tabs
 - in Preferences dialog box **67**
 - in VMware Tools control panel **119**
 - virtual machine **54**
- tape drive **361**
- .tar file for installing VMware Tools **109**
- team
 - adding virtual machine to **276**
 - and LAN segments **280**
 - cloning virtual machine from **283**
 - closing **274**
 - creating clone in New Team wizard **272, 276**
 - deleting **275**
 - Ethernet adapters for **282**
 - name change **274**
 - network **271**
 - new **272**
 - no clone template **221**
 - opening **273**
 - overview **271**
 - power off **279**
 - powering on **279**
 - removing virtual machine from **277**
 - resume **279**

- snapshot **283**
- suspend **279**
- Telnet **318**
- template mode for clones **221**
- 3D support **173**
- time, synchronizing, between guest and host **120**
- time.synchronize options for VMware Tools **121**
- token ring **289**
- toolbar
 - customizing **61, 62**
 - hide **369**
- Tools panel in the virtual machine settings editor **117**
- Tools upgrade options **115**
- troubleshooting
 - responding to ACE hot fix requests **481**
 - with vmware-acetool **479**
- Turion 64 processor **37**
- two-way virtual SMP **366**

U

- UHCI controller **31**
- uninstalling
 - an ACE instance from a Linux host **473**
 - an ACE instance from a Windows host **468**
 - host virtual adapters **301**
 - VMware Tools **118**
 - Workstation on Linux host **47**
 - Workstation on Windows host **44**
- Unity mode **158**
- update frequency **421**
- updates, checking for Workstation **65**
- updating VMware Tools **117**

- upgrade
 - ACE instances **473**
 - guest operating systems **94**
 - on Linux host **51**
 - on Windows host **48**
 - on Windows Vista host **49**
 - removing snapshots before virtual machine upgrades **47**
 - virtual machines **94, 95**
 - VMware Tools **115, 117**

USB

- connecting devices **353**
- control of devices by host and guest **356**
- controller, enabling and disabling **352**
- device policies, ACE **411, 412**
- devices in a virtual machine **351**
- disconnecting devices **357**
- keyboard and mouse **351**
- on a Linux host **356**
- on a Windows host **355**
- port specifications **31**
- supported device types **351**

user interface

- overview **54**
- restricted **369**

UUID (universal unique identifier)

- and clones **219**
- location **217**
- options for when you move a virtual machine **218**
- specifying **218**

V

- VAssert API **185**
- version, changing virtual machine **94**
- VGA **171**

virtual adapters

- host virtual adapters **301**
- specifications for **32**

virtual appliances

- open virtual machine format (OVF) **137**

virtual disk

- See also* disk
- adding to virtual machine **242, 243**
- allocating disk space **88**
- compacting **240**
- defined **236**
- defragmenting **239**
- expanding **240**
- IDE, size **30**
- legacy **254**
- mapping, to a Windows drive **198, 199**
- setting up as IDE or SCSI **237**
- shrinking **123, 240**
- shrinking in Netware **123**
- size **30**
- storing on physical disks **237**
- using in a new virtual machine **82**
- Virtual Disk Manager **254**
- .vmdk file **97**

Virtual Disk Manager **254**

virtual hardware

- CPU issues **143**
- disk device issues **143**
- Ethernet adapter issues **143**
- graphics card issues **143**

virtual keyboard **339**

virtual machine

- adding a virtual disk **242, 243**
- adding floppy drive **252**
- adding or modifying an Ethernet adapter **295**
- adding physical disk **244**

adding to team **276**

and SMP **366**

cloning from team **283**

constituent files **97**

conversion **133**

creating **79, 133**

creating a clone **221**

default location of **83**

delete **158**

encrypting **155**

files **150**

IDE drives in **30**

installing software in **179**

migrating **226**

moving **217, 223**

moving SMP virtual machines **367**

name change **65**

pausing **154**

platform specifications **29**

portability **236**

power off vs. shut down **152**

removing from Favorites list **64**

removing from team **277**

reset vs. restart **152**

resuming **201**

running in the background **71, 264**

settings **69**

shutting down **151**

starting **148**

starting in full screen mode **377**

suspending **201**

upgrade or downgrade **94**

upgrading procedure **95**

using snapshots **203**

Virtual Machine Communication Interface (VMCI) **102**

virtual machine settings editor

restricting access **369**

VMware Tools panel **117**

- Virtual PC, importing **135**
- virtual printer feature **180**
- virtual printer policy, ACE **414**
- virtual SMP **366, 367**
- virtual switch **285**
- virtual symmetric multiprocessing
 - See virtual SMP
- Visual Studio
 - installing the Workstation plug-in for **41**
- VIX API **185**
- VM streaming **149, 230**
- .vmc file, importing **135**
- VMCI Sockets interface **185**
- .vmdk file **97**
- .vmem file **97**
- VMI (Virtual Machine Interface) enabled kernels **93**
- VMnet1 **312**
- VMnet8 **317**
- .vmsd file **97**
- .vmsn file **97**
- .vmss file **97**
- .vmtm file **97**
- vmtoolsd program **102, 126, 130, 132**
- VMware ACE, key features of **382**
- vmware command for VM streaming **149, 230**
- vmware command-line program **485**
- VMware Converter **133, 135**
- VMware Player
 - installing on a Linux host **469**
 - quitting ACE **479**
 - running **232**
 - sharing virtual machines with **231**
 - starting ACE **474**
- VMware Tools
 - About tab **123**
 - automated install **106**
 - command-line interface **132**
 - configuring **119**
 - configuring in a Netware virtual machine **123**
 - control panel **119**
 - device drivers **102**
 - Devices tab **122**
 - for FreeBSD guests **112**
 - for NetWare guests **113**
 - for Solaris guests **111**
 - installing from the command line with the RPM installer **109**
 - installing from the command line with the tar installer **109**
 - installing on Windows guests **104**
 - modifying installation **118**
 - Options tab **120**
 - running scripts during power state changes **125**
 - Scripts tab **122**
 - Shrink tab **123**
 - silent install **106**
 - taskbar icon, displaying **120**
 - uninstalling **118**
 - updating **115, 117**
 - using from command line **123**
 - VMware user process **103**
 - vmwtool commands **123**
- VMware Tools service
 - executing commands on halt or reboot **128**
 - overview of **102**
 - passing strings from the host **129**
- VMware user process, in VMware Tools **103**
- vmware-user, starting manually **114**
- vmware-acetool, using **479**
- vmware-fullscreen log file **379**
- vmwtool program **123**
- .vmx file **97**

.vmxf file 97

VNC

- setting a keyboard map for **341**
- setting a virtual machine to act as a VNC server **228**

VProbes 185

v-scan code

- defined **344**
- table of codes **347**

W

.wav file 175

Windows

- 32-bit guest operating systems **33**
- 64-bit guest operating systems **34**
- uninstalling on Windows host **44**
- upgrading on Windows host **48**
- upgrading to Windows Vista **49**
- VMware Tools for **104**

Windows 95 sound driver 176

Windows 98 sound driver 176

Windows NT

- SCSI driver for guest **362**
- sound driver **176**

Windows Server 2003

- SCSI driver for guest **362**

Windows XP

- SCSI driver for guest **362**

Windows XP Mode 145

wizard

- Add Hardware **332, 363**
- Add Shared Folder **191**
- Change Version **94**
- Clone Virtual Machine **222**
- Conversion **133**
- New Package **449**
- New Team **272**
- New Virtual Machine **66, 80, 89**

Workspace tab in preferences editor 67

workspaces

- location of **67**
- switching in Linux guest **340**

Workstation

- checking for updates for **65**
- starting **53**

X

X server and keyboard mapping 342

X toolkit options 486

xFree86 and keyboard mapping 342

Z

zip drives 357